

QuTiP: Quantum Toolbox in Python Release 4.4.0

P.D. Nation, J.R. Johansson, A.J.G. Pitchford, C. Granade, A.L. O

Jul 02, 2019


Contents

1	1 Frontmatter				
	1.1	About This Documentation			
	1.2	Citing This Project			
	1.3	Funding			
	1.4	About QuTiP			
	1.5	Contributing to QuTiP			
		•			
2		Ilation 7			
	2.1	General Requirements			
	2.2	Platform-independent Installation			
		2.2.1 Building your Conda environment			
		2.2.2 Adding the conda-forge channel			
	2.3	Installing via pip			
	2.4	Installing from Source			
	2.5	Installation on MS Windows			
		2.5.1 Windows and Python 2.7			
	2.6	Verifying the Installation			
	2.7	Checking Version Information using the About Function			
•					
3		s Guide			
	3.1	Guide Overview 11 2.1.1 Operation			
	2.0	3.1.1 Organization 11 Basic Operations on Quantum Objects 12			
	3.2	1 5			
		1 5			
	2.2	3.2.3 Functions operating on Qobj class			
	3.3	Manipulating States and Operators 21			
		3.3.1 Introduction 21 2.2.2 State Vectors (bets as here) 21			
		3.3.2 State Vectors (kets or bras)			
		3.3.3 Density matrices			
		3.3.4 Qubit (two-level) systems			
		3.3.5 Expectation values			
		3.3.6 Superoperators and Vectorized Operators			
		3.3.7 Choi, Kraus, Stinespring and χ Representations			
	2.4	3.3.8 Properties of Quantum Maps			
	3.4	Using Tensor Products and Partial Traces			
		3.4.1 Tensor products			
		3.4.2 Example: Constructing composite Hamiltonians			
		3.4.3 Partial trace			
	2.5	3.4.4 Superoperators and Tensor Manipulations			
	3.5	Time Evolution and Quantum System Dynamics			
		3.5.1 Dynamics Simulation Results			
		3.5.2 Lindblad Master Equation Solver			
		3.5.3 Monte Carlo Solver			
		3.5.4 Stochastic Solver - Photocurrent			
		3.5.5 Stochastic Solver			
		3.5.6 Solving Problems with Time-dependent Hamiltonians 61			

		3.5.7	Bloch-Redfield master equation
		3.5.8	Floquet Formalism
		3.5.9	Permutational Invariance
		3.5.10	Setting Options for the Dynamics Solvers
	3.6		for Steady-State Solutions
	5.0	3.6.1	Introduction
		3.6.2	Steady State solvers in QuTiP
		3.6.3	Using the Steadystate Solver
		3.6.4	
	27	3.6.5	
	3.7		rview of the Eseries Class
		3.7.1	Exponential-series representation of time-dependent quantum objects
	2.0	3.7.2	Applications of exponential series
	3.8		ne correlation functions
		3.8.1	Steadystate correlation function
		3.8.2	Emission spectrum
		3.8.3	Non-steadystate correlation function
	3.9		m Optimal Control
		3.9.1	Introduction
		3.9.2	Closed Quantum Systems
		3.9.3	The GRAPE algorithm
		3.9.4	The CRAB Algorithm
		3.9.5	Optimal Quantum Control in QuTiP
		3.9.6	Using the pulseoptim functions
	3.10	Plotting	on the Bloch Sphere
		3.10.1	Introduction
		3.10.2	The Bloch and Bloch3d Classes
		3.10.3	Configuring the Bloch sphere
		3.10.4	Animating with the Bloch sphere
	3.11	Visualiz	zation of quantum states and processes
		3.11.1	Fock-basis probability distribution
		3.11.2	Quasi-probability distributions
		3.11.3	Visualizing operators
		3.11.4	Quantum process tomography
	3.12	Parallel	computation
		3.12.1	Parallel map and parallel for-loop
		3.12.2	IPython-based parallel_map
	3.13		QuTiP Objects and Data Sets
		3.13.1	Storing and loading QuTiP objects
		3.13.2	Storing and loading datasets
	3.14	Generat	ing Random Quantum States & Operators
		3.14.1	Random objects with a given eigen spectrum
		3.14.2	Composite random objects
	3.15		ing Internal QuTiP Settings
		3.15.1	User Accessible Parameters
		3.15.2	Example: Changing Settings
		3.15.3	Persistent Settings
4	API o	locumen	itation 141
	4.1	Classes	
		4.1.1	Qobj
		4.1.2	QobjEvo
		4.1.3	eseries
		4.1.4	Bloch sphere
		4.1.5	Cubic Spline
		4.1.6	Non-Markovian Solvers
		4.1.7	Solver Options and Results
		4.1.8	Permutational Invariance

		4.1.9	Distribution functions
		4.1.10	Quantum information processing
		4.1.11	Optimal control
	4.2	Function	ns
		4.2.1	Manipulation and Creation of States and Operators
		4.2.2	Functions acting on states and operators
		4.2.3	Dynamics and Time-Evolution
		4.2.4	Visualization
		4.2.5	Quantum Information Processing
		4.2.6	Non-Markovian Solvers
		4.2.7	Optimal control
		4.2.8	Utility Functions
		1.2.0	
5	Chan	ge Log	291
	5.1		4.4.0 (July 03, 2019)
		5.1.1	Bug Fixes
	5.2	Version	4.3.0 (July 14, 2018)
		5.2.1	Improvements
		5.2.2	Bug Fixes
	5.3		4.2.0 (July 28, 2017)
	5.5	5.3.1	Improvements
		5.3.2	Bug Fixes
	5.4		4.1.0 (March 10, 2017)
	5.4	5.4.1	Improvements
		5.4.1	Bug Fixes
	5.5		4.0.2 (January 5, 2017)
	5 (5.5.1	Bug Fixes
	5.6		4.0.0 (December 22, 2016)
		5.6.1	Improvements
		5.6.2	Bug Fixes
	5.7		3.2.0 (Never officially released)
		5.7.1	New Features
		5.7.2	Improvements
		5.7.3	Bug Fixes
	5.8		3.1.0 (January 1, 2015):
		5.8.1	New Features
		5.8.2	Bug Fixes
	5.9	Version	3.0.1 (Aug 5, 2014):
		5.9.1	Bug Fixes
	5.10	Version	3.0.0 (July 17, 2014):
		5.10.1	New Features
		5.10.2	Improvements
	5.11	Version	2.2.0 (March 01, 2013):
		5.11.1	New Features
		5.11.2	Bug Fixes:
	5.12	Version	2.1.0 (October 05, 2012):
		5.12.1	New Features
		5.12.2	Bug Fixes:
	5.13	Version	2.0.0 (June 01, 2012):
		5.13.1	New Features
	5.14	Version	1.1.4 (May 28, 2012):
		5.14.1	Bug Fixes:
	5.15		1.1.3 (November 21, 2011): 301
	2.10	5.15.1	New Functions:
		5.15.2	Bug Fixes:
	5.16		1.1.2 (October 27, 2011) 302
	5.10	5.16.1	Bug Fixes
	5.17		1.1.1 (October 25, 2011) 302
	5.17	10131011	$1111 (00000125, 2011) \dots $

		5.17.1 New Functions		302		
		5.17.2 Bug Fixes		302		
	5.18	Version 1.1.0 (October 04, 2011)		302		
		5.18.1 New Functions		302		
		5.18.2 Bug Fixes		303		
	5.19	Version 1.0.0 (July 29, 2011)	• • • •	303		
6	Deve	lopers		305		
	6.1	Lead Developers		305		
	6.2	Contributors				
7	Bibli	ography		307		
8	Indices and tables 30					
Bił	311 311					
Py	Python Module Index 313					
Inc	lex			315		



Chapter 1

Frontmatter

1.1 About This Documentation

This document contains a user guide and automatically generated API documentation for QuTiP. A PDF version of this text is available at the documentation page.

For more information see the QuTiP project web page.

Author P.D. Nation
Author Alexander Pitchford
Author Arne Grimsmo
Author J.R. Johansson
Author Chris Grenade
Author P.D. Nation
Author Nathan Shammah
Author Shahnawaz Ahmed
Author Neill Lambert
Author Eric Giguere
version 4.4
status Released (July 18, 2018)
copyright This documentation is licensed under the Creative Commons Attribution 3.0 Unported License.

1.2 Citing This Project

If you find this project useful, then please cite:

J. R. Johansson, P.D. Nation, and F. Nori, "QuTiP 2: A Python framework for the dynamics of open quantum systems", Comp. Phys. Comm. **184**, 1234 (2013).

or

J. R. Johansson, P.D. Nation, and F. Nori, "QuTiP: An open-source Python framework for the dynamics of open quantum systems", Comp. Phys. Comm. **183**, 1760 (2012).

which may also be download from http://arxiv.org/abs/1211.6518 or http://arxiv.org/abs/1110.0573, respectively.

1.3 Funding

QuTiP is developed under the auspice of the non-profit organization:



QuTiP was partially supported by



1.4 About QuTiP

Every quantum system encountered in the real world is an open quantum system. For although much care is taken experimentally to eliminate the unwanted influence of external interactions, there remains, if ever so slight, a coupling between the system of interest and the external world. In addition, any measurement performed on the system necessarily involves coupling to the measuring device, therefore introducing an additional source of external influence. Consequently, developing the necessary tools, both theoretical and numerical, to account for the interactions between a system and its environment is an essential step in understanding the dynamics of practical quantum systems.

In general, for all but the most basic of Hamiltonians, an analytical description of the system dynamics is not possible, and one must resort to numerical simulations of the equations of motion. In absence of a quantum computer, these simulations must be carried out using classical computing techniques, where the exponentially increasing dimensionality of the underlying Hilbert space severely limits the size of system that can be efficiently simulated. However, in many fields such as quantum optics, trapped ions, superconducting circuit devices, and most recently nanomechanical systems, it is possible to design systems using a small number of effective oscillator and spin components, excited by a limited number of quanta, that are amenable to classical simulation in a truncated Hilbert space.

The Quantum Toolbox in Python, or QuTiP, is an open-source framework written in the Python programming language, designed for simulating the open quantum dynamics of systems such as those listed above. This framework distinguishes itself from other available software solutions in providing the following advantages:

- QuTiP relies entirely on open-source software. You are free to modify and use it as you wish with no licensing fees or limitations.
- QuTiP is based on the Python scripting language, providing easy to read, fast code generation without the need to compile after modification.
- The numerics underlying QuTiP are time-tested algorithms that run at C-code speeds, thanks to the Numpy, Scipy, and Cython libraries, and are based on many of the same algorithms used in propriety software.
- QuTiP allows for solving the dynamics of Hamiltonians with (almost) arbitrary time-dependence, including collapse operators.
- Time-dependent problems can be automatically compiled into C++-code at run-time for increased performance.
- Takes advantage of the multiple processing cores found in essentially all modern computers.
- QuTiP was designed from the start to require a minimal learning curve for those users who have experience using the popular quantum optics toolbox by Sze M. Tan.
- Includes the ability to create high-quality plots, and animations, using the excellent Matplotlib package.

For detailed information about new features of each release of QuTiP, see the Change Log.

1.5 Contributing to QuTiP

We welcome anyone who is interested in helping us make QuTiP the best package for simulating quantum systems. Anyone who contributes will be duly recognized. Even small contributions are noted. See *Contributors* for a list of people who have helped in one way or another. If you are interested, please drop us a line at the QuTiP discussion group webpage.

Chapter 2

Installation

2.1 General Requirements

QuTiP depends on several open-source libraries for scientific computing in the Python programming language. The following packages are currently required:

Package	Version	Details
Python	2.7+	Version 3.5+ is highly recommended.
NumPy	1.8+	Not tested on lower versions.
SciPy	0.15+	Lower versions have missing features.
Matplotlib	1.2.1+	Some plotting does not work on lower versions.
Cython	0.21+	Needed for compiling some time-dependent Hamiltonians.
C++ Compiler	GCC 4.7+, MS VS 2015	Needed for compiling Cython files.
Python Headers	2.7+	Linux only. Needed for compiling Cython files.

In addition, there are several optional packages that provide additional functionality:

Package	Version	Details
LaTeX	TexLive 2009+	Needed if using LaTeX in matplotlib figures.
nose	1.1.2+	For running the test suite.

We would not recommend installation into the system Python on Linux platforms, as it is likely that the required libraries will be difficult to update to sufficiently recent versions. The system Python on Linux is used for system things, changing its configuration could lead to highly undesirable results. We are recommending and supporting Anaconda / Miniconda Python environments for QuTiP on all platformsx [It is also possible to install the Intel Python Distribution via the conda installer in Anaconda].

2.2 Platform-independent Installation

QuTiP is designed to work best when using the Anaconda or Intel Python distributions that support the conda package management system.

If you aleady have your conda environment set up, and have the conda-forge channel available, then you can install QuTiP using:

conda install qutip

Otherwise refer to building-conda-environment

If you are using MS Windows, then you will probably want to refer to installation-on-MS-Windows

2.2.1 Building your Conda environment

Important: There are no working conda-forge packages for Python 2.7 on Windows. On Windows you should create a Python 3.5+ environment.

The default Anaconda environment has all the Python packages needed for running QuTiP. You may however wish to install QuTiP in a Conda environment (env) other than the default Anaconda environment. You may wish to install Miniconda instead if you need to be economical with disk space. However, if you are not familiar with conda environments and only plan to use if for QuTiP, then you should probably work with a default Anaconda / Miniconda environment.

To create a Conda env for QuTiP called qutip-env:

```
conda create -n qutip-env python=3
```

Note the python=3 can be ommitted if you want the default Python version for the Anaconda / Miniconda install.

If you have created a specific conda environment, or you have installed Miniconda, then you will need to install the required packages for QuTiP.

recommended:

conda install numpy scipy cython matplotlib nose jupyter notebook spyder

minimum (recommended):

conda install numpy scipy cython nose matplotlib

absolute mimimum:

conda install numpy scipy cython

The jupyter and notebook packages are for working with Jupyter notebooks (fka IPython notebooks). Spyder is an IDE for scientific development with Python.

2.2.2 Adding the conda-forge channel

If you have conda 4.1.0 or later then, add the conda-forge channel with lowest priority using:

conda config --append channels conda-forge

Otherwise you should consider reinstalling Anaconda / Miniconda. In theory:

conda update conda

will update your conda to the latest version, but this can lead to breaking your default Ananconda environment.

Alternatively, this will add conda-forge as the highest priority channel.

conda config --add channels conda-forge

It is almost certainly better to have defaults as the highest priority channel. You can edit your .condarc (user home folder) file manually, so that conda-forge is below defaults in the channels list.

2.3 Installing via pip

For other types of installation, it is often easiest to use the Python package manager pip.

pip install qutip

More detailed platform-dependent installation alternatives are given below.

2.4 Installing from Source

Official releases of QuTiP are available from the download section on the project's web pages

http://www.qutip.org/download.html

and the latest source code is available in our Github repository

```
http://github.com/qutip
```

In general we recommend users to use the latest stable release of QuTiP, but if you are interested in helping us out with development or wish to submit bug fixes, then use the latest development version from the Github repository.

Installing QuTiP from source requires that all the dependencies are satisfied. To install QuTiP from the source code run:

python setup.py install

To install OPENMP support, if available, run:

python setup.py install --with-openmp

If you are wishing to contribute to the QuTiP project, then you will want to create your own fork of qutip, clone this to a local folder, and 'install' it into your Python env using:

python setup.py develop --with-openmp

import qutip in this Python env will then load the code from your local fork, enabling you to test changes interactively.

The sudo pre-command is typically not needed when installing into Anaconda type environments, as Anaconda is usually installed in the users home directory. sudo will be needed (on Linux and OSX) for installing into Python environments where the user does not have write access.

2.5 Installation on MS Windows

Important: Installation on Windows has changed substantially as of QuTiP 4.1. The only supported installation configuration is using the Conda environment with Python 3.5+ and Visual Studio 2015.

We are recommending and supporting installation of QuTiP into a Conda environment. Other scientific Python implementations such as Python-xy may also work, but are not supported.

As of QuTiP 4.1, recommended installation on Windows requires Python 3.5+, as well as Visual Studio 2015. With this configuration, one can install QuTiP using any of the above mentioned receipes. Visual Studio 2015 is not required for the install of the conda-forge package, but it is required at runtime for the string format time-dependence solvers. When installing Visual Studio 2015 be sure to select options for the C++ compiler.

The 'Community' edition of Visual Studio 2015 is free to download use, however it does require approx 10GB of disk space, much of which does have to be on the system drive. If this is not feasible, then it is possible to run QuTiP under Python 2.7.

2.5.1 Windows and Python 2.7

Important: Running QuTiP under Python 2.7 on Windows is not recommended or supported. However, it is currently possible. There are no working conda-forge packages for Python 2.7 on Windows. You will have to install via pip or from source in Python 2.7 on Windows. The 'MS Visual C for Python 2.7' compiler will not work with QuTiP. You will have to use the g++ compiler in mingw32.

If you need to create a Python 2.7 conda environment see *building-conda-environment*, including *adding-conda-forge*

Then run:

conda install mingwpy

To specify the use of the mingw compiler you will need to create the following file:

```
<path to my Python env>/Lib/distutils/distutils.cfg
```

with the following contents:

```
[build]
compiler=mingw32
[build_ext]
compiler=mingw32
```

<path to my Python env> will be something like C:\Ananconda2\ or C:\Ananconda2\envs\qutip-env\ depending on where you installed Anaconda or Miniconda, and whether you created a specific environment.

You can then install QuTiP using either the *install-via_pip* or *install-get-it* method.

2.6 Verifying the Installation

QuTiP includes a collection of built-in test scripts to verify that an installation was successful. To run the suite of tests scripts you must have the nose testing library. After installing QuTiP, leave the installation directory, run Python (or iPython), and call:

import qutip.testing as qt
qt.run()

If successful, these tests indicate that all of the QuTiP functions are working properly. If any errors occur, please check that you have installed all of the required modules. See the next section on how to check the installed versions of the QuTiP dependencies. If these tests still fail, then head on over to the QuTiP Discussion Board and post a message detailing your particular issue.

2.7 Checking Version Information using the About Function

QuTiP includes an "about" function for viewing information about QuTiP and the important dependencies installed on your system. To view this information:

```
In [1]: from qutip import *
In [2]: about()
```

Chapter 3


Users Guide

3.1 Guide Overview

The goal of this guide is to introduce you to the basic structures and functions that make up QuTiP. This guide is divided up into several sections, each highlighting a specific set of functionalities. In combination with the examples that can be found on the project web page http://qutip.org/tutorials.html, this guide should provide a more or less complete overview. In addition, the *API documentation* for each function is located at the end of this guide.

3.1.1 Organization

QuTiP is designed to be a general framework for solving quantum mechanics problems such as systems composed of few-level quantum systems and harmonic oscillators. To this end, QuTiP is built from a large (and ever growing) library of functions and classes; from *qutip.states.basis* to *qutip.wigner*. The general organization of QuTiP, highlighting the important API available to the user, is shown in the figure-qutip_org



Tree-diagram of the 361 user accessible functions and classes in QuTiP 4.4. A vector image of the code tree is in qutip_tree.pdf.

3.2 Basic Operations on Quantum Objects

3.2.1 First things first

Warning: Do not run QuTiP from the installation directory.

To load the qutip modules, we must first call the import statement:

In [1]: from qutip import *

that will load all of the user available functions. Often, we also need to import the NumPy and Matplotlib libraries with:

```
In [2]: import numpy as np
In [3]: import matplotlib.pyplot as plt
```

Note that, in the rest of the documentation, functions are written using *qutip.module.function()* notation which links to the corresponding function in the QuTiP API: *Functions*. However, in calling *import* *, we have already loaded all of the QuTiP modules. Therefore, we will only need the function name and not the complete path when calling the function from the interpreter prompt, Python script, or Jupyter notebook.

3.2.2 The quantum object class

Introduction

The key difference between classical and quantum mechanics lies in the use of operators instead of numbers as variables. Moreover, we need to specify state vectors and their properties. Therefore, in computing the dynamics of quantum systems we need a data structure that is capable of encapsulating the properties of a quantum operator and ket/bra vectors. The quantum object class, *qutip.Qobj*, accomplishes this using matrix representation.

To begin, let us create a blank Qobj:

```
In [4]: Qobj()
Out[4]:
Quantum object: dims = [[1], [1]], shape = (1, 1), type = bra
Qobj data =
[[0.]]
```

where we see the blank Qobj object with dimensions, shape, and data. Here the data corresponds to a 1x1dimensional matrix consisting of a single zero entry.

Hint: By convention, Class objects in Python such as Qobj() differ from functions in the use of a beginning capital letter.

We can create a Qobj with a user defined data set by passing a list or array of data into the Qobj:

```
In [5]: Qobj([[1],[2],[3],[4],[5]])
Out[5]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[1.]
 [2.]
 [3.]
 [4.]
 [5.]]
In [6]: x = np.array([[1, 2, 3, 4, 5]])
In [7]: Qobj(x)
Out[7]:
Quantum object: dims = [[1], [5]], shape = (1, 5), type = bra
Qobj data =
[[1. 2. 3. 4. 5.]]
In [8]: r = np.random.rand(4, 4)
In [9]: Qobj(r)
Out[9]:
Quantum object: dims = [[4], [4]], shape = (4, 4), type = oper, isherm = False
Qobj data =
```

[[0.82193622 0.28680567 0.55292196 0.83316048] [0.30297883 0.93693723 0.26247422 0.25713038] [0.90666158 0.23240648 0.68416325 0.64744769] [0.18936817 0.45738617 0.5634729 0.05839005]]

Notice how both the dims and shape change according to the input data. Although dims and shape appear to have the same function, the difference will become quite clear in the section on *tensor products and partial traces*.

Note: If you are running QuTiP from a python script you must use the print function to view the Qobj attributes.

States and operators

Manually specifying the data for each quantum object is inefficient. Even more so when most objects correspond to commonly used types such as the ladder operators of a harmonic oscillator, the Pauli spin operators for a two-level system, or state vectors such as Fock states. Therefore, QuTiP includes predefined objects for a variety of states:

States	Command (#	Inputs
	means optional)	
Fock state ket vector	basis(N,	N = number of levels in Hilbert space, m = level con-
	#m)/fock(N,#m)	taining excitation (0 if no m given)
Fock density matrix (outer	<pre>fock_dm(N, #p)</pre>	same as basis(N,m) / fock(N,m)
product of basis)		
Coherent state	coherent (N,	alpha = complex number (eigenvalue) for requested co-
	alpha)	herent state
Coherent density matrix	coherent_dm(N,	same as coherent(N,alpha)
(outer product)	alpha)	
Thermal density matrix (for	thermal_dm(N,	n = particle number expectation value
n particles)	n)	

and operators:

Operators	Command (#	Inputs
	means optional)	
Charge operator	charge(N,M=-N)	Diagonal operator with entries from M0N.
Commutator	commutator(A,	Kind = 'normal' or 'anti'.
	B, kind)	
Diagonals operator	qdiags(N)	Quantum object created from arrays of diagonals at
		given offsets.
Displacement operator	displace(N,	N=number of levels in Hilbert space, alpha = complex
(Single-mode)	alpha)	displacement amplitude.
Higher spin operators	jmat(j,#s)	j = integer or half-integer representing spin, s = 'x', 'y',
		'z', '+', or '-'
Identity	qeye(N)	N = number of levels in Hilbert space.
Lowering (destruction)	destroy(N)	same as above
operator		
Momentum operator	momentum(N)	same as above
Number operator	num(N)	same as above
Phase operator (Single-	phase(N, phi0)	Single-mode Pegg-Barnett phase operator with ref phase
mode)		phi0.
Position operator	position(N)	same as above
Raising (creation) opera-	create(N)	same as above
tor		
Squeezing operator	squeeze(N, sp)	N=number of levels in Hilbert space, sp = squeezing pa-
(Single-mode)		rameter.
Squeezing operator (Gen-	squeezing(q1,	q1,q2 = Quantum operators (Qobj) sp = squeezing pa-
eralized)	q2, sp)	rameter.
Sigma-X	sigmax()	
Sigma-Y	sigmay()	
Sigma-Z	sigmaz()	
Sigma plus	sigmap()	
Sigma minus	sigmam()	
Tunneling operator	tunneling(N,m)	Tunneling operator with elements of the form $ N><$
		N+m + N+m < N .

As an example, we give the output for a few of these functions:

```
In [10]: basis(5,3)
Out[10]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
[0.]
[0.]
[1.]
[0.]]
In [11]: coherent(5,0.5-0.5j)
\rightarrow
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[ 0.7788017 +0.j
                ]
[ 0.38939142-0.38939142j]
[ 0. -0.27545895j]
[-0.07898617-0.07898617j]
[-0.04314271+0.j
                ]]
In [12]: destroy(4)
```

```
(continued from previous page)
Quantum object: dims = [[4], [4]], shape = (4, 4), type = oper, isherm = False
Qobj data =
[[0.
          1.
                  Ο.
                           0.
                                   ]
                  1.41421356 0.
[0.
          0.
                                   ]
                     1.73205081]
          Ο.
[0.
                  0.
          0.
                  0.
                           Ο.
[0.
                                  ]]
In [13]: sigmaz()
\rightarrow
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[ 1. 0.]
[ 0. -1.]]
In [14]: jmat(5/2.0, '+')
Quantum object: dims = [[6], [6]], shape = (6, 6), type = oper, isherm = False
Qobj data =
[[0.
          2.23606798 0.
                           Ο.
                                    0.
                                             Ο.
                                                     ]
          0.
                  2.82842712 0.
                                    Ο.
[0.
                                             0.
                                                     ]
[0.
          0.
                  Ο.
                           3.
                                    Ο.
                                             Ο.
                                                     ]
[0.
          Ο.
                  0.
                           0.
                                    2.82842712 0.
                                                     ]
[0.
          Ο.
                  Ο.
                           0.
                                    Ο.
                                             2.23606798]
[0.
          Ο.
                  Ο.
                           0.
                                    0.
                                             0.
                                                     ]]
```

Qobj attributes

We have seen that a quantum object has several internal attributes, such as data, dims, and shape. These can be accessed in the following way:

In general, the attributes (properties) of a Qobj object (or any Python class) can be retrieved using the *Q.attribute* notation. In addition to the attributes shown with the print function, the Qobj class also has the following:

Property	At-	Description	
	tribute		
Data	Q.	Matrix representing state or operator	
	data		
Dimen-	Q.	List keeping track of shapes for individual components of a multipartite system (for	
sions	dims	tensor products and partial traces).	
Shape	Q.	Dimensions of underlying data matrix.	
	shape		
is Hermi-	Q.	Is the operator Hermitian or not?	
tian?	isherm		
Туре	Q.	Is object of type 'ket, 'bra', 'oper', or 'super'?	
	type		




Fig. 1: The Qobj Class viewed as a container for the properties need to characterize a quantum operator or state vector.

For the destruction operator above:

The data attribute returns a message stating that the data is a sparse matrix. All Qobj instances store their data as a sparse matrix to save memory. To access the underlying dense matrix one needs to use the *qutip.Qobj.full* function as described below.

Qobj Math

The rules for mathematical operations on Qob j instances are similar to standard matrix arithmetic:

```
In [21]: q = destroy(4)
In [22]: x = sigmax()
In [23]: q + 5
Out[23]:
Quantum object: dims = [[4], [4]], shape = (4, 4), type = oper, isherm = False
Qobj data =
                            0.
[[5.
          1.
                   0.
                                    ]
[0.
          5.
                   1.41421356 0.
                                    1
                   5.
          Ο.
                           1.73205081]
[0.
[0.
          0.
                   0.
                            5.
                                    11
In [24]: x * x
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[1. 0.]
[0. 1.]]
```

```
In [25]: q ** 3
Quantum object: dims = [[4], [4]], shape = (4, 4), type = oper, isherm = False
Qobj data =
[[0.
               Ο.
                      2.449489741
       0.
[0.
       Ο.
               0.
                      Ο.
                           1
[0.
        Ο.
               Ο.
                      Ο.
                            1
[0.
        0.
               0.
                      0.
                            ]]
In [26]: x / np.sqrt(2)
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
        0.70710678]
[[0.
[0.70710678 0.
              11
```

Of course, like matrices, multiplying two objects of incompatible shape throws an error:

```
In [27]: q * x
TypeError
                                            Traceback (most recent call last)
<ipython-input-27-57f05cd0899f> in <module>
----> 1 q * x
~/release/build_doc/lib/python3.7/site-packages/qutip/qobj.py in __mul_ (self, _
\rightarrowother)
    543
    544
                     else:
--> 545
                         raise TypeError("Incompatible Qobj shapes")
    546
    547
                elif isinstance(other, np.ndarray):
TypeError: Incompatible Qobj shapes
```

In addition, the logic operators is equal == and is not equal /= are also supported.

3.2.3 Functions operating on Qobj class

Like attributes, the quantum object class has defined functions (methods) that operate on Qobj class instances. For a general quantum object Q:

Function	Command	Description
Check Her-	Q.check_herm()	Check if quantum object is Hermitian
micity		
Conjugate	Q.conj()	Conjugate of quantum object.
Cosine	Q.cosm()	Cosine of quantum object.
Dagger (ad-	Q.dag()	Returns adjoint (dagger) of object.
joint)		
Diagonal	Q.diag()	Returns the diagonal elements.
Diamond	Q.dnorm()	Returns the diamond norm.
Norm		
Eigenenergies	Q.eigenenergies()	Eigenenergies (values) of operator.
Eigenstates	Q.eigenstates()	Returns eigenvalues and eigenvectors.
Eliminate	Q.	Returns quantum object with states in list inds removed.
States	eliminate_states(inds)	
Exponential	Q.expm()	Matrix exponential of operator.
Extract States	Q.	Qobj with states listed in inds only.
	<pre>extract_states(inds)</pre>	
Full	Q.full()	Returns full (not sparse) array of Q's data.
Groundstate	Q.groundstate()	Eigenval & eigket of Qobj groundstate.
Matrix Ele-	Q.	Matrix element <bralqlket></bralqlket>
ment	<pre>matrix_element(bra,</pre>	
	ket)	
Norm	Q.norm()	Returns L2 norm for states, trace norm for operators.
Overlap	Q.overlap(state)	Overlap between current Qobj and a given state.
Partial Trace	Q.ptrace(sel)	Partial trace returning components selected using 'sel' pa-
		rameter.
Permute	Q.permute(order)	Permutes the tensor structure of a composite object in the
		given order.
Projector	Q.proj()	Form projector operator from given ket or bra vector.
Sine	Q.sinm()	Sine of quantum operator.
Sqrt	Q.sqrtm()	Matrix sqrt of operator.
Tidyup	Q.tidyup()	Removes small elements from Qobj.
Trace	Q.tr()	Returns trace of quantum object.
Transform	Q.transform(inpt)	A basis transformation defined by matrix or list of kets
		'inpt' .
Transpose	Q.trans()	Transpose of quantum object.
Truncate Neg	Q.trunc_neg()	Truncates negative eigenvalues
Unit	Q.unit()	Returns normalized (unit) vector Q/Q.norm().

```
In [28]: basis(5, 3)
Out[28]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
[0.]
[0.]
[1.]
[0.]]
In [29]: basis(5, 3).dag()
 \rightarrow 
Quantum object: dims = [[1], [5]], shape = (1, 5), type = bra
Qobj data =
[[0. 0. 0. 1. 0.]]
In [30]: coherent_dm(5, 1)
```

```
(continued from previous page)
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0.36791117 0.36774407 0.26105441 0.14620658 0.08826704]
[0.36774407 0.36757705 0.26093584 0.14614018 0.08822695]
[0.26105441 0.26093584 0.18523331 0.10374209 0.06263061]
[0.14620658 0.14614018 0.10374209 0.05810197 0.035077 ]
[0.08826704 0.08822695 0.06263061 0.035077
                                 0.0211765 11
In [31]: coherent_dm(5, 1).diag()
→array([0.36791117, 0.36757705, 0.18523331, 0.05810197, 0.0211765 ])
In [32]: coherent_dm(5, 1).full()
array([[0.36791117+0.j, 0.36774407+0.j, 0.26105441+0.j, 0.14620658+0.j,
     0.08826704+0.j],
     [0.36774407+0.j, 0.36757705+0.j, 0.26093584+0.j, 0.14614018+0.j,
     0.08822695+0.j],
     [0.26105441+0.j, 0.26093584+0.j, 0.18523331+0.j, 0.10374209+0.j,
     0.06263061+0.j],
     [0.14620658+0.j, 0.14614018+0.j, 0.10374209+0.j, 0.05810197+0.j,
     0.035077 +0.j],
     [0.08826704+0.j, 0.08822695+0.j, 0.06263061+0.j, 0.035077 +0.j,
     0.0211765 +0.j]])
In [33]: coherent_dm(5, 1).norm()
→1.00000029930193
In [34]: coherent_dm(5, 1).sqrtm()
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = False
Qobj data =
[[0.36791119+0.0000000e+00j 0.36774406+0.0000000e+00j
 0.2610544 +0.0000000e+00j 0.14620658+0.0000000e+00j
 0.08826704+0.00000000e+00j]
[0.36774406+0.0000000e+00j 0.36757705+9.33478344e-11j
 0.26093584+4.30453576e-11j 0.14614018-2.99165502e-10j
 0.08822695-2.06796067e-11j]
[0.2610544 +0.0000000e+00j 0.26093584+4.30453576e-11j
 0.18523332+1.98494461e-11j 0.10374209-1.37953774e-10j
 0.06263061-9.53595840e-12j]
[0.14620658+0.0000000e+00j 0.14614018-2.99165502e-10j
 0.10374209-1.37953774e-10j 0.05810197+9.58779581e-10j
 0.035077 +6.62749700e-11j]
[0.08826704+0.0000000e+00j 0.08822695-2.06796067e-11j
 0.06263061-9.53595840e-12j 0.035077 +6.62749700e-11j
 0.0211765 +4.58121108e-12j]]
In [35]: coherent_dm(5, 1).tr()
⊶1.0
In [36]: (basis(4, 2) + basis(4, 1)).unit()
Quantum object: dims = [[4], [1]], shape = (4, 1), type = ket
```

```
Qobj data =
[[0. ]
[0.70710678]
[0.70710678]
[0. ]]
```

3.3 Manipulating States and Operators

3.3.1 Introduction

In the previous guide section *Basic Operations on Quantum Objects*, we saw how to create states and operators, using the functions built into QuTiP. In this portion of the guide, we will look at performing basic operations with states and operators. For more detailed demonstrations on how to use and manipulate these objects, see the examples on the tutorials web page.

3.3.2 State Vectors (kets or bras)

Here we begin by creating a Fock *qutip.states.basis* vacuum state vector $|0\rangle$ with in a Hilbert space with 5 number states, from 0 to 4:

```
In [1]: vac = basis(5, 0)
In [2]: vac
Out[2]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[1.]
[0.]
[0.]
[0.]
[0.]
[0.]]
```

and then create a lowering operator (\hat{a}) corresponding to 5 number states using the *qutip.operators*. *destroy* function:

```
In [3]: a = destroy(5)
In [4]: a
Out[4]:
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = False
Qobj data =
                         Ο.
                                     0.
                                                 Ο.
[[0.
                                                            ]
             1.
[0.
             0.
                         1.41421356 0.
                                                 0.
                                                            ]
                                     1.73205081 0.
 [0.
             Ο.
                         0.
                                                            ]
 [0.
             Ο.
                         0.
                                     Ο.
                                                 2.
                                                            1
 [0.
             0.
                         0.
                                     0.
                                                 0.
                                                            ]]
```

Now lets apply the destruction operator to our vacuum state vac,

```
In [5]: a * vac
Out[5]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
[0.]
[0.]
[0.]
```

[0.] [0.]]

We see that, as expected, the vacuum is transformed to the zero vector. A more interesting example comes from using the adjoint of the lowering operator, the raising operator \hat{a}^{\dagger} :

```
In [6]: a.dag() * vac
Out[6]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
[1.]
[0.]
[0.]
[0.]
[0.]]
```

The raising operator has in indeed raised the state *vec* from the vacuum to the $|1\rangle$ state. Instead of using the dagger Qobj.dag() method to raise the state, we could have also used the built in *qutip.operators.create* function to make a raising operator:

```
In [7]: c = create(5)
In [8]: c * vac
Out[8]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
[1.]
[0.]
[0.]
[0.]
[0.]]
```

which does the same thing. We can raise the vacuum state more than once by successively apply the raising operator:

```
In [9]: c * c * vac
Out[9]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0. ]
[0. ]
[1.41421356]
[0. ]
[0. ]]
```

or just taking the square of the raising operator $(\hat{a}^{\dagger})^2$:

```
In [10]: c ** 2 * vac
Out[10]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0. ]
[0. ]
[1.41421356]
[0. ]
[0. ]]
```

Applying the raising operator twice gives the expected $\sqrt{n+1}$ dependence. We can use the product of c * a to also apply the number operator to the state vector vac:

```
In [11]: c * a * vac
Out[11]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
[0.]
[0.]
[0.]
[0.]
[0.]]
```

or on the $|1\rangle$ state:

In [12]: c * a * (c * vac)
Out[12]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
[1.]
[0.]
[0.]
[0.]
[0.]]

or the $|2\rangle$ state:

```
In [13]: c * a * (c**2 * vac)
Out[13]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0. ]
[0. ]
[2.82842712]
[0. ]
[0. ]]
```

Notice how in this last example, application of the number operator does not give the expected value n = 2, but rather $2\sqrt{2}$. This is because this last state is not normalized to unity as $c |n\rangle = \sqrt{n+1} |n+1\rangle$. Therefore, we should normalize our vector first:

```
In [14]: c * a * (c**2 * vac).unit()
Out[14]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
[0.]
[2.]
[0.]
[0.]
[0.]]
```

Since we are giving a demonstration of using states and operators, we have done a lot more work than we should have. For example, we do not need to operate on the vacuum state to generate a higher number Fock state. Instead we can use the *qutip.states.basis* (or *qutip.states.fock*) function to directly obtain the required state:

```
In [15]: ket = basis(5, 2)
In [16]: print(ket)
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
[0.]
[0.]
[1.]
```

[0.] [0.]]

Notice how it is automatically normalized. We can also use the built in *qutip.operators.num* operator:

```
In [17]: n = num(5)
In [18]: print(n)
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0. 0. 0. 0. 0.]
[0. 1. 0. 0. 0.]
[0. 0. 2. 0. 0.]
[0. 0. 2. 0. 0.]
[0. 0. 0. 3. 0.]
[0. 0. 0. 0. 4.]]
```

Therefore, instead of c * a * (c ** 2 * vac).unit() we have:

```
In [19]: n * ket
Out[19]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.]
[0.]
[2.]
[0.]
[0.]
[0.]]
```

We can also create superpositions of states:

```
In [20]: ket = (basis(5, 0) + basis(5, 1)).unit()
In [21]: print(ket)
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0.70710678]
[0.70710678]
[0.]
[0.]
[0.]]
```

where we have used the *qutip.Qobj.unit* method to again normalize the state. Operating with the number function again:

```
In [22]: n * ket
Out[22]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[0. ]
[0.70710678]
[0. ]
[0. ]
[0. ]
[0. ]]
```

We can also create coherent states and squeezed states by applying the *qutip.operators.displace* and *qutip.operators.squeeze* functions to the vacuum state:

```
In [23]: vac = basis(5, 0)
In [24]: d = displace(5, 1j)
```

```
In [25]: s = squeeze(5, 0.25 + 0.25j)
In [26]: d * vac
Out[26]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[ 0.60655682+0.j ]
[ 0. +0.60628133j]
[-0.4303874 +0.j ]
[ 0. -0.24104351j]
[ 0.14552147+0.j ]]
```

```
In [27]: d * s * vac
Out[27]:
Quantum object: dims = [[5], [1]], shape = (5, 1), type = ket
Qobj data =
[[ 0.65893786+0.08139381j]
[ 0.10779462+0.51579735j]
[-0.37567217-0.01326853j]
[-0.02688063-0.23828775j]
[ 0.26352814+0.11512178j]]
```

Of course, displacing the vacuum gives a coherent state, which can also be generated using the built in *qutip*. *states.coherent* function.

3.3.3 Density matrices

One of the main purpose of QuTiP is to explore the dynamics of **open** quantum systems, where the most general state of a system is not longer a state vector, but rather a density matrix. Since operations on density matrices operate identically to those of vectors, we will just briefly highlight creating and using these structures.

The simplest density matrix is created by forming the outer-product $\ket{\psi}ra{\psi}$ of a ket vector:

```
In [28]: ket = basis(5, 2)
In [29]: ket * ket.dag()
Out[29]:
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0. 0. 0. 0. 0.]
[0. 0. 0. 0. 0.]
[0. 0. 1. 0. 0.]
[0. 0. 0. 0. 0.]
[0. 0. 0. 0. 0.]
[0. 0. 0. 0. 0.]
```

A similar task can also be accomplished via the <code>qutip.states.fock_dm</code> or <code>qutip.states.ket2dm</code> functions:

```
In [30]: fock_dm(5, 2)
Out[30]:
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0. 0. 0. 0. 0.]
[0. 0. 0. 0. 0.]
[0. 0. 1. 0. 0.]
[0. 0. 0. 0. 0.]
[0. 0. 0. 0. 0.]]
```

```
In [31]: ket2dm(ket)
Out[31]:
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0. 0. 0. 0. 0.]
[0. 0. 0. 0. 0.]
[0. 0. 1. 0. 0.]
[0. 0. 0. 0. 0.]
[0. 0. 0. 0. 0.]
[0. 0. 0. 0. 0.]
```

If we want to create a density matrix with equal classical probability of being found in the $|2\rangle$ or $|4\rangle$ number states we can do the following:

```
In [32]: 0.5 * ket2dm(basis(5, 4)) + 0.5 * ket2dm(basis(5, 2))
Out[32]:
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0. 0. 0. 0. 0. ]
[0. 0. 0. 0. 0. ]
[0. 0. 0.5 0. 0. ]
[0. 0. 0. 0. 0. ]
[0. 0. 0. 0. 0. ]
[0. 0. 0. 0. 0. ]
```

or use $0.5 * \text{fock}_dm(5, 2) + 0.5 * \text{fock}_dm(5, 4)$. There are also several other built-in functions for creating predefined density matrices, for example $qutip.states.coherent_dm$ and $qutip.states.thermal_dm$ which create coherent state and thermal state density matrices, respectively.

```
In [33]: coherent_dm(5, 1.25)
Out[33]:
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0.20980701 0.26141096 0.23509686 0.15572585 0.13390765]
[0.26141096 0.32570738 0.29292109 0.19402805 0.16684347]
[0.23509686 0.29292109 0.26343512 0.17449684 0.1500487 ]
[0.15572585 0.19402805 0.17449684 0.11558499 0.09939079]
[0.13390765 0.16684347 0.1500487 0.09939079 0.0854655 ]]
```

```
In [34]: thermal_dm(5, 1.25)
Out[34]:
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[0.46927974 0.
                       Ο.
                                  Ο.
                                             0.
                                                       ]
           0.26071096 0.
[0.
                                  0.
                                             0.
                                                       ]
            0. 0.14483942 0.
[0.
                                             0.
                                                       ]
                       0.
                                  0.08046635 0.
[0.
            0.
                                                       1
            0.
                       0.
                                             0.0447035311
[0.
                                  0.
```

QuTiP also provides a set of distance metrics for determining how close two density matrix distributions are to each other. Included are the trace distance *qutip.metrics.tracedist*, fidelity *qutip.metrics.fidelity*, Hilbert-Schmidt distance *qutip.metrics.hilbert_dist*, Bures distance *qutip.metrics.bures_dist*, Bures angle *qutip.metrics.bures_angle*, and quantum Hellinger distance qutip.metrics.hellinger_dist.

```
In [35]: x = coherent_dm(5, 1.25)
In [36]: y = coherent_dm(5, 1.25j) # <-- note the 'j'
In [37]: z = thermal_dm(5, 0.125)
In [38]: fidelity(x, x)
Out[38]: 1.00000015469825</pre>
```

We also know that for two pure states, the trace distance (T) and the fidelity (F) are related by $T = \sqrt{1 - F^2}$, while the quantum Hellinger distance (QHE) between two pure states $|\psi\rangle$ and $|\phi\rangle$ is given by $QHE = \sqrt{2 - 2|\langle\psi|\phi\rangle|^2}$.

```
In [41]: tracedist(y, x)
Out[41]: 0.9771565890327389
```

```
In [42]: np.sqrt(1 - fidelity(y, x) ** 2)
Out[42]: 0.9771565710257347
```

For a pure state and a mixed state, $1 - F^2 \leq T$ which can also be verified:

```
In [43]: 1 - fidelity(x, z) ** 2
Out[43]: 0.778289048903402
```

```
In [44]: tracedist(x, z)
Out[44]: 0.8559028328862639
```

3.3.4 Qubit (two-level) systems

Having spent a fair amount of time on basis states that represent harmonic oscillator states, we now move on to qubit, or two-level quantum systems (for example a spin-1/2). To create a state vector corresponding to a qubit system, we use the same *qutip.states.basis*, or *qutip.states.fock*, function with only two levels:

In [45]: spin = basis(2, 0)

Now at this point one may ask how this state is different than that of a harmonic oscillator in the vacuum state truncated to two energy levels?

In [46]: vac = basis(2, 0)

At this stage, there is no difference. This should not be surprising as we called the exact same function twice. The difference between the two comes from the action of the spin operators qutip.operators.sigmax, qutip.operators.sigmay, qutip.operators.sigmaz, qutip.operators.sigmap, and qutip.operators.sigmam on these two-level states. For example, if vac corresponds to the vacuum state of a harmonic oscillator, then, as we have already seen, we can use the raising operator to get the $|1\rangle$ state:

```
In [47]: vac
Out[47]:
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[1.]
[0.]]
```

```
In [48]: c = create(2)
In [49]: c * vac
Out[49]:
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[0.]
[1.]]
```

For a spin system, the operator analogous to the raising operator is the sigma-plus operator *qutip.operators*. *sigmap*. Operating on the spin state gives:

Now we see the difference! The *qutip.operators.sigmap* operator acting on the spin state returns the zero vector. Why is this? To see what happened, let us use the *qutip.operators.sigmaz* operator:

```
In [52]: sigmaz()
Out[52]:
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[ 1. 0.]
[ 0. -1.]]
In [53]: sigmaz() * spin
\hookrightarrow
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[1.]
[0.]]
In [54]: spin2 = basis(2, 1)
In [55]: spin2
Out[55]:
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[0.]
[1.]]
In [56]: sigmaz() * spin2
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[ 0.]
[-1.]]
```

The answer is now apparent. Since the QuTiP *qutip.operators.sigmaz* function uses the standard z-basis representation of the sigma-z spin operator, the spin state corresponds to the $|\uparrow\rangle$ state of a two-level spin system while spin2 gives the $|\downarrow\rangle$ state. Therefore, in our previous example sigmap() * spin, we raised the qubit state out of the truncated two-level Hilbert space resulting in the zero state.

While at first glance this convention might seem somewhat odd, it is in fact quite handy. For one, the spin operators remain in the conventional form. Second, when the spin system is in the $|\uparrow\rangle$ state:

```
In [57]: sigmaz() * spin
Out[57]:
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[1.]
[0.]]
```

the non-zero component is the zeroth-element of the underlying matrix (remember that python uses c-indexing, and matrices start with the zeroth element). The $|\downarrow\rangle$ state therefore has a non-zero entry in the first index position. This corresponds nicely with the quantum information definitions of qubit states, where the excited $|\uparrow\rangle$ state is label as $|0\rangle$, and the $|\downarrow\rangle$ state by $|1\rangle$.

If one wants to create spin operators for higher spin systems, then the *qutip.operators.jmat* function comes in handy.

3.3.5 Expectation values

Some of the most important information about quantum systems comes from calculating the expectation value of operators, both Hermitian and non-Hermitian, as the state or density matrix of the system varies in time. Therefore, in this section we demonstrate the use of the *qutip.expect* function. To begin:

```
In [64]: coh = coherent_dm(5, 1.0j)
In [65]: expect(N, coh)
Out[65]: 0.99705557458066
```

```
In [66]: cat = (basis(5, 4) + 1.0j * basis(5, 3)).unit()
In [67]: expect(c, cat)
Out[67]: 0.999999999999999
```

The *qutip.expect* function also accepts lists or arrays of state vectors or density matrices for the second input:

```
In [68]: states = [(c**k * vac).unit() for k in range(5)] # must normalize
In [69]: expect(N, states)
Out[69]: array([0., 1., 2., 3., 4.])
```

```
In [70]: cat_list = [(basis(5, 4) + x * basis(5, 3)).unit() for x in [0, 1.0j, -1.

→0, -1.0j]]
In [71]: expect(c, cat_list)
Out[71]: array([ 0.+0.j, 0.+1.j, -1.+0.j, 0.-1.j])
```

Notice how in this last example, all of the return values are complex numbers. This is because the *qutip*. *expect* function looks to see whether the operator is Hermitian or not. If the operator is Hermitian, than the

output will always be real. In the case of non-Hermitian operators, the return values may be complex. Therefore, the *qutip.expect* function will return an array of complex values for non-Hermitian operators when the input is a list/array of states or density matrices.

Of course, the *qutip.expect* function works for spin states and operators:

as well as the composite objects discussed in the next section Using Tensor Products and Partial Traces:

3.3.6 Superoperators and Vectorized Operators

In addition to state vectors and density operators, QuTiP allows for representing maps that act linearly on density operators using the Kraus, Liouville supermatrix and Choi matrix formalisms. This support is based on the correspondance between linear operators acting on a Hilbert space, and vectors in two copies of that Hilbert space, vec : $\mathcal{L}(\mathcal{H}) \rightarrow \mathcal{H} \otimes \mathcal{H}$ [Hav03], [Wat13].

This isomorphism is implemented in QuTiP by the <code>operator_to_vector</code> and <code>vector_to_operator</code> functions:

```
In [83]: psi = basis(2, 0)
In [84]: rho = ket2dm(psi)
In [85]: rho
Out[85]:
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[1. 0.]
[0. 0.]]
In [86]: vec_rho = operator_to_vector(rho)
In [87]: vec_rho
Out[87]:
Quantum object: dims = [[[2], [2]], [1]], shape = (4, 1), type = operator-ket
Qobj data =
```

```
[[1.]
[0.]
[0.]
[0.]]
In [88]: rho2 = vector_to_operator(vec_rho)
In [89]: (rho - rho2).norm()
Out[89]: 0.0
```

The type attribute indicates whether a quantum object is a vector corresponding to an operator (operator-ket), or its Hermitian conjugate (operator-bra).

Note that QuTiP uses the *column-stacking* convention for the isomorphism between $\mathcal{L}(\mathcal{H})$ and $\mathcal{H} \otimes \mathcal{H}$:

```
In [90]: import numpy as np
In [91]: A = Qobj(np.arange(4).reshape((2, 2)))
In [92]: A
Out[92]:
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = False
Qobj data =
[[0. 1.]
[2. 3.]]
In [93]: operator_to_vector(A)
Quantum object: dims = [[[2], [2]], [1]], shape = (4, 1), type = operator-ket
Qobj data =
[[0.]
[2.]
[1.]
[3.]]
```

Since $\mathcal{H} \otimes \mathcal{H}$ is a vector space, linear maps on this space can be represented as matrices, often called *super-operators*. Using the *Qobj*, the *spre* and *spost* functions, supermatrices corresponding to left- and right-multiplication respectively can be quickly constructed.

```
In [94]: X = sigmax()
In [95]: S = spre(X) * spost(X.dag()) # Represents conjugation by X.
```

Note that this is done automatically by the to_super function when given type='oper' input.

```
In [96]: S2 = to_super(X)
In [97]: (S - S2).norm()
Out[97]: 0.0
```

Quantum objects representing superoperators are denoted by type='super':

```
In [98]: S
Out[98]:
Quantum object: dims = [[[2], [2]], [[2], [2]], shape = (4, 4), type = super,__
→isherm = True
Qobj data =
[[0. 0. 0. 1.]
[0. 0. 1. 0.]
[0. 1. 0.0]
[1. 0. 0.]]
```


Information about superoperators, such as whether they represent completely positive maps, is exposed through the iscp, istp and iscptp attributes:

In [99]: S.iscp, S.istp, S.iscptp
Out[99]: (True, True, True)

In addition, dynamical generators on this extended space, often called *Liouvillian superoperators*, can be created using the *liouvillian* function. Each of these takes a Hamilonian along with a list of collapse operators, and returns a type="super" object that can be exponentiated to find the superoperator for that evolution.

For qubits, a particularly useful way to visualize superoperators is to plot them in the Pauli basis, such that $S_{\mu,\nu} = \langle\!\langle \sigma_{\mu} | S[\sigma_{\nu}] \rangle\!\rangle$. Because the Pauli basis is Hermitian, $S_{\mu,\nu}$ is a real number for all Hermitian-preserving superoperators S, allowing us to plot the elements of S as a Hinton diagram. In such diagrams, positive elements are indicated by white squares, and negative elements by black squares. The size of each element is indicated by the size of the corresponding square. For instance, let $S[\rho] = \sigma_x \rho \sigma_x^{\dagger}$. Then $S[\sigma_{\mu}] = \sigma_{\mu} \cdot \begin{cases} +1 & \mu = 0, x \\ -1 & \mu = y, z \end{cases}$. We

can quickly see this by noting that the Y and Z elements of the Hinton diagram for S are negative:



3.3.7 Choi, Kraus, Stinespring and χ Representations

In addition to the superoperator representation of quantum maps, QuTiP supports several other useful representations. First, the Choi matrix $J(\Lambda)$ of a quantum map Λ is useful for working with ancilla-assisted process tomography (AAPT), and for reasoning about properties of a map or channel. Up to normalization, the Choi matrix is defined by acting Λ on half of an entangled pair. In the column-stacking convention,

$$J(\Lambda) = (\mathscr{W} \otimes \Lambda)[\mathscr{W}] \langle \mathscr{W} |]$$

In QuTiP, $J(\Lambda)$ can be found by calling the *to_choi* function on a type="super" Qobj.

Qobj data =
[[1. 0. 0. 1.]
[0. 0. 0. 0.]
[0. 0. 0. 0.]
[1. 0. 0. 1.]]

If a Qobj instance is already in the Choi superrep, then calling to_choi does nothing:

```
In [110]: print(to_choi(J))
Quantum object: dims = [[[2], [2]], [[2], [2]], shape = (4, 4), type = super,_
→isherm = True, superrep = choi
Qobj data =
[[0. 0. 0. 0.]
[0. 1. 1. 0.]
[0. 1. 1. 0.]
[0. 0. 0. 0.]]
```

To get back to the superoperator representation, simply use the *to_super* function. As with *to_choi*, *to_super* is idempotent:

```
In [111]: print(to_super(J) - S)
Quantum object: dims = [[[2], [2]], [[2], [2]], shape = (4, 4), type = super,
⇔isherm = True
Qobj data =
[[0. 0. 0. 0.]
[0. 0. 0. 0.]
[0. 0. 0. 0.]
[0. 0. 0. 0.]]
In [112]: print(to_super(S))
→object: dims = [[[2], [2]], [[2]], [2]]], shape = (4, 4), type = super, isherm =_
⇔True
Qobj data =
[[0. 0. 0. 1.]
[0. 0. 1. 0.]
[0. 1. 0. 0.]
[1. 0. 0. 0.]]
```

We can quickly obtain another useful representation from the Choi matrix by taking its eigendecomposition. In particular, let $\{A_i\}$ be a set of operators such that $J(\Lambda) = \sum_i |A_i\rangle\rangle\langle\langle A_i|$. We can write $J(\Lambda)$ in this way for any hermicity-preserving map; that is, for any map Λ such that $J(\Lambda) = J^{\dagger}(\Lambda)$. These operators then form the Kraus representation of Λ . In particular, for any input ρ ,

$$\Lambda(\rho) = \sum_i A_i \rho A_i^{\dagger}$$

Notice using the column-stacking identity that $(C^{T} \otimes A)|B\rangle = |ABC\rangle$, we have that

$$\sum_i (\mathscr{W} \otimes A_i) (\mathscr{W} \otimes A_i)^\dagger | \mathscr{W}
angle \langle \langle \mathscr{W} | = \sum_i |A_i
angle
angle \langle \langle A_i | = J(\Lambda) |
angle$$

The Kraus representation of a hermicity-preserving map can be found in QuTiP using the to_kraus function.

```
In [113]: I, X, Y, Z = qeye(2), sigmax(), sigmay(), sigmaz()
In [114]: S = sum([sprepost(P, P) for P in (I, X, Y, Z)]) / 4
....: print(S)
....:
Quantum object: dims = [[[2], [2]], [[2], [2]]], shape = (4, 4), type = super, _
→isherm = True
Qobj data =
```

```
[[0.5 0. 0. 0.5]
[0. 0. 0. 0. ]
[0. 0. 0. 0. ]
[0.5 0. 0. 0.5]]
In [115]: J = to_choi(S)
  ....: print (J)
  . . . . . :
→object: dims = [[[2], [2]], [[2], [2]]], shape = (4, 4), type = super, isherm =_
→True, superrep = choi
Qobj data =
[[0.5 0. 0. ]
[0. 0.5 0. 0. ]
[0. 0. 0.5 0. ]
[0. 0. 0. 0.5]]
In [116]: print(J.eigenstates()[1])
\rightarrowobject: dims = [[[2], [2]], [1, 1]], shape = (4, 1), type = operator-ket
Qobj data =
[[1.]
[0.]
[0.]
[0.]]
Quantum object: dims = [[[2], [2]], [1, 1]], shape = (4, 1), type = operator-ket
Qobj data =
[[0.]
[1.]
[0.]
[0.]]
Quantum object: dims = [[[2], [2]], [1, 1]], shape = (4, 1), type = operator-ket
Qobj data =
[[0.]
[0.]
[1.]
[0.]]
Quantum object: dims = [[[2], [2]], [1, 1]], shape = (4, 1), type = operator-ket
Qobj data =
[[0.]]
[0.]
[0.]
[1.]]]
In [117]: K = to_kraus(S)
 ....: print (K)
  . . . . . :
\rightarrowobject: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0.70710678 0.
                   1
[0.
          0.
                  ]], Quantum object: dims = [[2], [2]], shape = (2, 2), type
\rightarrow = oper, isherm = False
Qobj data =
          Ο.
[[0.
                   1
[0.70710678 0.
                   ]], Quantum object: dims = [[2], [2]], shape = (2, 2), type_
\rightarrow = oper, isherm = False
Qobj data =
          0.70710678]
[[0.
          0. ]], Quantum object: dims = [[2], [2]], shape = (2, 2), type_
[0.
\rightarrow= oper, isherm = True
                                                           (continues on next page)
```

```
Qobj data =
[[0. 0. ]
[0. 0.70710678]]]
```

As with the other representation conversion functions, *to_kraus* checks the superrep attribute of its input, and chooses an appropriate conversion method. Thus, in the above example, we can also call *to_kraus* on J.

```
In [118]: KJ = to_kraus(J)
  ....: print (KJ)
  . . . . . :
[Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0.70710678 0.
                     1
[0.
           Ο.
                     ]], Quantum object: dims = [[2], [2]], shape = (2, 2), type
\rightarrow = oper, isherm = False
Qobj data =
[[0.
            0.
                      1
[0.70710678 0.
                     ]], Quantum object: dims = [[2], [2]], shape = (2, 2), type...
→= oper, isherm = False
Qobj data =
            0.70710678]
[[0.
[0.
            0. ]], Quantum object: dims = [[2], [2]], shape = (2, 2), type_
\rightarrow= oper, isherm = True
Qobj data =
[[0.
            Ο.
                     1
            0.70710678111
[0.
In [119]: for A, AJ in zip(K, KJ):
            print (A - AJ)
  . . . . . :
   . . . . . :
\rightarrowobject: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 0.]
[0. 0.]]
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 0.]
[0. 0.]]
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 0.]
[0. 0.]]
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 0.]
[0. 0.]]
```

The Stinespring representation is closely related to the Kraus representation, and consists of a pair of operators A and B such that for all operators X acting on \mathcal{H} ,

 $\Lambda(X) = \mathrm{Tr}_2(AXB^{\dagger}),$

where the partial trace is over a new index that corresponds to the index in the Kraus summation. Conversion to Stinespring is handled by the to_stinespring function.

```
In [120]: a = create(2).dag()
In [121]: S_ad = sprepost(a * a.dag(), a * a.dag()) + sprepost(a, a.dag())
....: S = 0.9 * sprepost(I, I) + 0.1 * S_ad
....: print(S)
```

```
. . . . . :
Quantum object: dims = [[[2], [2]], [[2], [2]], shape = (4, 4), type = super,
⇔isherm = False
Qobj data =
[[1. 0. 0. 0.1]
[0. 0.9 0. 0. ]
[0. 0. 0.9 0. ]
[0. 0. 0. 0.9]]
In [122]: A, B = to_stinespring(S)
  ....: print (A)
  ....: print (B)
   . . . . . .
\hookrightarrowobject: dims = [[2, 3], [2]], shape = (6, 2), type = other
Qobj data =
[[-0.98845443 0.
ΓΟ.
            0.31622777]
[ 0.15151842 0.
[ 0.
            -0.93506452]
[ 0.
            0.
                     1
            -0.16016975]]
[ 0.
Quantum object: dims = [[2, 3], [2]], shape = (6, 2), type = other
Qobj data =
[[-0.98845443 0.
                    1
[ 0.
            0.31622777]
[ 0.15151842 0.
                     1
[ 0.
           -0.93506452]
            Ο.
[ 0.
            -0.16016975]]
[ 0.
```

Notice that a new index has been added, such that A and B have dimensions [[2, 3], [2]], with the length-3 index representing the fact that the Choi matrix is rank-3 (alternatively, that the map has three Kraus operators).

```
In [123]: to_kraus(S)
Out[123]:
[Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0.98845443 0.
           0.93506452]],
 [0.
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[-0.15151842 0.
 [ 0.
             0.16016975]],
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 0.]]
 [0. 0.]],
Quantum object: dims = [2], [2], shape = (2, 2), type = oper, isherm = False
Qobj data =
[[0.
            0.31622777]
 [0.
           0.
                   ]]]
In [124]: print(to_choi(S).eigenenergies())
0.04861218 0.1
                            1.851387821
\rightarrow
```

Finally, the last superoperator representation supported by QuTiP is the χ -matrix representation,

$$\Lambda(\rho) = \sum_{\alpha,\beta} \chi_{\alpha,\beta} B_{\alpha} \rho B_{\beta}^{\dagger},$$

where $\{B_{\alpha}\}$ is a basis for the space of matrices acting on \mathcal{H} . In QuTiP, this basis is taken to be the Pauli basis $B_{\alpha} = \sigma_{\alpha}/\sqrt{2}$. Conversion to the χ formalism is handled by the to_chi function.

```
In [125]: chi = to_chi(S)
....: print(chi)
....:
Quantum object: dims = [[[2], [2]], [[2], [2]]], shape = (4, 4), type = super,__
→isherm = True, superrep = chi
Qobj data =
[[3.7+0.j 0.+0.j 0.+0.j 0.1+0.j ]
[0.+0.j 0.1+0.j 0.+0.j ]
[0.+0.j 0.-0.1j 0.1+0.j 0.+0.j ]
[0.+0.j 0.-0.1j 0.1+0.j 0.+0.j ]
[0.1+0.j 0.+0.j 0.+0.j 0.1+0.j ]]
```

One convenient property of the χ matrix is that the average gate fidelity with the identity map can be read off directly from the χ_{00} element:

Here, the factor of 4 comes from the dimension of the underlying Hilbert space \mathcal{H} . As with the superperator and Choi representations, the χ representation is denoted by the superrep, such that to_super, to_choi, to_kraus, to_stinespring and to_chi all convert from the χ representation appropriately.

3.3.8 Properties of Quantum Maps

In addition to converting between the different representations of quantum maps, QuTiP also provides attributes to make it easy to check if a map is completely positive, trace preserving and/or hermicity preserving. Each of these attributes uses superrep to automatically perform any needed conversions.

In particular, a quantum map is said to be positive (but not necessarily completely positive) if it maps all positive operators to positive operators. For instance, the transpose map $\Lambda(\rho) = \rho^{T}$ is a positive map. We run into problems, however, if we tensor Λ with the identity to get a partial transpose map.

```
In [128]: rho = ket2dm(bell_state())
In [129]: rho_out = partial_transpose(rho, [0, 1])
    ....: print(rho_out.eigenenergies())
    ....:
[-0.5 0.5 0.5 0.5]
```

Notice that even though we started with a positive map, we got an operator out with negative eigenvalues. Complete positivity addresses this by requiring that a map returns positive operators for all positive operators, and does so even under tensoring with another map. The Choi matrix is very useful here, as it can be shown that a map is completely positive if and only if its Choi matrix is positive [Wat13]. QuTiP implements this check with the iscp attribute. As an example, notice that the snippet above already calculates the Choi matrix of the transpose map by acting it on half of an entangled pair. We simply need to manually set the dims and superrep attributes to reflect the structure of the underlying Hilbert space and the chosen representation.

```
In [130]: J = rho_out
In [131]: J.dims = [[[2], [2]], [[2], [2]]]
....: J.superrep = 'choi'
....:
In [132]: print(J.iscp)
False
```

This confirms that the transpose map is not completely positive. On the other hand, the transpose map does satisfy a weaker condition, namely that it is hermicity preserving. That is, $\Lambda(\rho) = (\Lambda(\rho))^{\dagger}$ for all ρ such that $\rho = \rho^{\dagger}$. To see this, we note that $(\rho^{T})^{\dagger} = \rho^{*}$, the complex conjugate of ρ . By assumption, $\rho = \rho^{\dagger} = (\rho^{*})^{T}$, though, such that $\Lambda(\rho) = \Lambda(\rho^{\dagger}) = \rho^{*}$. We can confirm this by checking the ishp attribute:

```
In [133]: print(J.ishp)
True
```

Next, we note that the transpose map does preserve the trace of its inputs, such that $Tr(\Lambda[\rho]) = Tr(\rho)$ for all ρ . This can be confirmed by the istp attribute:

```
In [134]: print(J.istp)
False
```

Finally, a map is called a quantum channel if it always maps valid states to valid states. Formally, a map is a channel if it is both completely positive and trace preserving. Thus, QuTiP provides a single attribute to quickly check that this is true.

```
In [135]: print(J.iscptp)
False
In [136]: print(to_super(qeye(2)).iscptp)
\\\\\\True
```

3.4 Using Tensor Products and Partial Traces

3.4.1 Tensor products

To describe the states of multipartite quantum systems - such as two coupled qubits, a qubit coupled to an oscillator, etc. - we need to expand the Hilbert space by taking the tensor product of the state vectors for each of the system components. Similarly, the operators acting on the state vectors in the combined Hilbert space (describing the coupled system) are formed by taking the tensor product of the individual operators.

In QuTiP the function *qutip.tensor.tensor* is used to accomplish this task. This function takes as argument a collection:

```
>>> tensor(op1, op2, op3)
oralist:
>>> tensor([op1, op2, op3])
```

of state vectors *or* operators and returns a composite quantum object for the combined Hilbert space. The function accepts an arbitray number of states or operators as argument. The type returned quantum object is the same as that of the input(s).

For example, the state vector describing two qubits in their ground states is formed by taking the tensor product of the two single-qubit ground state vectors:

```
In [1]: tensor(basis(2, 0), basis(2, 0))
Out[1]:
Quantum object: dims = [[2, 2], [1, 1]], shape = (4, 1), type = ket
Qobj data =
[[1.]
[0.]
[0.]
[0.]
[0.]]
```

or equivalently using the list format:

```
In [2]: tensor([basis(2, 0), basis(2, 0)])
Out[2]:
Quantum object: dims = [[2, 2], [1, 1]], shape = (4, 1), type = ket
Qobj data =
[[1.]
[0.]
[0.]
[0.]
[0.]]
```

This is straightforward to generalize to more qubits by adding more component state vectors in the argument list to the *qutip.tensor.tensor* function, as illustrated in the following example:

```
In [3]: tensor((basis(2, 0) + basis(2, 1)).unit(),
...: (basis(2, 0) + basis(2, 1)).unit(), basis(2, 0))
...:
Out[3]:
Quantum object: dims = [[2, 2, 2], [1, 1, 1]], shape = (8, 1), type = ket
Qobj data =
[[0.5]
[0. ]
[0.5]
[0. ]
[0.5]
[0. ]
[0.5]
[0. ]
[0.5]
[0. ]
```

This state is slightly more complicated, describing two qubits in a superposition between the up and down states, while the third qubit is in its ground state.

To construct operators that act on an extended Hilbert space of a combined system, we similarly pass a list of operators for each component system to the *qutip.tensor.tensor* function. For example, to form the operator that represents the simultaneous action of the σ_x operator on two qubits:

```
In [4]: tensor(sigmax(), sigmax())
Out[4]:
Quantum object: dims = [[2, 2], [2, 2]], shape = (4, 4), type = oper, isherm = True
Qobj data =
[[0. 0. 0. 1.]
[0. 0. 1. 0.]
[0. 1. 0. 0.]
[1. 0. 0. 0.]]
```

To create operators in a combined Hilbert space that only act only on a single component, we take the tensor product of the operator acting on the subspace of interest, with the identity operators corresponding to the components that are to be unchanged. For example, the operator that represents σ_z on the first qubit in a two-qubit system, while leaving the second qubit unaffected:

```
In [5]: tensor(sigmaz(), identity(2))
Out[5]:
Quantum object: dims = [[2, 2], [2, 2]], shape = (4, 4), type = oper, isherm = True
Qobj data =
[[ 1. 0. 0. 0.]
[ 0. 1. 0. 0.]
[ 0. 0. -1. 0.]
[ 0. 0. -1. 0.]
[ 0. 0. 0. -1.]]
```

3.4.2 Example: Constructing composite Hamiltonians

The *qutip.tensor.tensor* function is extensively used when constructing Hamiltonians for composite systems. Here we'll look at some simple examples.

Two coupled qubits

First, let's consider a system of two coupled qubits. Assume that both qubit has equal energy splitting, and that the qubits are coupled through a $\sigma_x \otimes \sigma_x$ interaction with strength g = 0.05 (in units where the bare qubit energy splitting is unity). The Hamiltonian describing this system is:

```
In [6]: H = tensor(sigmaz(), identity(2)) + tensor(identity(2),
                  sigmaz()) + 0.05 * tensor(sigmax(), sigmax())
   . . . :
   . . . :
In [7]: H
Out[7]:
Quantum object: dims = [[2, 2], [2, 2]], shape = (4, 4), type = oper, isherm = True
Qobj data =
[[ 2.
        0.
               0.
                     0.05]
               0.05 0. ]
 [ 0.
         0.
                     0. 1
         0.05 0.
[ 0.
                    -2. ]]
[ 0.05 0.
               0.
```

Three coupled qubits

The two-qubit example is easily generalized to three coupled qubits:

```
In [8]: H = (tensor(sigmaz(), identity(2), identity(2)) +
            tensor(identity(2), sigmaz(), identity(2)) +
   . . . :
            tensor(identity(2), identity(2), sigmaz()) +
   . . . :
            0.5 * tensor(sigmax(), sigmax(), identity(2)) +
   . . . :
            0.25 * tensor(identity(2), sigmax(), sigmax()))
   . . . :
   . . . :
In [9]: H
Out[9]:
Quantum object: dims = [[2, 2, 2], [2, 2, 2]], shape = (8, 8), type = oper, isherm,
\rightarrow = True
Qobj data =
[[ 3.
               0.
                     0.25 0.
                                  Ο.
                                        0.5
                                               0. ]
        Ο.
                                               0.5 1
               0.25 0.
                            0.
 [ 0.
         1.
                                  Ο.
                                        0.
                                               0. ]
                     Ο.
                            0.5
                                  0.
                                        0.
[ 0.
         0.25 1.
               0.
                    -1.
                                  0.5
[ 0.25 0.
                            Ο.
                                        0.
                                               0. 1
 [ 0.
                            1.
               0.5
                    Ο.
                                  0.
                                        Ο.
                                               0.251
         0.
 [ 0.
         0.
               0.
                     0.5
                            Ο.
                                 -1.
                                        0.25 0. ]
 [ 0.5
         0.
               0.
                     Ο.
                            0.
                                  0.25 -1.
                                               0. ]
         0.5
                            0.25 0.
 [ 0.
               0.
                     0.
                                        0.
                                              -3. ]]
```

A two-level system coupled to a cavity: The Jaynes-Cummings model

The simplest possible quantum mechanical description for light-matter interaction is encapsulated in the Jaynes-Cummings model, which describes the coupling between a two-level atom and a single-mode electromagnetic field (a cavity mode). Denoting the energy splitting of the atom and cavity omega_a and omega_c, respectively, and the atom-cavity interaction strength g, the Jaynes-Cumming Hamiltonian can be constructed as:

```
In [10]: N = 10
In [11]: omega_a = 1.0
In [12]: omega_c = 1.25
In [13]: g = 0.05
```

Here N is the number of Fock states included in the cavity mode.

3.4.3 Partial trace

The partial trace is an operation that reduces the dimension of a Hilbert space by eliminating some degrees of freedom by averaging (tracing). In this sense it is therefore the converse of the tensor product. It is useful when one is interested in only a part of a coupled quantum system. For open quantum systems, this typically involves tracing over the environment leaving only the system of interest. In QuTiP the class method *qutip.Qobj.ptrace* is used to take partial traces. *qutip.Qobj.ptrace* acts on the *qutip.Qobj* instance for which it is called, and it takes one argument sel, which is a list of integers that mark the component systems that should be **kept**. All other components are traced out.

For example, the density matrix describing a single qubit obtained from a coupled two-qubit system is obtained via:

```
In [18]:
         psi = tensor(basis(2, 0), basis(2, 1))
In [19]:
         psi.ptrace(0)
Out[19]:
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[1. 0.]
[0. 0.]]
In [20]:
         psi.ptrace(1)
 \rightarrow 
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 0.]
[0. 1.]]
```

Note that the partial trace always results in a density matrix (mixed state), regardless of whether the composite system is a pure state (described by a state vector) or a mixed state (described by a density matrix):

```
In [21]:
         psi = tensor((basis(2, 0) + basis(2, 1)).unit(), basis(2, 0))
In [22]:
         psi
Out[22]:
Quantum object: dims = [[2, 2], [1, 1]], shape = (4, 1), type = ket
Qobj data =
[[0.70710678]
[0.
        1
[0.70710678]
[0.
         11
In [23]:
        psi.ptrace(0)
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
```

(continues on next page)

(continued from previous page)

```
Qobj data =
[[0.5 0.5]
[0.5 0.5]]
         rho = tensor(ket2dm((basis(2, 0) + basis(2, 1)).unit()), fock_dm(2, 0))
In [24]:
In [25]:
         rho
Out [25]:
Quantum object: dims = [[2, 2], [2, 2]], shape = (4, 4), type = oper, isherm = True
Qobj data =
[[0.5 0. 0.5 0.]
[0. 0. 0. 0. ]
[0.5 0. 0.5 0. ]
[0. 0. 0. 0. ]]
In [26]:
         rho.ptrace(0)
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0.5 0.5]
[0.5 0.5]]
```

3.4.4 Superoperators and Tensor Manipulations

As described in *Superoperators and Vectorized Operators*, *superoperators* are operators that act on Liouville space, the vectorspace of linear operators. Superoperators can be represented using the isomorphism vec : $\mathcal{L}(\mathcal{H}) \rightarrow \mathcal{H} \otimes \mathcal{H}$ [Hav03], [Wat13]. To represent superoperators acting on $\mathcal{L}(\mathcal{H}_1 \otimes \mathcal{H}_2)$ thus takes some tensor rearrangement to get the desired ordering $\mathcal{H}_1 \otimes \mathcal{H}_2 \otimes \mathcal{H}_1 \otimes \mathcal{H}_2$.

In particular, this means that *qutip.tensor* does not act as one might expect on the results of qutip. to_super:

In the former case, the result correctly has four copies of the compound index with dims [2, 3]. In the latter case, however, each of the Hilbert space indices is listed independently and in the wrong order.

The qutip.super_tensor function performs the needed rearrangement, providing the most direct analog to *qutip.tensor* on the underlying Hilbert space. In particular, for any two type="oper" Qobjs A and B, to_super(tensor(A, B)) == super_tensor(to_super(A), to_super(B)) and operator_to_vector(tensor(A, B)) == super_tensor(operator_to_vector(A), operator_to_vector(B)). Returning to the previous example:

```
In [31]: super_tensor(to_super(A), to_super(B)).dims
Out[31]: [[[2, 3], [2, 3]], [[2, 3], [2, 3]]]
```

The qutip.composite function automatically switches between *qutip.tensor* and *qutip.* super_tensor based on the type of its arguments, such that composite (A, B) returns an appropriate Qobj to represent the composition of two systems.

QuTiP also allows more general tensor manipulations that are useful for converting between superoperator representations [WBC11]. In particular, the tensor_contract function allows for contracting one or more pairs of indices. As detailed in the channel contraction tutorial, this can be used to find superoperators that represent partial trace maps. Using this functionality, we can construct some quite exotic maps, such as a map from 3×3 operators to 2×2 operators:

```
In [34]: tensor_contract(composite(to_super(A), to_super(B)), (1, 3), (4, 6)).dims
Out[34]: [[[2], [2]], [[3], [3]]]
```

3.5 Time Evolution and Quantum System Dynamics

3.5.1 Dynamics Simulation Results

Important: In QuTiP 2, the results from all of the dynamics solvers are returned as Odedata objects. This unified and significantly simplified postprocessing of simulation results from different solvers, compared to QuTiP 1. However, this change also results in the loss of backward compatibility with QuTiP version 1.x. In QuTiP 3, the Odedata class has been renamed to Result, but for backwards compatibility an alias between Result and Odedata is provided.

The solver.Result Class

Before embarking on simulating the dynamics of quantum systems, we will first look at the data structure used for returning the simulation results to the user. This object is a *qutip.solver.Result* class that stores all the crucial data needed for analyzing and plotting the results of a simulation. Like the *qutip.Qobj* class, the Result class has a collection of properties for storing information. However, in contrast to the Qobj class, this structure contains no methods, and is therefore nothing but a container object. A generic Result object result contains the following properties for storing simulation data:

Property	Description
result.solver	String indicating which solver was used to generate the data.
result.times	List/array of times at which simulation data is calculated.
result.expect	List/array of expectation values, if requested.
result.states	List/array of state vectors/density matrices calculated at times, if requested.
result.	The number of expectation value operators in the simulation.
num_expect	
result.	The number of collapse operators in the simulation.
num_collapse	
result.ntraj	Number of Monte Carlo trajectories run.
result.	Times at which state collapse occurred. Only for Monte Carlo solver.
col_times	
result.	Which collapse operator was responsible for each collapse in in col_times. Only
col_which	used by Monte Carlo solver.
result.seeds	Seeds used in generating random numbers for Monte Carlo solver.

Accessing Result Data

To understand how to access the data in a Result object we will use an example as a guide, although we do not worry about the simulation details at this stage. Like all solvers, the Monte Carlo solver used in this example returns an Result object, here called simply result. To see what is contained inside result we can use the print function:

```
>>> print(result)
    Result object with mcsolve data.
    ------
    expect = True
    num_expect = 2, num_collapse = 2, ntraj = 500
```

The first line tells us that this data object was generated from the Monte Carlo solver mcsolve (discussed in *Monte Carlo Solver*). The next line (not the --- line of course) indicates that this object contains expectation value data. Finally, the last line gives the number of expectation value and collapse operators used in the simulation, along with the number of Monte Carlo trajectories run. Note that the number of trajectories ntraj is only displayed when using the Monte Carlo solver.

Now we have all the information needed to analyze the simulation results. To access the data for the two expectation values one can do:

```
>>> expt0 = result.expect[0]
>>> expt1 = result.expect[1]
```

Recall that Python uses C-style indexing that begins with zero (i.e., $[0] \Rightarrow 1$ st collapse operator data). Together with the array of times at which these expectation values are calculated:

```
>>> times = result.times
```

we can plot the resulting expectation values:

```
>>> plot(times, expt0, times, expt1)
>>> show()
```

State vectors, or density matrices, as well as col_times and col_which, are accessed in a similar manner, although typically one does not need an index (i.e [0]) since there is only one list for each of these components. The one exception to this rule is if you choose to output state vectors from the Monte Carlo solver, in which case there are ntraj number of state vector arrays.

Saving and Loading Result Objects

The main advantage in using the Result class as a data storage object comes from the simplicity in which simulation data can be stored and later retrieved. The *qutip.fileio.qsave* and *qutip.fileio.qload* functions are designed for this task. To begin, let us save the data object from the previous section into a file called "cavity+qubit-data" in the current working directory by calling:

>>> qsave(result, 'cavity+qubit-data')

All of the data results are then stored in a single file of the same name with a ".qu" extension. Therefore, everything needed to later this data is stored in a single file. Loading the file is just as easy as saving:

where stored_result is the new name of the Result object. We can then extract the data and plot in the same manner as before:

```
expt0 = stored_result.expect[0]
expt1 = stored_result.expect[1]
times = stored_result.times
plot(times, expt0, times, expt1)
show()
```

Also see *Saving QuTiP Objects and Data Sets* for more information on saving quantum objects, as well as arrays for use in other programs.

3.5.2 Lindblad Master Equation Solver

Unitary evolution

The dynamics of a closed (pure) quantum system is governed by the Schrödinger equation

$$i\hbar\frac{\partial}{\partial t}\Psi = \hat{H}\Psi,\tag{3.1}$$

where Ψ is the wave function, \hat{H} the Hamiltonian, and \hbar is Planck's constant. In general, the Schrödinger equation is a partial differential equation (PDE) where both Ψ and \hat{H} are functions of space and time. For computational purposes it is useful to expand the PDE in a set of basis functions that span the Hilbert space of the Hamiltonian, and to write the equation in matrix and vector form

$$i\hbar\frac{d}{dt}\left|\psi\right\rangle =H\left|\psi\right\rangle$$

where $|\psi\rangle$ is the state vector and H is the matrix representation of the Hamiltonian. This matrix equation can, in principle, be solved by diagonalizing the Hamiltonian matrix H. In practice, however, it is difficult to perform this diagonalization unless the size of the Hilbert space (dimension of the matrix H) is small. Analytically, it is a formidable task to calculate the dynamics for systems with more than two states. If, in addition, we consider dissipation due to the inevitable interaction with a surrounding environment, the computational complexity grows even larger, and we have to resort to numerical calculations in all realistic situations. This illustrates the importance of numerical calculations in describing the dynamics of open quantum systems, and the need for efficient and accessible tools for this task.

The Schrödinger equation, which governs the time-evolution of closed quantum systems, is defined by its Hamiltonian and state vector. In the previous section, Using Tensor Products and Partial Traces, we showed how Hamiltonians and state vectors are constructed in QuTiP. Given a Hamiltonian, we can calculate the unitary (non-dissipative) time-evolution of an arbitrary state vector $|\psi_0\rangle$ (psi0) using the QuTiP function qutip.mesolve. It evolves the state vector and evaluates the expectation values for a set of operators expt_ops at the points in time in the list times, using an ordinary differential equation solver. Alternatively, we can use the function qutip.mesolve, which uses the exponential-series technique to calculate the time evolution of a system. The qutip.mesolve and qutip.essolve functions take the same arguments and it is therefore easy switch between the two solvers.


For example, the time evolution of a quantum spin-1/2 system with tunneling rate 0.1 that initially is in the up state is calculated, and the expectation values of the σ_z operator evaluated, with the following code

```
In [1]: H = 2 * np.pi * 0.1 * sigmax()
In [2]: psi0 = basis(2, 0)
In [3]: times = np.linspace(0.0, 10.0, 20)
In [4]: result = sesolve(H, psi0, times, [sigmaz()])
```

The brackets in the fourth argument is an empty list of collapse operators, since we consider unitary evolution in this example. See the next section for examples on how dissipation is included by defining a list of collapse operators. The function returns an instance of *qutip.solver.Result*, as described in the previous section *Dynamics Simulation Results*. The attribute expect in result is a list of expectation values for the operators that are included in the list in the fifth argument. Adding operators to this list results in a larger output list returned by the function (one array of numbers, corresponding to the times in times, for each operator)

The resulting list of expectation values can easily be visualized using matplotlib's plotting functions:

```
In [7]: H = 2 * np.pi * 0.1 * sigmax()
In [8]: psi0 = basis(2, 0)
In [9]: times = np.linspace(0.0, 10.0, 100)
In [10]: result = sesolve(H, psi0, times, [sigmaz(), sigmay()])
In [11]: fig, ax = subplots()
In [12]: ax.plot(result.times, result.expect[0]);
In [13]: ax.plot(result.times, result.expect[1]);
In [14]: ax.set_xlabel('Time');
In [15]: ax.set_ylabel('Expectation values');
In [16]: ax.legend(("Sigma-Z", "Sigma-Y"));
In [17]: show()
```



If an empty list of operators is passed as fifth parameter, the *qutip.mesolve* function returns a *qutip.* solver.Result instance that contains a list of state vectors for the times specified in times

Non-unitary evolution

While the evolution of the state vector in a closed quantum system is deterministic, open quantum systems are stochastic in nature. The effect of an environment on the system of interest is to induce stochastic transitions between energy levels, and to introduce uncertainty in the phase difference between states of the system. The state of an open quantum system is therefore described in terms of ensemble averaged states using the density matrix formalism. A density matrix ρ describes a probability distribution of quantum states $|\psi_n\rangle$, in a matrix representation $\rho = \sum_n p_n |\psi_n\rangle \langle \psi_n|$, where p_n is the classical probability that the system is in the quantum state $|\psi_n\rangle$. The time evolution of a density matrix ρ is the topic of the remaining portions of this section.

The Lindblad Master equation

The standard approach for deriving the equations of motion for a system interacting with its environment is to expand the scope of the system to include the environment. The combined quantum system is then closed, and its evolution is governed by the von Neumann equation

$$\dot{\rho}_{\rm tot}(t) = -\frac{i}{\hbar} [H_{\rm tot}, \rho_{\rm tot}(t)], \qquad (3.2)$$

the equivalent of the Schrödinger equation (3.1) in the density matrix formalism. Here, the total Hamiltonian

$$H_{\rm tot} = H_{\rm sys} + H_{\rm env} + H_{\rm int},$$

includes the original system Hamiltonian H_{sys} , the Hamiltonian for the environment H_{env} , and a term representing the interaction between the system and its environment H_{int} . Since we are only interested in the dynamics of the system, we can at this point perform a partial trace over the environmental degrees of freedom in Eq. (3.2), and thereby obtain a master equation for the motion of the original system density matrix. The most general tracepreserving and completely positive form of this evolution is the Lindblad master equation for the reduced density matrix $\rho = \text{Tr}_{\text{env}}[\rho_{\text{tot}}]$

$$\dot{\rho}(t) = -\frac{i}{\hbar} [H(t), \rho(t)] + \sum_{n} \frac{1}{2} \left[2C_n \rho(t) C_n^+ - \rho(t) C_n^+ C_n - C_n^+ C_n \rho(t) \right]$$
(3.3)

where the $C_n = \sqrt{\gamma_n} A_n$ are collapse operators, and A_n are the operators through which the environment couples to the system in H_{int} , and γ_n are the corresponding rates. The derivation of Eq. (3.3) may be found in several sources, and will not be reproduced here. Instead, we emphasize the approximations that are required to arrive at the master equation in the form of Eq. (3.3) from physical arguments, and hence perform a calculation in QuTiP:

- Separability: At t = 0 there are no correlations between the system and its environment such that the total density matrix can be written as a tensor product $\rho_{tot}^{I}(0) = \rho^{I}(0) \otimes \rho_{env}^{I}(0)$.
- Born approximation: Requires: (1) that the state of the environment does not significantly change as a result of the interaction with the system; (2) The system and the environment remain separable throughout the evolution. These assumptions are justified if the interaction is weak, and if the environment is much larger than the system. In summary, $\rho_{tot}(t) \approx \rho(t) \otimes \rho_{env}$.
- Markov approximation The time-scale of decay for the environment τ_{env} is much shorter than the smallest time-scale of the system dynamics $\tau_{sys} \gg \tau_{env}$. This approximation is often deemed a "short-memory environment" as it requires that environmental correlation functions decay on a time-scale fast compared to those of the system.
- Secular approximation Stipulates that elements in the master equation corresponding to transition frequencies satisfy $|\omega_{ab} \omega_{cd}| \ll 1/\tau_{sys}$, i.e., all fast rotating terms in the interaction picture can be neglected. It also ignores terms that lead to a small renormalization of the system energy levels. This approximation is not strictly necessary for all master-equation formalisms (e.g., the Block-Redfield master equation), but it is required for arriving at the Lindblad form (3.3) which is used in *qutip.mesolve*.


For systems with environments satisfying the conditions outlined above, the Lindblad master equation (3.3) governs the time-evolution of the system density matrix, giving an ensemble average of the system dynamics. In order to ensure that these approximations are not violated, it is important that the decay rates γ_n be smaller than the minimum energy splitting in the system Hamiltonian. Situations that demand special attention therefore include, for example, systems strongly coupled to their environment, and systems with degenerate or nearly degenerate energy levels.

For non-unitary evolution of a quantum systems, i.e., evolution that includes incoherent processes such as relaxation and dephasing, it is common to use master equations. In QuTiP, the same function (*qutip.mesolve*) is used for evolution both according to the Schrödinger equation and to the master equation, even though these two equations of motion are very different. The *qutip.mesolve* function automatically determines if it is sufficient to use the Schrödinger equation (if no collapse operators were given) or if it has to use the master equation (if collapse operators were given). Note that to calculate the time evolution according to the Schrödinger equation is easier and much faster (for large systems) than using the master equation, so if possible the solver will fall back on using the Schrödinger equation.

What is new in the master equation compared to the Schrödinger equation are processes that describe dissipation in the quantum system due to its interaction with an environment. These environmental interactions are defined by the operators through which the system couples to the environment, and rates that describe the strength of the processes.

In QuTiP, the product of the square root of the rate and the operator that describe the dissipation process is called a collapse operator. A list of collapse operators (c_{ops}) is passed as the fourth argument to the *qutip.mesolve* function in order to define the dissipation processes in the master equation. When the c_{ops} isn't empty, the *qutip.mesolve* function will use the master equation instead of the unitary Schrödinger equation.

Using the example with the spin dynamics from the previous section, we can easily add a relaxation process (describing the dissipation of energy from the spin to its environment), by adding np.sqrt(0.05) * sigmax() to the previously empty list in the fourth parameter to the qutip.mesolve function:



Here, 0.05 is the rate and the operator σ_x (*qutip.operators.sigmax*) describes the dissipation process.


Now a slightly more complex example: Consider a two-level atom coupled to a leaky single-mode cavity through a dipole-type interaction, which supports a coherent exchange of quanta between the two systems. If the atom initially is in its groundstate and the cavity in a 5-photon Fock state, the dynamics is calculated with the lines following code

```
In [30]: times = np.linspace(0.0, 10.0, 200)
In [31]: psi0 = tensor(fock(2,0), fock(10, 5))
In [32]: a = tensor(qeye(2), destroy(10))
In [33]: sm = tensor(destroy(2), qeye(10))
```

```
(continued from previous page)
```

```
In [34]: H = 2 * np.pi * a.dag() * a + 2 * np.pi * sm.dag() * sm + \
 ....: 2 * np.pi * 0.25 * (sm * a.dag() + sm.dag() * a)
  . . . . :
In [35]: result = mesolve(H, psi0, times, [np.sqrt(0.1)*a], [a.dag()*a, sm.
→dag()*sm])
In [36]: figure()
Out[36]: <Figure size 640x480 with 0 Axes>
In [37]: plot(times, result.expect[0])
→0x2acc508c9ac8>]
In [38]: plot(times, result.expect[1])

→ [<matplotlib.lines.Line2D at 0x2acc508c9080>]
In [39]: xlabel('Time')
→Text(0.5,0,'Time')
In [40]: ylabel('Expectation values')
→Text(0,0.5,'Expectation values')
In [41]: legend(("cavity photon number", "atom excitation probability"))
↔<matplotlib.legend.Legend at 0x2acc4e9a97b8>
In [42]: show()
```



3.5.3 Monte Carlo Solver

Introduction

Where as the density matrix formalism describes the ensemble average over many identical realizations of a quantum system, the Monte Carlo (MC), or quantum-jump approach to wave function evolution, allows for simulating an individual realization of the system dynamics. Here, the environment is continuously monitored, resulting in a series of quantum jumps in the system wave function, conditioned on the increase in information gained about the state of the system via the environmental measurements. In general, this evolution is governed by the Schrödinger equation with a **non-Hermitian** effective Hamiltonian

$$H_{\rm eff} = H_{\rm sys} - \frac{i\hbar}{2} \sum_{i} C_n^+ C_n, \qquad (3.4)$$

where again, the C_n are collapse operators, each corresponding to a separate irreversible process with rate γ_n . Here, the strictly negative non-Hermitian portion of Eq. (3.4) gives rise to a reduction in the norm of the wave function, that to first-order in a small time δt , is given by $\langle \psi(t + \delta t) | \psi(t + \delta t) \rangle = 1 - \delta p$ where

$$\delta p = \delta t \sum_{n} \left\langle \psi(t) | C_n^+ C_n | \psi(t) \right\rangle, \qquad (3.5)$$

and δt is such that $\delta p \ll 1$. With a probability of remaining in the state $|\psi(t + \delta t)\rangle$ given by $1 - \delta p$, the corresponding quantum jump probability is thus Eq. (3.5). If the environmental measurements register a quantum jump, say via the emission of a photon into the environment, or a change in the spin of a quantum dot, the wave function undergoes a jump into a state defined by projecting $|\psi(t)\rangle$ using the collapse operator C_n corresponding to the measurement

$$|\psi(t+\delta t)\rangle = C_n |\psi(t)\rangle / \langle \psi(t)|C_n^+ C_n |\psi(t)\rangle^{1/2}.$$
(3.6)

If more than a single collapse operator is present in Eq. (3.4), the probability of collapse due to the *i*th-operator C_i is given by

$$P_i(t) = \left\langle \psi(t) | C_i^+ C_i | \psi(t) \right\rangle / \delta p.$$
(3.7)

Evaluating the MC evolution to first-order in time is quite tedious. Instead, QuTiP uses the following algorithm to simulate a single realization of a quantum system. Starting from a pure state $|\psi(0)\rangle$:

- I: Choose a random number r between zero and one, representing the probability that a quantum jump occurs.
- II: Integrate the Schrödinger equation, using the effective Hamiltonian (3.4) until a time τ such that the norm of the wave function satisfies $\langle \psi(\tau) | \psi(\tau) \rangle = r$, at which point a jump occurs.
- III: The resultant jump projects the system at time τ into one of the renormalized states given by Eq. (3.6). The corresponding collapse operator C_n is chosen such that n is the smallest integer satisfying:

$$\sum_{i=1}^{n} P_n(\tau) \ge r \tag{3.8}$$

where the individual P_n are given by Eq. (3.7). Note that the left hand side of Eq. (3.8) is, by definition, normalized to unity.


• IV: Using the renormalized state from step III as the new initial condition at time τ , draw a new random number, and repeat the above procedure until the final simulation time is reached.

Monte Carlo in QuTiP

In QuTiP, Monte Carlo evolution is implemented with the *qutip.mcsolve* function. It takes nearly the same arguments as the *qutip.mesolve* function for master-equation evolution, except that the initial state must be a ket vector, as oppose to a density matrix, and there is an optional keyword parameter ntraj that defines the number of stochastic trajectories to be simulated. By default, ntraj=500 indicating that 500 Monte Carlo trajectories will be performed.

To illustrate the use of the Monte Carlo evolution of quantum systems in QuTiP, let's again consider the case of a two-level atom coupled to a leaky cavity. The only differences to the master-equation treatment is that in this case we invoke the *qutip.mcsolve* function instead of *qutip.mesolve*

```
In [1]: times = np.linspace(0.0, 10.0, 200)
In [2]: psi0 = tensor(fock(2, 0), fock(10, 5))
In [3]: a = tensor(qeye(2), destroy(10))
In [4]: sm = tensor(destroy(2), qeye(10))
In [5]: H = 2 * np.pi * a.dag() * a + 2 * np.pi * sm.dag() * sm + 2 * np.pi * 0.25_
\rightarrow * (sm * a.dag() + sm.dag() * a)
In [6]: data = mcsolve(H, psi0, times, [np.sqrt(0.1) * a], [a.dag() * a, sm.dag()]
→* sm])
10.0%. Run time: 0.92s. Est. time left: 00:00:00:08
20.0%. Run time: 1.67s. Est. time left: 00:00:00:06
30.0%. Run time: 2.41s. Est. time left: 00:00:00:05
40.0%. Run time: 3.16s. Est. time left: 00:00:00:04
50.0%. Run time: 3.92s. Est. time left: 00:00:03
60.0%. Run time:
             4.67s. Est. time left: 00:00:00:03
70.0%. Run time:
             5.48s. Est. time left: 00:00:00:02
80.0%. Run time: 6.21s. Est. time left: 00:00:00:01
90.0%. Run time:
             6.95s. Est. time left: 00:00:00:00
100.0%. Run time:
             7.68s. Est. time left: 00:00:00:00
Total run time: 7.70s
In [7]: figure()
↔<Figure size 640x480 with 0 Axes>
In [8]: plot(times, data.expect[0], times, data.expect[1])
[<matplotlib.lines.Line2D at 0x2acc50d30908>,
<matplotlib.lines.Line2D at 0x2acc50d30048>]
In [9]: title('Monte Carlo time evolution')
→Text(0.5,1,'Monte Carlo time evolution')
In [10]: xlabel('Time')
→Text(0.5,0, 'Time')
In [11]: ylabel('Expectation values')
→Text(0,0.5,'Expectation values')
In [12]: legend(("cavity photon number", "atom excitation probability"))
↔<matplotlib.legend.Legend at 0x2acc508ddcc0>
In [13]: show()
```



The advantage of the Monte Carlo method over the master equation approach is that only the state vector is required to be kept in the computers memory, as opposed to the entire density matrix. For large quantum system this becomes a significant advantage, and the Monte Carlo solver is therefore generally recommended for such systems. For example, simulating a Heisenberg spin-chain consisting of 10 spins with random parameters and initial states takes almost 7 times longer using the master equation rather than Monte Carlo approach with the default number of trajectories running on a quad-CPU machine. Furthermore, it takes about 7 times the memory as well. However, for small systems, the added overhead of averaging a large number of stochastic trajectories to obtain the open system dynamics, as well as starting the multiprocessing functionality, outweighs the benefit of the minor (in this case) memory saving. Master equation methods are therefore generally more efficient when Hilbert space sizes are on the order of a couple of hundred states or smaller.

Like the master equation solver *qutip.mesolve*, the Monte Carlo solver returns a *qutip.solver.Result* object consisting of expectation values, if the user has defined expectation value operators in the 5th argument to mcsolve, or state vectors if no expectation value operators are given. If state vectors are returned, then the *qutip.solver.Result* returned by *qutip.mcsolve* will be an array of length ntraj, with each element containing an array of ket-type qobjs with the same number of elements as times. Furthermore, the output *qutip.solver.Result* object will also contain a list of times at which collapse occurred, and which collapse operators did the collapse, in the col_times and col_which properties, respectively.

Changing the Number of Trajectories

As mentioned earlier, by default, the mcsolve function runs 500 trajectories. This value was chosen because it gives good accuracy, Monte Carlo errors scale as 1/n where n is the number of trajectories, and simultaneously does not take an excessive amount of time to run. However, like many other options in QuTiP you are free to change the number of trajectories to fit your needs. If we want to run 1000 trajectories in the above example, we can simply modify the call to mcsolve like:

```
In [14]: data = mcsolve(H, psi0, times, [np.sqrt(0.1) * a], [a.dag() * a, sm.dag()]

→* sm], ntraj=1000)

10.0%. Run time: 1.71s. Est. time left: 00:00:00:15

20.0%. Run time: 3.23s. Est. time left: 00:00:00:12

30.0%. Run time: 5.00s. Est. time left: 00:00:00:11

40.0%. Run time: 6.67s. Est. time left: 00:00:00:10

50.0%. Run time: 8.25s. Est. time left: 00:00:00:08
```

```
60.0%. Run time: 9.97s. Est. time left: 00:00:00:06
70.0%. Run time: 11.46s. Est. time left: 00:00:00:04
80.0%. Run time: 13.00s. Est. time left: 00:00:00:03
90.0%. Run time: 14.63s. Est. time left: 00:00:00:01
100.0%. Run time: 16.21s. Est. time left: 00:00:00:00
Total run time: 16.30s
```

where we have added the keyword argument ntraj=1000 at the end of the inputs. Now, the Monte Carlo solver will calculate expectation values for both operators, a.dag() * a, sm.dag() * sm averaging over 1000 trajectories. Sometimes one is also interested in seeing how the Monte Carlo trajectories converge to the master equation solution by calculating expectation values over a range of trajectory numbers. If, for example, we want to average over 1, 10, 100, and 1000 trajectories, then we can input this into the solver using:

In [15]: ntraj = [1, 10, 100, 1000]

Keep in mind that the input list must be in ascending order since the total number of trajectories run by mcsolve will be calculated using the last element of ntraj. In this case, we need to use an extra index when getting the expectation values from the *qutip.solver.Result* object returned by mcsolve. In the above example using:

```
In [16]: data = mcsolve(H, psi0, times, [np.sqrt(0.1) * a], [a.dag() * a, sm.dag()]
→* sm], ntraj=[1, 10, 100, 1000])
10.0%. Run time:
                  1.88s. Est. time left: 00:00:00:16
20.0%. Run time:
                  3.45s. Est. time left: 00:00:00:13
30.0%. Run time:
                  4.96s. Est. time left: 00:00:00:11
40.0%. Run time:
                  6.56s. Est. time left: 00:00:00:09
50.0%. Run time: 8.24s. Est. time left: 00:00:00:08
60.0%. Run time: 10.03s. Est. time left: 00:00:00:06
70.0%. Run time: 11.57s. Est. time left: 00:00:00:04
80.0%. Run time: 13.54s. Est. time left: 00:00:00:03
90.0%. Run time: 15.35s. Est. time left: 00:00:00:01
100.0%. Run time: 17.09s. Est. time left: 00:00:00:00
Total run time: 17.16s
```

we can extract the relevant expectation values using:

```
In [17]: expt1 = data.expect[0]
In [18]: expt10 = data.expect[1]
In [19]: expt100 = data.expect[2]
In [20]: expt1000 = data.expect[3]
```

The Monte Carlo solver also has many available options that can be set using the *qutip.solver.Options* class as discussed in *Setting Options for the Dynamics Solvers*.

Reusing Hamiltonian Data

Note: This section covers a specialized topic and may be skipped if you are new to QuTiP.

In order to solve a given simulation as fast as possible, the solvers in QuTiP take the given input operators and break them down into simpler components before passing them on to the ODE solvers. Although these operations are reasonably fast, the time spent organizing data can become appreciable when repeatedly solving a system over, for example, many different initial conditions. In cases such as this, the Hamiltonian and other operators may be reused after the initial configuration, thus speeding up calculations. Note that, unless you are planning to reuse the data many times, this functionality will not be very useful.

To turn on the "reuse" functionality we must set the rhs_reuse=True flag in the qutip.solver.Options:


In [21]: options = Options(rhs_reuse=True)


A full account of this feature is given in *Setting Options for the Dynamics Solvers*. Using the previous example, we will calculate the dynamics for two different initial states, with the Hamiltonian data being reused on the second call

```
In [22]: times = np.linspace(0.0, 10.0, 200)
In [23]: psi0 = tensor(fock(2, 0), fock(10, 5))
In [24]: a = tensor(qeye(2), destroy(10))
In [25]: sm = tensor(destroy(2), qeye(10))
In [26]: H = 2 * np.pi * a.dag() * a + 2 * np.pi * sm.dag() * sm + \
  ....: 2 * np.pi * 0.25 * (sm * a.dag() + sm.dag() * a)
   . . . . :
In [27]: data1 = mcsolve(H, psi0, times, [np.sqrt(0.1) * a], [a.dag() * a, sm.
→dag() * sm])
                 0.85s. Est. time left: 00:00:00:07
10.0%. Run time:
20.0%. Run time: 1.62s. Est. time left: 00:00:00:06
30.0%. Run time:
                 2.34s. Est. time left: 00:00:00:05
40.0%. Run time:
                 3.08s. Est. time left: 00:00:00:04
50.0%. Run time:
                 3.90s. Est. time left: 00:00:00:03
                 4.79s. Est. time left: 00:00:00:03
60.0%. Run time:
                 5.70s. Est. time left: 00:00:00:02
70.0%. Run time:
                 6.60s. Est. time left: 00:00:00:01
80.0%. Run time:
                 7.49s. Est. time left: 00:00:00:00
90.0%. Run time:
100.0%. Run time: 8.39s. Est. time left: 00:00:00:00
Total run time: 8.48s
In [28]: psi1 = tensor(fock(2, 0), coherent(10, 2 - 1j))
In [29]: opts = Options(rhs_reuse=True) # Run a second time, reusing RHS
In [30]: data2 = mcsolve(H, psil, times, [np.sqrt(0.1) * a], [a.dag() * a, sm.

→dag() * sm], options=opts)

10.0%. Run time: 1.69s. Est. time left: 00:00:00:15
20.0%. Run time:
                3.20s. Est. time left: 00:00:00:12
                 4.50s. Est. time left: 00:00:00:10
30.0%. Run time:
                 5.83s. Est. time left: 00:00:00:08
40.0%. Run time:
                 7.12s. Est. time left: 00:00:00:07
50.0%. Run time:
60.0%. Run time: 8.42s. Est. time left: 00:00:00:05
70.0%. Run time:
                 9.74s. Est. time left: 00:00:00:04
80.0%. Run time: 11.04s. Est. time left: 00:00:00:02
90.0%. Run time: 12.34s. Est. time left: 00:00:00:01
100.0%. Run time: 13.61s. Est. time left: 00:00:00:00
Total run time: 13.69s
In [31]: figure()
\leftrightarrow<Figure size 640x480 with 0 Axes>
In [32]: plot(times, data1.expect[0], times, data1.expect[1], lw=2)
[<matplotlib.lines.Line2D at 0x2acc519ea518>,
<matplotlib.lines.Line2D at 0x2acc519ea748>]
```





In addition to the initial state, one may reuse the Hamiltonian data when changing the number of trajectories ntraj or simulation times times. The reusing of Hamiltonian data is also supported for time-dependent Hamiltonians. See *Solving Problems with Time-dependent Hamiltonians* for further details.

3.5.4 Stochastic Solver - Photocurrent

Photocurrent method, like monte-carlo method, allows for simulating an individual realization of the system evolution under continuous measurement.

Closed system

Photocurrent evolution have the state evolve deterministically between quantum jumps. During the deterministic part, the system evolve by schrodinger equation with a non-hermitian, norm conserving effective Hamiltonian.

$$H_{\rm eff} = H_{\rm sys} + \frac{i\hbar}{2} \left(-\sum_{n} C_{n}^{+} C_{n} + |C_{n}\psi|^{2} \right).$$
(3.9)

With C_n , the collapse operators. This effective Hamiltonian is equivalent to the monte-carlo effective Hamiltonian with an extra term to keep the state normalized. At each time step of δt , the wave function has a probability

$$\delta p_n = \left\langle \psi(t) | C_n^+ C_n | \psi(t) \right\rangle \delta t \tag{3.10}$$

of making a quantum jump. δt must be chosen small enough to keep that probability small $\delta p \ll 1$. If multiple jumps happen at the same time step, the state become unphysical. Each jump result in a sharp variation of the state by,

$$\delta\psi = \left(\frac{C_n\psi}{|C_n\psi|} - \psi\right) \tag{3.11}$$

The basic photocurrent method directly integrates these equations to the first-order. Starting from a state $|\psi(0)\rangle$, it evolves the state according to

$$\delta\psi(t) = -iH_{\rm sys}\psi(t)\delta t + \sum_{n} \left(-\frac{C_n^+ C_n}{2}\psi(t)\delta t + \frac{|C_n\psi|^2}{2}\delta t + \delta N_n \left(\frac{C_n\psi}{|C_n\psi|} - \psi\right) \right),\tag{3.12}$$

for each time-step. Here $\delta N = 1$ with a probability of $\delta \omega$ and $\delta N_n = 0$ with a probability of $1 - \delta \omega$.

Trajectories obtained with this algorithm are equivalent to those obtained with monte-carlo evolution (up to $O(\delta t^2)$). In most cases, qutip.mcsolve is more efficient than $qutip.photocurrent_sesolve$.

Open system

Photocurrent approach allows to obtain trajectories for a system with both measured and dissipative interaction with the bath. The system evolves according to the master equation between jumps with a modified liouvillian

$$L_{\text{eff}}(\rho(t)) = L_{\text{sys}}(\rho(t)) + \sum_{n} \left(\text{tr} \left(\mathbf{C}_{n}^{+} \mathbf{C}_{n} \rho \mathbf{C}_{n}^{+} \mathbf{C}_{n} \right) - \mathbf{C}_{n}^{+} \mathbf{C}_{n} \rho \mathbf{C}_{n}^{+} \mathbf{C}_{n} \right),$$
(3.13)

with the probability of jumps in a time step δt given by

$$\delta p = \operatorname{tr} \left(\mathbf{C} \rho \mathbf{C}^+ \right) \delta \mathbf{t}. \tag{3.14}$$

After a jump, the density matrix become

$$\rho' = \frac{C\rho C^+}{\operatorname{tr}\left(C\rho C^+\right)}.$$

The evolution of the system at each time step if thus given by

$$\rho(t+\delta t) = \rho(t) + L_{\text{eff}}(\rho)\delta t + \delta N \left(\frac{C\rho C^+}{\operatorname{tr}(C\rho C^+)} - \rho\right).$$
(3.15)

3.5.5 Stochastic Solver

Homodyne detection

Homodyne detection is an extension of the photocurrent method where the output is mixed with a strong external source allowing to get information about the phase of the system. With this method, the resulting detection rate depends is

$$: label: jump_rate$$

$$\tau = tr\left((\gamma^2 + \gamma(C + C^{\dagger}) + C^{\dagger}C)\rho\right)$$

With γ , the strength of the external beam and C the collapse operator. When the beam is very strong ($\gamma >> C^{\dagger}C$), the rate becomes a constant term plus a term proportional to the quadrature of the system.

Closed system

In closed systems, the resulting stochastic differential equation is

$$\delta\psi(t) = -iH\psi(t)\delta t - \sum_{n} \left(\frac{C_n^+ C_n}{2} - \frac{e_n}{2}C_n + \frac{e_n^2}{8}\right)\psi\delta t + \sum_{n} \left(C_n - \frac{e_n}{2}\right)\psi\delta\omega$$
(3.16)

with

$$: label: jump_rate$$
$$e_n = \left\langle \psi(t) | C_n + C_n^+ | \psi(t) \right\rangle$$


Here $\delta \omega$ is a Wiener increment.

In QuTiP, this is available with the function ssesolve.

```
In [1]: times = np.linspace(0.0, 10.0, 201)
In [2]: psi0 = tensor(fock(2, 0), fock(10, 5))
In [3]: a = tensor(qeye(2), destroy(10))
In [4]: sm = tensor(destroy(2), qeye(10))
In [5]: H = 2 * np.pi * a.dag() * a + 2 * np.pi * sm.dag() * sm + 2 * np.pi * 0.25_
\rightarrow \star (sm \star a.dag() + sm.dag() \star a)
In [6]: data = ssesolve(H, psi0, times, sc_ops=[np.sqrt(0.1) * a], e_ops=[a.dag()_
0.01s
Total run time:
In [7]: figure()
In [8]: plot(times, data.expect[0], times, data.expect[1])
[<matplotlib.lines.Line2D at 0x2acc508bd748>,
<matplotlib.lines.Line2D at 0x2acc508bd5f8>]
In [9]: title('Homodyne time evolution')
→Text(0.5,1, 'Homodyne time evolution')
In [10]: xlabel('Time')
→Text(0.5,0,'Time')
```



In [13]: show()



Open system

In open systems, 2 types of collapse operators are considered, S_i represent the dissipation in the environment, C_i are monitored operators. The deterministic part of the evolution is the liouvillian with both types of collapses

$$L(\rho(t)) = -i[H(t), \rho(t)] + \sum_{n} D(S_n, \rho) + \sum_{i} D(C_i, \rho),$$
(3.17)

with

$$D(C,\rho) = \frac{1}{2} \left[2C\rho(t)C^{+} - \rho(t)C^{+}C - C^{+}C\rho(t) \right].$$
(3.18)

The stochastic part is given by

$$d_2 = \left(C\rho(t) + \rho(t)C^+ - \operatorname{tr}\left(C \times \rho + \rho \times C^+\right)\rho(t)\right), \qquad (3.19)$$

resulting in the stochastic differential equation

$$\delta\rho(t) = L(\rho(t))\delta t + d_2\delta\omega \tag{3.20}$$

The function smesslve covert these cases in QuTiP.

Heterodyne detection

With heterodyne detection, two measurements are made in order to obtain information about 2 orthogonal quadratures at once.

3.5.6 Solving Problems with Time-dependent Hamiltonians

Methods for Writing Time-Dependent Operators

In the previous examples of quantum evolution, we assumed that the systems under consideration were described by time-independent Hamiltonians. However, many systems have explicit time dependence in either the Hamiltonian, or the collapse operators describing coupling to the environment, and sometimes both components might depend on time. The time-evolutions solvers *qutip.mesolve*, *qutip.mesolve*, *qutip.sesolve*, *qutip.sesolve*, *qutip.sesolve*, *qutip.sesolve*, *qutip.sesolve*, *qutip.sesolve*, *qutip.photocurrent_sesolve*, *qutip.smesolve*, *and qutip.* photocurrent_mesolve are all capable of handling time-dependent Hamiltonians and collapse terms. There are, in general, three different ways to implement time-dependent problems in QuTiP:

- 1. **Function based**: Hamiltonian / collapse operators expressed using [qobj, func] pairs, where the timedependent coefficients of the Hamiltonian (or collapse operators) are expressed using Python functions.
- 2. String (Cython) based: The Hamiltonian and/or collapse operators are expressed as a list of [qobj, string] pairs, where the time-dependent coefficients are represented as strings. The resulting Hamiltonian is then compiled into C code using Cython and executed.
- 3. **Array Based**: The Hamiltonian and/or collapse operators are expressed as a list of [qobj, np.array] pairs. The arrays are 1 dimensional and dtype are complex or float. They must contain one value for each time in the tlist given to the solver. Cubic spline interpolation will be used between the given times.
- 4. **Hamiltonian function (outdated)**: The Hamiltonian is itself a Python function with time-dependence. Collapse operators must be time independent using this input format.

Give the multiple choices of input style, the first question that arrises is which option to choose? In short, the function based method (option #1) is the most general, allowing for essentially arbitrary coefficients expressed via user defined functions. However, by automatically compiling your system into C++ code, the second option (string based) tends to be more efficient and will run faster [This is also the only format that is supported in the qutip.brmesolve solver]. Of course, for small system sizes and evolution times, the difference will be minor. Although this method does not support all time-dependent coefficients that one can think of, it does support essentially all problems that one would typically encounter. Time-dependent coefficients using any of the following functions, or combinations thereof (including constants) can be compiled directly into C++-code:

```
'abs', 'acos', 'acosh', 'arg', 'asin', 'asinh', 'atan', 'atanh', 'conj',
'cos', 'cosh','exp', 'erf', 'zerf', 'imag', 'log', 'log10', 'norm', 'pi',
'proj', 'real', 'sin', 'sinh', 'sqrt', 'tan', 'tanh'
```

In addition, QuTiP supports cubic spline based interpolation functions [Modeling Non-Analytic and/or Experimental Time-Dependent Parameters using Interpolating Functions].

If you require mathematical functions other than those listed above, it is possible to call any of the functions in the NumPy library using the prefix np. before the function name in the string, i.e 'np.sin(t)' and scipy. special imported as spe. This includes a wide range of functionality, but comes with a small overhead created by going from C++->Python->C++.

Finally option #4, expressing the Hamiltonian as a Python function, is the original method for time dependence in QuTiP 1.x. However, this method is somewhat less efficient then the previously mentioned methods. However, in contrast to the other options this method can be used in implementing time-dependent Hamiltonians that cannot be expressed as a function of constant operators with time-dependent coefficients.

A collection of examples demonstrating the simulation of time-dependent problems can be found on the tutorials web page.

Function Based Time Dependence

A very general way to write a time-dependent Hamiltonian or collapse operator is by using Python functions as the time-dependent coefficients. To accomplish this, we need to write a Python function that returns the time-dependent coefficient. Additionally, we need to tell QuTiP that a given Hamiltonian or collapse operator should be associated with a given Python function. To do this, one needs to specify operator-function pairs in list format: [Op, py_coeff], where Op is a given Hamiltonian or collapse operator and py_coeff is the name of the Python function representing the coefficient. With this format, the form of the Hamiltonian for both mesolve and mcsolve is:

>>> H = [H0, [H1, py_coeff1], [H2, py_coeff2], ...]

where H0 is a time-independent Hamiltonian, while H1, "H2", are time dependent. The same format can be used for collapse operators:

>>> c_ops = [[C0, py_coeff0], C1, [C2, py_coeff2], ...]

Here we have demonstrated that the ordering of time-dependent and time-independent terms does not matter. In addition, any or all of the collapse operators may be time dependent.

Note: While, in general, you can arrange time-dependent and time-independent terms in any order you like, it is best to place all time-independent terms first.

As an example, we will look at an example that has a time-dependent Hamiltonian of the form $H = H_0 - f(t)H_1$ where f(t) is the time-dependent driving strength given as $f(t) = A \exp\left[-(t/\sigma)^2\right]$. The follow code sets up the problem

```
In [1]: ustate = basis(3, 0)
In [2]: excited = basis(3, 1)
In [3]: ground = basis(3, 2)
In [4]: N = 2 # Set where to truncate Fock state for cavity
In [5]: sigma_ge = tensor(qeye(N), ground * excited.dag()) # |g><e/pre>
In [6]: sigma_ue = tensor(qeye(N), ustate * excited.dag()) # /u><e/pre>
In [7]: a = tensor(destroy(N), qeye(3))
In [8]: ada = tensor(num(N), qeye(3))
In [9]: c_ops = [] # Build collapse operators
In [10]: kappa = 1.5 # Cavity decay rate
In [11]: c_ops.append(np.sqrt(kappa) * a)
In [12]: gamma = 6 # Atomic decay rate
In [13]: c_ops.append(np.sqrt(5*gamma/9) * sigma_ue) # Use Rb branching ratio of 5/
→9 e->u
In [14]: c_ops.append(np.sqrt(4*gamma/9) * sigma_ge) # 4/9 e->g
In [15]: t = np.linspace(-15, 15, 100) # Define time vector
In [16]: psi0 = tensor(basis(N, 0), ustate) # Define initial state
```

```
In [17]: state_GG = tensor(basis(N, 1), ground) # Define states onto which to_

→project
In [18]: sigma_GG = state_GG * state_GG.dag()
In [19]: state_UU = tensor(basis(N, 0), ustate)
In [20]: sigma_UU = state_UU * state_UU.dag()
In [21]: g = 5 # coupling strength
In [22]: H0 = -g * (sigma_ge.dag() * a + a.dag() * sigma_ge) # time-independent_

→term
In [23]: H1 = (sigma_ue.dag() + sigma_ue) # time-dependent term
```

Given that we have a single time-dependent Hamiltonian term, and constant collapse terms, we need to specify a single Python function for the coefficient f(t). In this case, one can simply do

```
In [24]: def H1_coeff(t, args):
    ....: return 9 * np.exp(-(t / 5.) ** 2)
    ....:
```

In this case, the return value dependents only on time. However, when specifying Python functions for coefficients, **the function must have (t,args) as the input variables, in that order**. Having specified our coefficient function, we can now specify the Hamiltonian in list format and call the solver (in this case *qutip.mesolve*)

```
In [25]: H = [H0,[H1,H1_coeff]]
In [26]: output = mesolve(H, psi0, t, c_ops, [ada, sigma_UU, sigma_GG])
```

We can call the Monte Carlo solver in the exact same way (if using the default ntraj=500):

```
In [27]: output = mcsolve(H, psi0, t, c_ops, [ada, sigma_UU, sigma_GG])
10.0%. Run time: 0.29s. Est. time left: 00:00:00:02
20.0%. Run time: 0.53s. Est. time left: 00:00:00:02
30.0%. Run time: 0.75s. Est. time left: 00:00:00:01
40.0%. Run time: 1.00s. Est. time left: 00:00:00:01
50.0%. Run time: 1.21s. Est. time left: 00:00:00:01
60.0%. Run time: 1.43s. Est. time left: 00:00:00:00
70.0%. Run time: 1.66s. Est. time left: 00:00:00:00
80.0%. Run time: 1.90s. Est. time left: 00:00:00:00
90.0%. Run time: 2.14s. Est. time left: 00:00:00:00
100.0%. Run time: 2.34s. Est. time left: 00:00:00:00
```

The output from the master equation solver is identical to that shown in the examples, the Monte Carlo however will be noticeably off, suggesting we should increase the number of trajectories for this example. In addition, we can also consider the decay of a simple Harmonic oscillator with time-varying decay rate

```
In [28]: kappa = 0.5
In [29]: def col_coeff(t, args): # coefficient function
    ...: return np.sqrt(kappa * np.exp(-t))
    ...:
In [30]: N = 10 # number of basis states
In [31]: a = destroy(N)
```

```
In [32]: H = a.dag() * a # simple HO
In [33]: psi0 = basis(N, 9) # initial state
In [34]: c_ops = [[a, col_coeff]] # time-dependent collapse term
In [35]: times = np.linspace(0, 10, 100)
In [36]: output = mesolve(H, psi0, times, c_ops, [a.dag() * a])
```

Using the args variable

In the previous example we hardcoded all of the variables, driving amplitude A and width σ , with their numerical values. This is fine for problems that are specialized, or that we only want to run once. However, in many cases, we would like to change the parameters of the problem in only one location (usually at the top of the script), and not have to worry about manually changing the values on each run. QuTiP allows you to accomplish this using the keyword args as an input to the solvers. For instance, instead of explicitly writing 9 for the amplitude and 5 for the width of the gaussian driving term, we can make us of the args variable

```
In [37]: def H1_coeff(t, args):
    ....: return args['A'] * np.exp(-(t/args['sigma'])**2)
    ....:
```

or equivalently,

where args is a Python dictionary of key: value pairs args = {'A': a, 'sigma': b} where a and b are the two parameters for the amplitude and width, respectively. Of course, we can always hardcode the values in the dictionary as well args = {'A': 9, 'sigma': 5}, but there is much more flexibility by using variables in args. To let the solvers know that we have a set of args to pass we append the args to the end of the solver input:

```
In [39]: output = mesolve(H, psi0, times, c_ops, [a.dag() * a], args={'A': 9,

→'sigma': 5})
```

or to keep things looking pretty

```
In [40]: args = {'A': 9, 'sigma': 5}
In [41]: output = mesolve(H, psi0, times, c_ops, [a.dag() * a], args=args)
```

Once again, the Monte Carlo solver *qutip.mcsolve* works in an identical manner.

String Format Method

Note: You must have Cython installed on your computer to use this format. See *Installation* for instructions on installing Cython.

The string-based time-dependent format works in a similar manner as the previously discussed Python function method. That being said, the underlying code does something completely different. When using this format, the strings used to represent the time-dependent coefficients, as well as Hamiltonian and collapse operators, are

rewritten as Cython code using a code generator class and then compiled into C code. The details of this metaprogramming will be published in due course. however, in short, this can lead to a substantial reduction in time for complex time-dependent problems, or when simulating over long intervals.

Like the previous method, the string-based format uses a list pair format [Op, str] where str is now a string representing the time-dependent coefficient. For our first example, this string would be '9 $\star \exp(-(t / 5.) \times 2)$ '. The Hamiltonian in this format would take the form:

In [42]: H = [H0, [H1, '9 * exp(-(t / 5) ** 2)']]

Notice that this is a valid Hamiltonian for the string-based format as exp is included in the above list of suitable functions. Calling the solvers is the same as before:

In [43]: output = mesolve(H, psi0, t, c_ops, [a.dag() * a])

We can also use the args variable in the same manner as before, however we must rewrite our string term to read: 'A $* \exp(-(t / sig) * 2)$ '

```
In [44]: H = [H0, [H1, 'A * exp(-(t / sig) ** 2)']]
In [45]: args = {'A': 9, 'sig': 5}
In [46]: output = mesolve(H, psi0, times, c_ops, [a.dag()*a], args=args)
```

Important: Naming your args variables exp, sin, pi etc. will cause errors when using the string-based format.


Collapse operators are handled in the exact same way.

Modeling Non-Analytic and/or Experimental Time-Dependent Parameters using Interpolating Functions


Note: New in QuTiP 4.1

Sometimes it is necessary to model a system where the time-dependent parameters are non-analytic functions, or are derived from experimental data (i.e. a collection of data points). In these situations, one can use interpolating functions as an approximate functional form for input into a time-dependent solver. QuTiP includes it own custom cubic spline interpolation class *qutip.interpolate.Cubic_Spline* to provide this functionality. To see how this works, lets first generate some noisy data:

```
In [54]: plt.show()
```



To turn these data points into a function we call the QuTiP $qutip.interpolate.Cubic_Spline$ class using the first and last domain time points, t[0] and t[-1], respectively, as well as the entire array of data points:



Note that, at present, only equally spaced real or complex data sets can be accommodated. This cubic spline class S can now be pasted to any of the mesolve, mcsolve, or sesolve functions where one would normally input a time-dependent function or string-representation. Taking the problem from the previous section as an example. We would make the replacement:

```
H = [H0, [H1, '9 * exp(-(t / 5) * 2)']]
```

to

H = [H0, [H1, S]]

When combining interpolating functions with other Python functions or strings, the interpolating class will automatically pick the appropriate method for calling the class. That is to say that, if for example, you have other time-dependent terms that are given in the string-format, then the cubic spline representation will also be passed in a string-compatible format. In the string-format, the interpolation function is compiled into c-code, and thus is quite fast. This is the default method if no other time-dependent terms are present.

Accesing the state from solver

New in QuTiP 4.4

The state of the system, the ket vector or the density matrix, is available to time-dependent Hamiltonian and collapse operators in args. Some keys of the argument dictionary are understood by the solver to be values to be updated with the evolution of the system. The state can be obtained in 3 forms: Qobj, vector (1d np.array), matrix (2d np.array), expectation values and collapse can also be obtained.

Here psi0 is the initial value used for tests before the evolution begins. qutip.brmesolve does not support these arguments.

Reusing Time-Dependent Hamiltonian Data

Note: This section covers a specialized topic and may be skipped if you are new to QuTiP.

When repeatedly simulating a system where only the time-dependent variables, or initial state change, it is possible to reuse the Hamiltonian data stored in QuTiP and there by avoid spending time needlessly preparing the Hamiltonian and collapse terms for simulation. To turn on the the reuse features, we must pass a qutip.Options object with the rhs_reuse flag turned on. Instructions on setting flags are found in *Setting Options for the Dynamics Solvers*. For example, we can do

```
In [61]: H = [H0, [H1, 'A * exp(-(t / sig) ** 2)']]
In [62]: args = { 'A': 9, 'sig': 5}
In [63]: output = mcsolve(H, psi0, times, c_ops, [a.dag()*a], args=args)
10.0%. Run time: 0.20s. Est. time left: 00:00:00:01
20.0%. Run time:
                    0.35s. Est. time left: 00:00:00:01
30.0%. Run time:
                    0.59s. Est. time left: 00:00:00:01
                    0.72s. Est. time left: 00:00:00:01
40.0%. Run time:
                   0.84s. Est. time left: 00:00:00:00
50.0%. Run time:
60.0%. Run time: 0.97s. Est. time left: 00:00:00:00
70.0%. Run time: 1.09s. Est. time left: 00:00:00:00
80.0%. Run time: 1.21s. Est. time left: 00:00:00:00
90.0%. Run time: 1.37s. Est. time left: 00:00:00:00
100.0%. Run time: 1.55s. Est. time left: 00:00:00:00
Total run time: 1.64s
In [64]: opts = Options(rhs_reuse=True)
In [65]: args = {'A': 10, 'sig': 3}
In [66]: output = mcsolve(H, psi0, times, c_ops, [a.dag()*a], args=args,_
→options=opts)
10.0%. Run time:
                    0.18s. Est. time left: 00:00:00:01
20.0%. Run time: 0.36s. Est. time left: 00:00:00:01
30.0%. Run time: 0.49s. Est. time left: 00:00:00:01
40.0%. Run time:
                    0.68s. Est. time left: 00:00:00:01

      40.0%. Run time:
      0.82s. Est. time reft. 00:00:00:00

      50.0%. Run time:
      0.94s. Est. time left: 00:00:00:00

      10ft.
      00:00:00:00

70.0%. Run time: 1.11s. Est. time left: 00:00:00:00
80.0%. Run time: 1.26s. Est. time left: 00:00:00:00
90.0%. Run time: 1.42s. Est. time left: 00:00:00:00
100.0%. Run time: 1.59s. Est. time left: 00:00:00:00
Total run time: 1.70s
```

The second call to *qutip.mcsolve* does not reorganize the data, and in the case of the string format, does not recompile the Cython code. For the small system here, the savings in computation time is quite small, however, if you need to call the solvers many times for different parameters, this savings will obviously start to add up.

Running String-Based Time-Dependent Problems using Parfor

Note: This section covers a specialized topic and may be skipped if you are new to QuTiP.

In this section we discuss running string-based time-dependent problems using the qutip.parfor function. As the qutip.mcsolve function is already parallelized, running string-based time dependent problems inside of parfor loops should be restricted to the qutip.mesolve function only. When using the string-based format, the system Hamiltonian and collapse operators are converted into C code with a specific file name that is automatically genrated, or supplied by the user via the rhs_filename property of the qutip.Options class. Because the qutip.parfor function uses the built-in Python multiprocessing functionality, in calling the solver inside a parfor loop, each thread will try to generate compiled code with the same file name, leading to a crash. To get around this problem you can call the qutip.rhs_generate function to compile simulation into C code before calling parfor. You **must** then set the qutip.Odedata object rhs_reuse=True for all solver calls inside the parfor loop that indicates that a valid C code file already exists and a new one should not be generated. As an example, we will look at the Landau-Zener-Stuckelberg interferometry example that can be found in the notebook "Time-dependent master equation: Landau-Zener-Stuckelberg inteferometry" in the tutorials section of the QuTiP web site.

To set up the problem, we run the following code:

```
In [67]: delta = 0.1 * 2 * np.pi # qubit sigma_x coefficient
In [68]: w = 2.0 * 2 * np.pi # driving frequency
In [69]: T = 2 * np.pi / w
                                 # driving period
In [70]: gamma1 = 0.00001
                                 # relaxation rate
In [71]: gamma2 = 0.005
                                 # dephasing rate
In [72]: eps_list = np.linspace(-10.0, 10.0, 51) * 2 * np.pi # epsilon
In [73]: A_list = np.linspace(0.0, 20.0, 51) * 2 * np.pi  # Amplitude
In [74]: sx = sigmax(); sz = sigmaz(); sm = destroy(2); sn = num(2)
In [75]: c_ops = [np.sqrt(gamma1) * sm, np.sqrt(gamma2) * sz] # relaxation and_
→ dephasing
In [76]: H0 = -delta / 2.0 * sx
In [77]: H1 = [sz, '-eps / 2.0 + A / 2.0 * sin(w * t)']
In [78]: H_td = [H0, H1]
In [79]: Hargs = {'w': w, 'eps': eps_list[0], 'A': A_list[0]}
```

where the last code block sets up the problem using a string-based Hamiltonian, and Hargs is a dictionary of arguments to be passed into the Hamiltonian. In this example, we are going to use the *qutip.propagator* and *qutip.propagator.propagator_steadystate* to find expectation values for different values of ϵ and A in the Hamiltonian $H = -\frac{1}{2}\Delta\sigma_x - \frac{1}{2}\epsilon\sigma_z - \frac{1}{2}A\sin(\omega t)$.

We must now tell the *qutip.mesolve* function, that is called by *qutip.propagator* to reuse a pregenerated Hamiltonian constructed using the *qutip.rhs_generate* command:

```
In [80]: opts = Options(rhs_reuse=True)
In [81]: rhs_generate(H_td, c_ops, Hargs, name='lz_func')
```

Here, we have given the generated file a custom name lz_func, however this is not necessary as a generic name will automatically be given. Now we define the function task that is called by *qutip.parallel.parfor* with the m-index parallelized in loop over the elements of p_mat[m,n]:

```
In [82]: def task(args):
            m, eps = args
   . . . . :
              p_mat_m = np.zeros(len(A_list))
   . . . . :
             for n, A in enumerate(A_list):
   . . . . :
                  # change args sent to solver, w is really a constant though.
   . . . . :
                  Hargs = { 'w': w, 'eps': eps, 'A': A }
   . . . . :
                  U = propagator(H_td, T, c_ops, Hargs, opts) #<- IMPORTANT LINE
   . . . . :
                  rho_ss = propagator_steadystate(U)
   . . . . :
   . . . . :
                  p_mat_m[n] = expect(sn, rho_ss)
   . . . . :
              return [m, p_mat_m]
   . . . . :
```

Notice the Options opts in the call to the *qutip.propagator* function. This is tells the *qutip.mesolve* function used in the propagator to call the pre-generated file lz_func. If this were missing then the routine

would fail.

3.5.7 Bloch-Redfield master equation

Introduction

The Lindblad master equation introduced earlier is constructed so that it describes a physical evolution of the density matrix (i.e., trace and positivity preserving), but it does not provide a connection to any underlaying microscopic physical model. The Lindblad operators (collapse operators) describe phenomenological processes, such as for example dephasing and spin flips, and the rates of these processes are arbitrary parameters in the model. In many situations the collapse operators and their corresponding rates have clear physical interpretation, such as dephasing and relaxation rates, and in those cases the Lindblad master equation is usually the method of choice.

However, in some cases, for example systems with varying energy biases and eigenstates and that couple to an environment in some well-defined manner (through a physically motivated system-environment interaction operator), it is often desirable to derive the master equation from more fundamental physical principles, and relate it to for example the noise-power spectrum of the environment.

The Bloch-Redfield formalism is one such approach to derive a master equation from a microscopic system. It starts from a combined system-environment perspective, and derives a perturbative master equation for the system alone, under the assumption of weak system-environment coupling. One advantage of this approach is that the dissipation processes and rates are obtained directly from the properties of the environment. On the downside, it does not intrinsically guarantee that the resulting master equation unconditionally preserves the physical properties of the density matrix (because it is a perturbative method). The Bloch-Redfield master equation must therefore be used with care, and the assumptions made in the derivation must be honored. (The Lindblad master equation is in a sense more robust – it always results in a physical density matrix – although some collapse operators might not be physically justified). For a full derivation of the Bloch Redfield master equation, see e.g. [Coh92] or [Bre02]. Here we present only a brief version of the derivation, with the intention of introducing the notation and how it relates to the implementation in QuTiP.

Brief Derivation and Definitions

The starting point of the Bloch-Redfield formalism is the total Hamiltonian for the system and the environment (bath): $H = H_{\rm S} + H_{\rm B} + H_{\rm I}$, where H is the total system+bath Hamiltonian, $H_{\rm S}$ and $H_{\rm B}$ are the system and bath Hamiltonians, respectively, and $H_{\rm I}$ is the interaction Hamiltonian.

The most general form of a master equation for the system dynamics is obtained by tracing out the bath from the von-Neumann equation of motion for the combined system ($\dot{\rho} = -i\hbar^{-1}[H,\rho]$). In the interaction picture the result is

$$\frac{d}{dt}\rho_S(t) = -\hbar^{-2} \int_0^t d\tau \operatorname{Tr}_B[H_I(t), [H_I(\tau), \rho_S(\tau) \otimes \rho_B]],$$
(3.21)

where the additional assumption that the total system-bath density matrix can be factorized as $\rho(t) \approx \rho_S(t) \otimes \rho_B$. This assumption is known as the Born approximation, and it implies that there never is any entanglement between the system and the bath, neither in the initial state nor at any time during the evolution. It is justified for weak system-bath interaction.

The master equation (3.21) is non-Markovian, i.e., the change in the density matrix at a time t depends on states at all times $\tau < t$, making it intractable to solve both theoretically and numerically. To make progress towards a manageable master equation, we now introduce the Markovian approximation, in which $\rho(s)$ is replaced by $\rho(t)$ in Eq. (3.21). The result is the Redfield equation

$$\frac{d}{dt}\rho_S(t) = -\hbar^{-2} \int_0^t d\tau \operatorname{Tr}_B[H_I(t), [H_I(\tau), \rho_S(t) \otimes \rho_B]], \qquad (3.22)$$

which is local in time with respect the density matrix, but still not Markovian since it contains an implicit dependence on the initial state. By extending the integration to infinity and substituting $\tau \to t - \tau$, a fully Markovian

master equation is obtained:

$$\frac{d}{dt}\rho_S(t) = -\hbar^{-2} \int_0^\infty d\tau \operatorname{Tr}_B[H_I(t), [H_I(t-\tau), \rho_S(t) \otimes \rho_B]].$$
(3.23)

The two Markovian approximations introduced above are valid if the time-scale with which the system dynamics changes is large compared to the time-scale with which correlations in the bath decays (corresponding to a "short-memory" bath, which results in Markovian system dynamics).

The master equation (3.23) is still on a too general form to be suitable for numerical implementation. We therefore assume that the system-bath interaction takes the form $H_I = \sum_{\alpha} A_{\alpha} \otimes B_{\alpha}$ and where A_{α} are system operators and B_{α} are bath operators. This allows us to write master equation in terms of system operators and bath correlation functions:

$$\frac{d}{dt}\rho_S(t) = -\hbar^{-2}\sum_{\alpha\beta}\int_0^\infty d\tau \left\{ g_{\alpha\beta}(\tau) \left[A_\alpha(t)A_\beta(t-\tau)\rho_S(t) - A_\alpha(t-\tau)\rho_S(t)A_\beta(t) \right] g_{\alpha\beta}(-\tau) \left[\rho_S(t)A_\alpha(t-\tau)A_\beta(t) - A_\alpha(t)\rho_S(t)A_\beta(t-\tau) \right] \right\},$$

where $g_{\alpha\beta}(\tau) = \text{Tr}_B \left[B_\alpha(t) B_\beta(t-\tau) \rho_B \right] = \langle B_\alpha(\tau) B_\beta(0) \rangle$, since the bath state ρ_B is a steady state.

In the eigenbasis of the system Hamiltonian, where $A_{mn}(t) = A_{mn}e^{i\omega_{mn}t}$, $\omega_{mn} = \omega_m - \omega_n$ and ω_m are the eigenfrequencies corresponding the eigenstate $|m\rangle$, we obtain in matrix form in the Schrödinger picture

$$\begin{aligned} \frac{d}{dt}\rho_{ab}(t) &= -i\omega_{ab}\rho_{ab}(t) - \hbar^{-2}\sum_{\alpha,\beta}\sum_{c,d}^{\mathrm{sec}}\int_{0}^{\infty}d\tau \left\{g_{\alpha\beta}(\tau)\left[\delta_{bd}\sum_{n}A_{an}^{\alpha}A_{nc}^{\beta}e^{i\omega_{cn}\tau} - A_{ac}^{\alpha}A_{db}^{\beta}e^{i\omega_{ca}\tau}\right]\right. \\ &+ g_{\alpha\beta}(-\tau)\left[\delta_{ac}\sum_{n}A_{dn}^{\alpha}A_{nb}^{\beta}e^{i\omega_{nd}\tau} - A_{ac}^{\alpha}A_{db}^{\beta}e^{i\omega_{bd}\tau}\right]\right\}\rho_{cd}(t),\end{aligned}$$

where the "sec" above the summation symbol indicate summation of the secular terms which satisfy $|\omega_{ab} - \omega_{cd}| \ll \tau_{decay}$. This is an almost-useful form of the master equation. The final step before arriving at the form of the Bloch-Redfield master equation that is implemented in QuTiP, involves rewriting the bath correlation function $g(\tau)$ in terms of the noise-power spectrum of the environment $S(\omega) = \int_{-\infty}^{\infty} d\tau e^{i\omega\tau} g(\tau)$:

$$\int_{0}^{\infty} d\tau \ g_{\alpha\beta}(\tau) e^{i\omega\tau} = \frac{1}{2} S_{\alpha\beta}(\omega) + i\lambda_{\alpha\beta}(\omega), \qquad (3.24)$$

where $\lambda_{ab}(\omega)$ is an energy shift that is neglected here. The final form of the Bloch-Redfield master equation is

$$\frac{d}{dt}\rho_{ab}(t) = -i\omega_{ab}\rho_{ab}(t) + \sum_{c,d}^{\text{sec}} R_{abcd}\rho_{cd}(t), \qquad (3.25)$$

where

$$R_{abcd} = -\frac{\hbar^{-2}}{2} \sum_{\alpha,\beta} \left\{ \delta_{bd} \sum_{n} A^{\alpha}_{an} A^{\beta}_{nc} S_{\alpha\beta}(\omega_{cn}) - A^{\alpha}_{ac} A^{\beta}_{db} S_{\alpha\beta}(\omega_{ca}) + \delta_{ac} \sum_{n} A^{\alpha}_{dn} A^{\beta}_{nb} S_{\alpha\beta}(\omega_{dn}) - A^{\alpha}_{ac} A^{\beta}_{db} S_{\alpha\beta}(\omega_{db}) \right\},$$

is the Bloch-Redfield tensor.

The Bloch-Redfield master equation in the form Eq. (3.25) is suitable for numerical implementation. The input parameters are the system Hamiltonian H, the system operators through which the environment couples to the system A_{α} , and the noise-power spectrum $S_{\alpha\beta}(\omega)$ associated with each system-environment interaction term.

To simplify the numerical implementation we assume that A_{α} are Hermitian and that cross-correlations between different environment operators vanish, so that the final expression for the Bloch-Redfield tensor that is implemented in QuTiP is

$$R_{abcd} = -\frac{\hbar^{-2}}{2} \sum_{\alpha} \left\{ \delta_{bd} \sum_{n} A^{\alpha}_{an} A^{\alpha}_{nc} S_{\alpha}(\omega_{cn}) - A^{\alpha}_{ac} A^{\alpha}_{db} S_{\alpha}(\omega_{ca}) + \delta_{ac} \sum_{n} A^{\alpha}_{dn} A^{\alpha}_{nb} S_{\alpha}(\omega_{dn}) - A^{\alpha}_{ac} A^{\alpha}_{db} S_{\alpha}(\omega_{db}) \right\}.$$

Bloch-Redfield master equation in QuTiP

In QuTiP, the Bloch-Redfield tensor Eq. (3.26) can be calculated using the function qutip. $bloch_redfield.bloch_redfield_tensor$. It takes two mandatory arguments: The system Hamiltonian H, a nested list of operator A_{α} , spectral density functions $S_{\alpha}(\omega)$ pairs that characterize the coupling between system and bath. The spectral density functions are Python callback functions that takes the (angular) frequency as a single argument.

To illustrate how to calculate the Bloch-Redfield tensor, let's consider a two-level atom

$$H = -\frac{1}{2}\Delta\sigma_x - \frac{1}{2}\epsilon_0\sigma_z \tag{3.26}$$


that couples to an Ohmic bath through the σ_x operator. The corresponding Bloch-Redfield tensor can be calculated in QuTiP using the following code

```
In [1]: delta = 0.2 * 2*np.pi; eps0 = 1.0 * 2*np.pi; gamma1 = 0.5
In [2]: H = - delta/2.0 * sigmax() - eps0/2.0 * sigmaz()
In [3]: def ohmic_spectrum(w):
           if w == 0.0: # dephasing inducing noise
   . . . :
   . . . :
               return gammal
            else: # relaxation inducing noise
   . . . :
                return gamma1 / 2 * (w / (2 * np.pi)) * (w > 0.0)
   . . . :
   . . . :
In [4]: R, ekets = bloch_redfield_tensor(H, [[sigmax(), ohmic_spectrum]])
In [5]: R
Out[5]:
Quantum object: dims = [[[2], [2]], [[2], [2]], shape = (4, 4), type = super,
⇒isherm = False
Qobj data =
             +0.j
[[ 0.
                          Ο.
                                     +0.j
                                                  Ο.
                                                            +0.j
   0.24514517+0.j
                        1
 [ 0.
            +0.j
                         -0.16103412-6.4076169j 0.
                                                            +0.j
             +0.j
   0.
                        ]
                                                 -0.16103412+6.4076169j
 [ 0.
             +0.j
                          0.
                                    +0.j
             +0.j
   Ο.
                        ]
                          0.
                                     +0.j
                                                  0.
 [ 0.
             +0.j
                                                            +0.j
  -0.24514517+0.j
                        ]]
```

Note that it is also possible to add Lindblad dissipation superoperators in the Bloch-Refield tensor by passing the operators via the c_ops keyword argument like you would in the *qutip.mesolve* or *qutip.mesolve* functions. For convenience, the function *qutip.bloch_redfield.bloch_redfield_tensor* also returns a list of eigenkets *ekets*, since they are calculated in the process of calculating the Bloch-Redfield tensor *R*, and the *ekets* are usually needed again later when transforming operators between the computational basis and the eigenbasis.

The evolution of a wavefunction or density matrix, according to the Bloch-Redfield master equation (3.25), can be calculated using the QuTiP function *qutip.bloch_redfield.bloch_redfield_solve*. It takes five mandatory arguments: the Bloch-Redfield tensor R, the list of eigenkets ekets, the initial state psi0 (as a ket or density matrix), a list of times tlist for which to evaluate the expectation values, and a list of operators e_ops for which to evaluate the expectation values at each time step defined by *tlist*. For example, to evaluate the expectation values of the σ_x , σ_y , and σ_z operators for the example above, we can use the following code:

```
In [6]: import matplotlib.pyplot as plt
In [7]: tlist = np.linspace(0, 15.0, 1000)
In [8]: psi0 = rand_ket(2)
```



The two steps of calculating the Bloch-Redfield tensor and evolving according to the corresponding master equation can be combined into one by using the function *qutip.bloch_redfield.brmesolve*, which takes same arguments as *qutip.mesolve* and *qutip.mesolve*, save for the additional nested list of operatorspectrum pairs that is called a_ops.

where the resulting *output* is an instance of the class *qutip.solver*.Result.

Time-dependent Bloch-Redfield Dynamics

Note: New in QuTiP 4.2.

Warning: It takes ~3-5 seconds (~30 if using Visual Studio) to compile a time-dependent Bloch-Redfield problem. Therefore, if you are doing repeated simulations by varying parameters, then it is best to pass options = Options(rhs_reuse=True) to the solver.

If you have not done so already, please read the section: Solving Problems with Time-dependent Hamiltonians.


As we have already discussed, the Bloch-Redfield master equation requires transforming into the eigenbasis of the system Hamiltonian. For time-independent systems, this transformation need only be done once. However, for time-dependent systems, one must move to the instantaneous eigenbasis at each time-step in the evolution, thus greatly increasing the computational complexity of the dynamics. In addition, the requirement for computing all the eigenvalues severely limits the scalability of the method. Fortunately, this eigen decomposition occurs at the Hamiltonian level, as opposed to the super-operator level, and thus, with efficient programming, one can tackle many systems that are commonly encountered.

The time-dependent Bloch-Redfield solver in QuTiP relies on the efficient numerical computations afforded by the string-based time-dependent format, and Cython compilation. As such, all the time-dependent terms, and noise power spectra must be expressed in the string format. To begin, lets consider the previous example, but formatted to call the time-dependent solver:

Although the problem itself is time-independent, the use of a string as the noise power spectrum tells the solver to go into time-dependent mode. The string is nearly identical to the Python function format, except that we replaced np.pi with pi to avoid calling Python in our Cython code, and we have hard coded the gammal argument into the string as limitations prevent passing arguments into the time-dependent Bloch-Redfield solver.

For actual time-dependent Hamiltonians, the Hamiltonian itself can be passed into the solver like any other string-based Hamiltonian, as thus we will not discuss this topic further. Instead, here the focus is on time-dependent bath coupling terms. To this end, suppose that we have a dissipative harmonic oscillator, where the white-noise dissipation rate decreases exponentially with time $\kappa(t) = \kappa(0) \exp(-t)$. In the Lindblad or monte-carlo solvers, this could be implemented as a time-dependent collapse operator list c_ops = [[a, 'sqrt(kappa*exp(-t))']]. In the Bloch-Redfield solver, the bath coupling terms must be Hermitian. As such, in this example, our coupling operator is the position operator a+a.dag(). In addition, we do not need the sqrt operation that occurs in the c_ops definition. The complete example, and comparison to the analytic expression is:

```
In [20]: N = 10 # number of basis states to consider
In [21]: a = destroy(N)
In [22]: H = a.dag() * a
In [23]: psi0 = basis(N, 9) # initial state
In [24]: kappa = 0.2 # coupling to oscillator
In [25]: a_ops = [[a+a.dag(), '{kappa}*exp(-t)*(w>=0)'.format(kappa=kappa)]]
In [26]: tlist = np.linspace(0, 10, 100)
In [27]: out = brmesolve(H, psi0, tlist, a_ops, e_ops=[a.dag() * a])
In [28]: actual_answer = 9.0 * np.exp(-kappa * (1.0 - np.exp(-tlist)))
In [29]: plt.figure()
Out [29]: <Figure size 640x480 with 0 Axes>
```



In many cases, the bath-coupling operators can take the form $A = f(t)a + f(t)^*a^+$. In this case, the above format for inputting the a_ops is not sufficient. Instead, one must construct a nested-list of tuples to specify this time-dependence. For example consider a white-noise bath that is coupled to an operator of the form exp(lj*t) *a + exp(-lj*t) * a.dag(). In this example, the a_ops list would be:


where the first tuple element (a, a.dag()) tells the solver which operators make up the full Hermitian coupling operator. The second tuple ('{0} * ($w \ge 0$)'.format(kappa), 'exp(lj*t)', 'exp(-lj*t)'), gives the noise power spectrum, and time-dependence of each operator. Note that the noise spectrum must always come first in this second tuple. A full example is:

```
In [34]: N = 10
In [35]: w0 = 1.0 * 2 * np.pi
In [36]: g = 0.05 * w0
In [37]: kappa = 0.15
In [38]: times = np.linspace(0, 25, 1000)
In [39]: a = destroy(N)
```

```
(continued from previous page)
In [40]: H = w0 * a.dag() * a + g * (a + a.dag())
In [41]: psi0 = ket2dm((basis(N, 4) + basis(N, 2) + basis(N, 0)).unit())
In [42]: a_ops = [[ (a, a.dag()), ('{0} * (w >= 0)'.format(kappa), 'exp(1j*t)',
→ 'exp(-1j*t) ') ]]
In [43]: e_ops = [a.dag() * a, a + a.dag()]
In [44]: res_brme = brmesolve(H, psi0, times, a_ops, e_ops)
In [45]: plt.figure()
Out[45]: <Figure size 640x480 with 0 Axes>
In [46]: plt.plot(times,res_brme.expect[0], label=r'$a^{+}a$')
→0x2acc4f2f97f0>]
In [47]: plt.plot(times,res_brme.expect[1], label=r'$a+a^{+}$')
↔[<matplotlib.lines.Line2D at 0x2acc4f604a58>]
In [48]: plt.legend()

-><matplotlib.legend.Legend at 0x2acc4f2dc828>

In [49]: plt.show()
```



Further examples on time-dependent Bloch-Redfield simulations can be found in the online tutorials.

3.5.8 Floquet Formalism

Introduction

Many time-dependent problems of interest are periodic. The dynamics of such systems can be solved for directly by numerical integration of the Schrödinger or Master equation, using the time-dependent Hamiltonian. But they can also be transformed into time-independent problems using the Floquet formalism. Time-independent problems can be solve much more efficiently, so such a transformation is often very desirable.

In the standard derivations of the Lindblad and Bloch-Redfield master equations the Hamiltonian describing the system under consideration is assumed to be time independent. Thus, strictly speaking, the standard forms of these master equation formalisms should not blindly be applied to system with time-dependent Hamiltonians. However, in many relevant cases, in particular for weak driving, the standard master equations still turns out to be useful for many time-dependent problems. But a more rigorous approach would be to rederive the master equation taking the time-dependent nature of the Hamiltonian into account from the start. The Floquet-Markov Master equation is one such a formalism, with important applications for strongly driven systems (see e.g., [Gri98]).

Here we give an overview of how the Floquet and Floquet-Markov formalisms can be used for solving timedependent problems in QuTiP. To introduce the terminology and naming conventions used in QuTiP we first give a brief summary of quantum Floquet theory.

Floquet theory for unitary evolution

The Schrödinger equation with a time-dependent Hamiltonian H(t) is

$$H(t)\Psi(t) = i\hbar \frac{\partial}{\partial t}\Psi(t), \qquad (3.27)$$

where $\Psi(t)$ is the wave function solution. Here we are interested in problems with periodic time-dependence, i.e., the Hamiltonian satisfies H(t) = H(t + T) where T is the period. According to the Floquet theorem, there exist solutions to (3.27) on the form

$$\Psi_{\alpha}(t) = \exp(-i\epsilon_{\alpha}t/\hbar)\Phi_{\alpha}(t), \qquad (3.28)$$

where $\Psi_{\alpha}(t)$ are the *Floquet states* (i.e., the set of wave function solutions to the Schrödinger equation), $\Phi_{\alpha}(t) = \Phi_{\alpha}(t+T)$ are the periodic *Floquet modes*, and ϵ_{α} are the *quasienergy levels*. The quasienergy levels are constants in time, but only uniquely defined up to multiples of $2\pi/T$ (i.e., unique value in the interval $[0, 2\pi/T]$).

If we know the Floquet modes (for $t \in [0, T]$) and the quasienergies for a particular H(t), we can easily decompose any initial wavefunction $\Psi(t = 0)$ in the Floquet states and immediately obtain the solution for arbitrary t

$$\Psi(t) = \sum_{\alpha} c_{\alpha} \Psi_{\alpha}(t) = \sum_{\alpha} c_{\alpha} \exp(-i\epsilon_{\alpha} t/\hbar) \Phi_{\alpha}(t), \qquad (3.29)$$

where the coefficients c_{α} are determined by the initial wavefunction $\Psi(0) = \sum_{\alpha} c_{\alpha} \Psi_{\alpha}(0)$.

This formalism is useful for finding $\Psi(t)$ for a given H(t) only if we can obtain the Floquet modes $\Phi_a(t)$ and quasienergies ϵ_{α} more easily than directly solving (3.27). By substituting (3.28) into the Schrödinger equation (3.27) we obtain an eigenvalue equation for the Floquet modes and quasienergies

$$\mathcal{H}(t)\Phi_{\alpha}(t) = \epsilon_{\alpha}\Phi_{\alpha}(t), \qquad (3.30)$$

where $\mathcal{H}(t) = H(t) - i\hbar\partial_t$. This eigenvalue problem could be solved analytically or numerically, but in QuTiP we use an alternative approach for numerically finding the Floquet states and quasienergies [see e.g. Creffield et al., Phys. Rev. B 67, 165301 (2003)]. Consider the propagator for the time-dependent Schrödinger equation (3.27), which by definition satisfies

$$U(T+t,t)\Psi(t) = \Psi(T+t).$$

Inserting the Floquet states from (3.28) into this expression results in

$$U(T+t,t)\exp(-i\epsilon_{\alpha}t/\hbar)\Phi_{\alpha}(t) = \exp(-i\epsilon_{\alpha}(T+t)/\hbar)\Phi_{\alpha}(T+t),$$

or, since $\Phi_{\alpha}(T+t) = \Phi_{\alpha}(t)$,

$$U(T+t,t)\Phi_{\alpha}(t) = \exp(-i\epsilon_{\alpha}T/\hbar)\Phi_{\alpha}(t) = \eta_{\alpha}\Phi_{\alpha}(t),$$

which shows that the Floquet modes are eigenstates of the one-period propagator. We can therefore find the Floquet modes and quasienergies $\epsilon_{\alpha} = -\hbar \arg(\eta_{\alpha})/T$ by numerically calculating U(T + t, t) and diagonalizing it. In particular this method is useful to find $\Phi_{\alpha}(0)$ by calculating and diagonalize U(T, 0).

The Floquet modes at arbitrary time t can then be found by propagating $\Phi_{\alpha}(0)$ to $\Phi_{\alpha}(t)$ using the wave function propagator $U(t,0)\Psi_{\alpha}(0) = \Psi_{\alpha}(t)$, which for the Floquet modes yields

$$U(t,0)\Phi_{\alpha}(0) = \exp(-i\epsilon_{\alpha}t/\hbar)\Phi_{\alpha}(t),$$

so that $\Phi_{\alpha}(t) = \exp(i\epsilon_{\alpha}t/\hbar)U(t,0)\Phi_{\alpha}(0)$. Since $\Phi_{\alpha}(t)$ is periodic we only need to evaluate it for $t \in [0,T]$, and from $\Phi_{\alpha}(t \in [0,T])$ we can directly evaluate $\Phi_{\alpha}(t)$, $\Psi_{\alpha}(t)$ and $\Psi(t)$ for arbitrary large t.

Floquet formalism in QuTiP

QuTiP provides a family of functions to calculate the Floquet modes and quasi energies, Floquet state decomposition, etc., given a time-dependent Hamiltonian on the *callback format*, *list-string format* and *list-callback format* (see, e.g., *qutip.mesolve* for details).

Consider for example the case of a strongly driven two-level atom, described by the Hamiltonian

$$H(t) = -\frac{1}{2}\Delta\sigma_x - \frac{1}{2}\epsilon_0\sigma_z + \frac{1}{2}A\sin(\omega t)\sigma_z.$$
(3.31)

In QuTiP we can define this Hamiltonian as follows:


```
In [1]: delta = 0.2 * 2*np.pi; eps0 = 1.0 * 2*np.pi; A = 2.5 * 2*np.pi; omega = 1.

...0 * 2*np.pi
In [2]: H0 = - delta/2.0 * sigmax() - eps0/2.0 * sigmaz()
In [3]: H1 = A/2.0 * sigmaz()
In [4]: args = {'w': omega}
In [5]: H = [H0, [H1, 'sin(w * t)']]
```

The t = 0 Floquet modes corresponding to the Hamiltonian (3.31) can then be calculated using the *qutip*. *floquet_modes* function, which returns lists containing the Floquet modes and the quasienergies

For some problems interesting observations can be draw from the quasienergy levels alone. Consider for example the quasienergies for the driven two-level system introduced above as a function of the driving amplitude, calculated and plotted in the following example. For certain driving amplitudes the quasienergy levels cross. Since the the quasienergies can be associated with the time-scale of the long-term dynamics due that the driving, degenerate quasienergies indicates a "freezing" of the dynamics (sometimes known as coherent destruction of tunneling).

```
In [10]: delta = 0.2 * 2*np.pi; eps0 = 0.0 * 2*np.pi
In [11]: omega = 1.0 * 2*np.pi; A_vec = np.linspace(0, 10, 100) * omega;
In [12]: T = (2*pi)/omega
In [13]: tlist = np.linspace(0.0, 10 * T, 101)
In [14]: psi0 = basis(2,0)
In [15]: q_energies = np.zeros((len(A_vec), 2))
In [16]: H0 = delta/2.0 * sigmaz() - eps0/2.0 * sigmax()
In [17]: args = { 'w': omega}
In [18]: for idx, A in enumerate(A_vec):
        H1 = A/2.0 * sigmax()
  . . . . :
         H = [H0, [H1, lambda t, args: sin(args['w']*t)]]
  . . . . :
  . . . . :
         f_modes, f_energies = floquet_modes(H, T, args, True)
  . . . . :
         q_energies[idx,:] = f_energies
  . . . . :
In [19]: figure()
Out[19]: <Figure size 640x480 with 0 Axes>
In [20]: plot(A_vec/omega, q_energies[:,0] / delta, 'b', A_vec/omega, q_energies[:,
\rightarrow1] / delta, 'r')
[<matplotlib.lines.Line2D at 0x2acc4f1cee80>,
<matplotlib.lines.Line2D at 0x2acc4f18c1d0>]
In [21]: xlabel(r'$A/\omega$')
→Text(0.5,0,'$A/\\omega$')
In [22]: ylabel(r'Quasienergy / $\Delta$')
→Text(0,0.5,'Quasienergy / $\\Delta$')
In [23]: title(r'Floquet quasienergies')
→Text(0.5,1,'Floquet quasienergies')
In [24]: show()
```



Given the Floquet modes at t = 0, we obtain the Floquet mode at some later time t using the function qutip. floquet.floquet_mode_t:

```
In [25]: f_modes_t = floquet_modes_t(f_modes_0, f_energies, 2.5, H, T, args)
In [26]: f_modes_t
Out[26]:
[Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[-0.89630512-0.23191946j]
[ 0.37793106-0.00431336j]],
Quantum object: dims = [[2], [1]], shape = (2, 1), type = ket
Qobj data =
[[-0.37793106-0.00431336j]
[-0.89630512+0.23191946j]]]
```

The purpose of calculating the Floquet modes is to find the wavefunction solution to the original problem (3.31) given some initial state $|\psi_0\rangle$. To do that, we first need to decompose the initial state in the Floquet states, using the function $qutip.floquet.floquet_state_decomposition$

```
In [27]: psi0 = rand_ket(2)
In [28]: f_coeff = floquet_state_decomposition(f_modes_0, f_energies, psi0)
In [29]: f_coeff
Out[29]: [array(-0.15345484+0.50610123j), array(0.05941819+0.84663016j)]
```

and given this decomposition of the initial state in the Floquet states we can easily evaluate the wavefunction that is the solution to (3.31) at an arbitrary time t using the function qutip.floquet. $floquet_wavefunction_t$

```
Out[32]:
<2x1 sparse matrix of type '<class 'numpy.complex128'>'
with 2 stored elements in Compressed Sparse Row format>
```

The following example illustrates how to use the functions introduced above to calculate and plot the timeevolution of (3.31).

```
from qutip import *
from scipy import *
delta = 0.2 * 2*pi; eps0 = 1.0 * 2*pi
A = 0.5 * 2*pi; omega = 1.0 * 2*pi
Т
      = (2*pi)/omega
tlist = linspace(0.0, 10 * T, 101)
psi0
      = basis(2,0)
H0 = - delta/2.0 * sigmax() - eps0/2.0 * sigmaz()
H1 = A/2.0 \times sigmaz()
args = { 'w': omega }
H = [H0, [H1, lambda t,args: sin(args['w'] * t)]]
# find the floquet modes for the time-dependent hamiltonian
f_modes_0,f_energies = floquet_modes(H, T, args)
# decompose the inital state in the floquet modes
f_coeff = floquet_state_decomposition(f_modes_0, f_energies, psi0)
# calculate the wavefunctions using the from the floquet modes
p_ex = zeros(len(tlist))
for n, t in enumerate(tlist):
   psi_t = floquet_wavefunction_t(f_modes_0, f_energies, f_coeff, t, H, T, args)
   p_ex[n] = expect(num(2), psi_t)
# For reference: calculate the same thing with mesolve
p_ex_ref = mesolve(H, psi0, tlist, [], [num(2)], args).expect[0]
# plot the results
from pylab import *
                         'ro', tlist, 1-real(p_ex),
plot(tlist, real(p_ex),
                                                           'bo')
plot(tlist, real(p_ex_ref), 'r', tlist, 1-real(p_ex_ref), 'b')
xlabel('Time')
ylabel('Occupation probability')
legend(("Floquet $P_1$", "Floquet $P_0$", "Lindblad $P_1$", "Lindblad $P_0$"))
show()
```

Pre-computing the Floquet modes for one period

When evaluating the Floquet states or the wavefunction at many points in time it is useful to pre-compute the Floquet modes for the first period of the driving with the required resolution. In QuTiP the function *qutip*. *floquet_modes_table* calculates a table of Floquet modes which later can be used together with the function *qutip.floquet_floquet_floquet_modes_t_lookup* to efficiently lookup the Floquet mode at an arbitrary time. The following example illustrates how the example from the previous section can be solved more efficiently using these functions for pre-computing the Floquet modes.

```
from qutip import *
from scipy import *
delta = 0.0 * 2*pi; eps0 = 1.0 * 2*pi
A = 0.25 * 2*pi; omega = 1.0 * 2*pi
```

```
Т
     = (2*pi)/omega
tlist = linspace(0.0, 10 * T, 101)
psi0 = basis(2, 0)
H0 = - delta/2.0 * sigmax() - eps0/2.0 * sigmaz()
H1 = A/2.0 \times sigmax()
args = {'w': omega}
H = [H0, [H1, lambda t,args: sin(args['w'] * t)]]
# find the floquet modes for the time-dependent hamiltonian
f_modes_0,f_energies = floquet_modes(H, T, args)
# decompose the inital state in the floquet modes
f_coeff = floquet_state_decomposition(f_modes_0, f_energies, psi0)
# calculate the wavefunctions using the from the floquet modes
f_modes_table_t = floquet_modes_table(f_modes_0, f_energies, tlist, H, T, args)
p_ex = zeros(len(tlist))
for n, t in enumerate(tlist):
   f_modes_t = floquet_modes_t_lookup(f_modes_table_t, t, T)
            = floquet_wavefunction(f_modes_t, f_energies, f_coeff, t)
   psi t
   p_ex[n] = expect(num(2), psi_t)
# For reference: calculate the same thing with mesolve
p_ex_ref = mesolve(H, psi0, tlist, [], [num(2)], args).expect[0]
# plot the results
from pylab import *
                        'ro', tlist, 1-real(p_ex),
plot(tlist, real(p_ex),
                                                           'bo')
plot(tlist, real(p_ex_ref), 'r', tlist, 1-real(p_ex_ref), 'b')
xlabel('Time')
ylabel('Occupation probability')
legend(("Floquet $P_1$", "Floquet $P_0$", "Lindblad $P_1$", "Lindblad $P_0$"))
show()
```

Note that the parameters and the Hamiltonian used in this example is not the same as in the previous section, and hence the different appearance of the resulting figure.

For convenience, all the steps described above for calculating the evolution of a quantum system using the Floquet formalisms are encapsulated in the function *qutip.floquet.fsesolve*. Using this function, we could have achieved the same results as in the examples above using:

```
output = fsesolve(H, psi0, times, [num(2)], args)
p_ex = output.expect[0]
```

Floquet theory for dissipative evolution

A driven system that is interacting with its environment is not necessarily well described by the standard Lindblad master equation, since its dissipation process could be time-dependent due to the driving. In such cases a rigorious approach would be to take the driving into account when deriving the master equation. This can be done in many different ways, but one way common approach is to derive the master equation in the Floquet basis. That approach results in the so-called Floquet-Markov master equation, see Grifoni et al., Physics Reports 304, 299 (1998) for details.

The Floquet-Markov master equation in QuTiP

The QuTiP function *qutip.floquet.fmmesolve* implements the Floquet-Markov master equation. It calculates the dynamics of a system given its initial state, a time-dependent hamiltonian, a list of operators through

which the system couples to its environment and a list of corresponding spectral-density functions that describes the environment. In contrast to the *qutip.mesolve* and *qutip.mesolve*, and the *qutip.floquet*. *fmmesolve* does characterize the environment with dissipation rates, but extract the strength of the coupling to the environment from the noise spectral-density functions and the instantaneous Hamiltonian parameters (similar to the Bloch-Redfield master equation solver *qutip.bloch_redfield.brmesolve*).

Note: Currently the *qutip.floquet.fmmesolve* can only accept a single environment coupling operator and spectral-density function.


The noise spectral-density function of the environment is implemented as a Python callback function that is passed to the solver. For example:

```
>>> gamma1 = 0.1
>>> def noise_spectrum(omega):
>>> return 0.5 * gamma1 * omega/(2*pi)
```

The other parameters are similar to the *qutip.mesolve* and *qutip.mesolve*, and the same format for the return value is used *qutip.solver.Result*. The following example extends the example studied above, and uses *qutip.floquet.fmmesolve* to introduce dissipation into the calculation

```
from qutip import *
from scipy import *
delta = 0.0 * 2*pi; eps0 = 1.0 * 2*pi
  = 0.25 * 2*pi; omega = 1.0 * 2*pi
А
Т
     = (2*pi)/omega
tlist = linspace(0.0, 20 * T, 101)
psi0 = basis(2, 0)
H0 = - delta/2.0 * sigmax() - eps0/2.0 * sigmaz()
H1 = A/2.0 * sigmax()
args = {'w': omega}
H = [H0, [H1, lambda t,args: sin(args['w'] * t)]]
# noise power spectrum
gamma1 = 0.1
def noise_spectrum(omega):
   return 0.5 * gamma1 * omega/(2*pi)
# find the floquet modes for the time-dependent hamiltonian
f_modes_0, f_energies = floquet_modes(H, T, args)
# precalculate mode table
f_modes_table_t = floquet_modes_table(f_modes_0, f_energies,
                                      linspace(0, T, 500 + 1), H, T, args)
# solve the floquet-markov master equation
output = fmmesolve(H, psi0, tlist, [sigmax()], [], [noise_spectrum], T, args)
# calculate expectation values in the computational basis
p_ex = zeros(shape(tlist), dtype=complex)
for idx, t in enumerate(tlist):
    f_modes_t = floquet_modes_t_lookup(f_modes_table_t, t, T)
   p_ex[idx] = expect(num(2), output.states[idx].transform(f_modes_t, True))
# For reference: calculate the same thing with mesolve
output = mesolve(H, psi0, tlist, [sqrt(gammal) * sigmax()], [num(2)], args)
p_ex_ref = output.expect[0]
# plot the results
```

```
from pylab import *
plot(tlist, real(p_ex), 'r--', tlist, 1-real(p_ex), 'b--')
plot(tlist, real(p_ex_ref), 'r', tlist, 1-real(p_ex_ref), 'b')
xlabel('Time')
ylabel('Occupation probability')
legend(("Floquet $P_1$", "Floquet $P_0$", "Lindblad $P_1$", "Lindblad $P_0$"))
show()
```



Alternatively, we can let the *qutip.floquet.fmmesolve* function transform the density matrix at each time step back to the computational basis, and calculating the expectation values for us, but using:

output = fmmesolve(H, psi0, tlist, [sigmax()], [num(2)], [noise_spectrum], T, args)
p_ex = output.expect[0]

3.5.9 Permutational Invariance

Permutational Invariant Quantum Solver (PIQS)

The *Permutational Invariant Quantum Solver (PIQS)* is a QuTiP module that allows to study the dynamics of an open quantum system consisting of an ensemble of identical qubits that can dissipate through local and collective baths according to a Lindblad master equation.

The Liouvillian of an ensemble of N qubits, or two-level systems (TLSs), $\mathcal{D}_{TLS}(\rho)$, can be built using only polynomial – instead of exponential – resources. This has many applications for the study of realistic quantum optics models of many TLSs and in general as a tool in cavity QED.

Consider a system evolving according to the equation

$$\begin{split} \dot{\rho} &= \mathcal{D}_{\text{TLS}}(\rho) = -\frac{i}{\hbar} [H,\rho] + \frac{\gamma_{\text{CE}}}{2} \mathcal{L}_{J_{-}}[\rho] + \frac{\gamma_{\text{CD}}}{2} \mathcal{L}_{J_{z}}[\rho] + \frac{\gamma_{\text{CP}}}{2} \mathcal{L}_{J_{+}}[\rho] \\ &+ \sum_{n=1}^{N} \left(\frac{\gamma_{\text{E}}}{2} \mathcal{L}_{J_{-,n}}[\rho] + \frac{\gamma_{\text{D}}}{2} \mathcal{L}_{J_{z,n}}[\rho] + \frac{\gamma_{\text{P}}}{2} \mathcal{L}_{J_{+,n}}[\rho] \right) \end{split}$$

where $J_{\alpha,n} = \frac{1}{2}\sigma_{\alpha,n}$ are SU(2) Pauli spin operators, with $\alpha = x, y, z$ and $J_{\pm,n} = \sigma_{\pm,n}$. The collective spin operators are $J_{\alpha} = \sum_{n} J_{\alpha,n}$. The Lindblad super-operators are $\mathcal{L}_{A} = 2A\rho A^{\dagger} - A^{\dagger}A\rho - \rho A^{\dagger}A$.

The inclusion of local processes in the dynamics lead to using a Liouvillian space of dimension 4^N . By exploiting the permutational invariance of identical particles [2-8], the Liouvillian $\mathcal{D}_{TLS}(\rho)$ can be built as a block-diagonal matrix in the basis of Dicke states $|j, m\rangle$.

The system under study is defined by creating an object of the Dicke class, e.g. simply named system, whose first attribute is

• system.N, the number of TLSs of the system N.

The rates for collective and local processes are simply defined as

- collective_emission defines $\gamma_{\rm CE}$, collective (superradiant) emission
- collective_dephasing defines $\gamma_{\rm CD}$, collective dephasing
- collective_pumping defines γ_{CP} , collective pumping.
- emission defines $\gamma_{\rm E}$, incoherent emission (losses)
- dephasing defines $\gamma_{\rm D}$, local dephasing
- pumping defines $\gamma_{\rm P}$, incoherent pumping.

Then the system.lindbladian() creates the total TLS Lindbladian superoperator matrix. Similarly, system.hamiltonian defines the TLS hamiltonian of the system H_{TLS} .

The system's Liouvillian can be built using system.liouvillian(). The properties of a Piqs object can be visualized by simply calling system. We give two basic examples on the use of *PIQS*. In the first example the incoherent emission of N driven TLSs is considered.

```
from piqs import Dicke
from qutip import steadystate
N = 10
system = Dicke(N, emission = 1, pumping = 2)
L = system.liouvillian()
steady = steadystate(L)
```

For more example of use, see the "Permutational Invariant Lindblad Dynamics" section in the tutorials section of the website, http://qutip.org/tutorials.html.

Operators	Command	Description		
Collective spin algebra	jspin(N)	The collective spin algebra J_x , J_y , J_z for N TLSs		
J_x, J_y, J_z				
Collective spin J_x	jspin(N, "x")	The collective spin operator Jx . Requires N number		
		of TLSs		
Collective spin J_y	jspin(N, "y")	The collective spin operator J_y . Requires N number		
		of TLSs		
Collective spin J_z	jspin(N, "z")	The collective spin operator J_z . Requires N number		
		of TLSs		
Collective spin J_+	jspin(N, "+")	The collective spin operator J_+ .		
Collective spin J_{-}	jspin(N, "-")	The collective spin operator J_{-} .		
Collective spin J_z in un-	jspin(N, "z",	The collective spin operator J_z in the uncoupled basis		
coupled basis	<pre>basis='uncoupled')</pre>	of dimension 2^N .		
Dicke state $ j,m\rangle$ density	dicke(N, j, m)	The density matrix for the Dicke state given by $ j,m angle$		
matrix				
Excited-state density ma-	excited(N)	The excited state in the Dicke basis		
trix in Dicke basis				
Excited-state density ma-	excited(N,	The excited state in the uncoupled basis		
trix in uncoupled basis	<pre>basis="uncoupled")</pre>			
Ground-state density ma-	ground(N)	The ground state in the Dicke basis		
trix in Dicke basis				
GHZ-state density ma-	ghz(N)	The GHZ-state density matrix in the Dicke (default)		
trix in the Dicke basis		basis for N number of TLS		
Collapse operators of the	Dicke.c_ops()	The collapse operators for the ensemble can be called		
ensemble		by the <i>c_ops</i> method of the Dicke class.		

Table 1: Useful PIQS functions.

More functions relative to the *qutip.piqs* module can be found at *API documentation*. Attributes to the *qutip*. *piqs.Dicke* and *qutip.piqs.Pim* class can also be found there.

3.5.10 Setting Options for the Dynamics Solvers

Occasionally it is necessary to change the built in parameters of the dynamics solvers used by for example the *qutip.mesolve* and *qutip.mesolve* functions. The options for all dynamics solvers may be changed by using the Options class *qutip.solver.Options*.

```
In [1]: options = Options()
```

the properties and default values of this class can be view via the print function:

<pre>In [2]: print(options) Options:</pre>		
atol:	1e-08	
rtol:	1e-06	
method:	adams	
order:	12	
nsteps:	1000	
first_step:	0	
min_step:	0	
max_step:	0	
tidy:	True	
num_cpus:	4	
norm_tol:	0.001	
norm_steps:	5	
rhs_filename:	None	
rhs_reuse:	False	
seeds:	0	
rhs_with_state:	False	
average_expect:	True	
average_states:	False	
ntraj:	500	
store_states:	False	
<pre>store_final_state:</pre>	False	

These properties are detailed in the following table. Assuming options = Options():

As an example, let us consider changing the number of processors used, turn the GUI off, and strengthen the absolute tolerance. There are two equivalent ways to do this using the Options class. First way,

```
In [3]: options = Options()
In [4]: options.num_cpus = 3
In [5]: options.atol = 1e-10
```

or one can use an inline method,

In [6]: options = Options(num_cpus=4, atol=1e-10)

Note that the order in which you input the options does not matter. Using either method, the resulting *options* variable is now:

		1 .	10/
method:	adams		
order:	12		
nsteps:	1000		
first_step:	0		
min_step:	0		
max_step:	0		
tidy:	True		
num_cpus:	4		
norm_tol:	0.001		
norm_steps:	5		
rhs_filename:	None		
rhs_reuse:	False		
seeds:	0		
rhs_with_state:	False		
average_expect:	True		
average_states:	False		
ntraj:	500		
store_states:	False		
store_final_state:	False		

To use these new settings we can use the keyword argument options in either the func: *qutip.mesolve* and *qutip.mesolve* function. We can modify the last example as:

or:

3.6 Solving for Steady-State Solutions

Important: Updated in QuTiP 3.2.

3.6.1 Introduction

For time-independent open quantum systems with decay rates larger than the corresponding excitation rates, the system will tend toward a steady state as $t \to \infty$ that satisfies the equation

$$\frac{d\hat{\rho}_{ss}}{dt} = \mathcal{L}\hat{\rho}_{ss} = 0.$$

Although the requirement for time-independence seems quite resitrictive, one can often employ a transformation to the interaction picture that yields a time-independent Hamiltonian. For many these systems, solving for the asymptotic density matrix $\hat{\rho}_{ss}$ can be achieved using direct or iterative solution methods faster than using master equation or Monte Carlo simulations. Although the steady state equation has a simple mathematical form, the properties of the Liouvillian operator are such that the solutions to this equation are anything but straightforward to find.

3.6.2 Steady State solvers in QuTiP

In QuTiP, the steady-state solution for a system Hamiltonian or Liouvillian is given by *qutip.steadystate*. *steadystate*. This function implements a number of different methods for finding the steady state, each with their own pros and cons, where the method used can be chosen using the method keyword argument.

Method	Keyword	Description
Direct (default)	'direct'	Direct solution solving $Ax = b$ via sparse LU decomposi-
		tion.
Eigenvalue	'eigen'	Iteratively find the zero eigenvalue of \mathcal{L} .
Inverse-Power	'power'	Solve using the inverse-power method.
GMRES	'iterative-gmres'	Solve using the GMRES method and optional precondi-
		tioner.
LGMRES	'iterative-lgmres'	Solve using the LGMRES method and optional precondi-
		tioner.
BICGSTAB	'iterative-bicgstab'	Solve using the BICGSTAB method and optional precon-
		ditioner.
SVD	'svd'	Steady-state solution via the dense SVD of the Liouvillian.

The function *qutip.steadystate.steadystate* can take either a Hamiltonian and a list of collapse operators as input, generating internally the corresponding Liouvillian super operator in Lindblad form, or alternatively, a Liouvillian passed by the user. When possible, we recommend passing the Hamiltonian and collapse operators to *qutip.steadystate.steadystate*, and letting the function automatically build the Liouvillian (in Lindblad form) for the system.

As of QuTiP 3.2, the direct and power methods can take advantage of the Intel Pardiso LU solver in the Intel Math Kernel library that comes with the Anacoda (2.5+) and Intel Python distributions. This gives a substantial increase in performance compared with the standard SuperLU method used by SciPy. To verify that QuTiP can find the necessary libraries, one can check for INTEL MKL Ext: True in the QuTiP about box (*qutip. about*).

3.6.3 Using the Steadystate Solver

Solving for the steady state solution to the Lindblad master equation for a general system with *qutip*. *steadystate.steadystate* can be accomplished using:

```
>>> rho_ss = steadystate(H, c_ops)
```

where H is a quantum object representing the system Hamiltonian, and c_{ops} is a list of quantum objects for the system collapse operators. The output, labeled as rho_ss, is the steady-state solution for the systems. If no other keywords are passed to the solver, the default 'direct' method is used, generating a solution that is exact to machine precision at the expense of a large memory requirement. The large amount of memory need for the direct LU decomposition method stems from the large bandwidth of the system Liouvillian and the correspondingly large fill-in (extra nonzero elements) generated in the LU factors. This fill-in can be reduced by using bandwidth minimization algorithms such as those discussed in *Additional Solver Arguments*. However, in most cases, the default fill-in reducing algorithm is nearly optimal. Additional parameters may be used by calling the steady-state solver as:

rho_ss = steadystate(H, c_ops, method='power', use_rcm=True)

where method='power' indicates that we are using the inverse-power solution method, and use_rcm=True turns on a bandwidth minimization routine.

Although it is not obvious, the 'direct', eigen, and 'power' methods all use an LU decomposition internally and thus suffer from a large memory overhead. In contrast, iterative methods such as the 'iterative-gmres', 'iterative-lgmres', and 'iterative-bicgstab' methods do not factor the matrix and thus take less memory than these previous methods and allowing, in principle, for extremely large system sizes. The downside is that these methods can take much longer than the direct method as the condition number of the Liouvillian matrix is large, indicating that these iterative methods require a large number of iterations for convergence. To overcome this, one can use a preconditioner *M* that solves for an approximate inverse for the (modified) Liouvillian, thus better conditioning the problem, leading to faster convergence. The use of a preconditioner can actually make these iterative methods faster than the other solution methods. The problem with precondioning is that it is only well defined for Hermitian matrices. Since the Liouvillian is non-Hermitian, the ability to find a good preconditioner is not guaranteed. And moreover, if a preconditioner is found, it is not guaranteed to have a good condition number. QuTiP can make use of an incomplete LU preconditioner when using the iterative 'gmres', 'lgmres', and 'bicgstab' solvers by setting use_precond=True. The preconditioner optionally makes use of a combination of symmetric and anti-symmetric matrix permutations that attempt to improve the preconditioning process. These features are discussed in the *Additional Solver Arguments* section. Even with these state-of-the-art permutations, the generation of a successful preconditoner for non-symmetric matrices is currently a trial-and-error process due to the lack of mathematical work done in this area. It is always recommended to begin with the direct solver with no additional arguments before selecting a different method.

Finding the steady-state solution is not limited to the Lindblad form of the master equation. Any time-independent Liouvillian constructed from a Hamiltonian and collapse operators can be used as an input:

```
>>> rho_ss = steadystate(L)
```

where L is the Louvillian. All of the additional arguments can also be used in this case.

3.6.4 Additional Solver Arguments

The following additional solver arguments are available for the steady-state solver:

Keyword		Description	
method	'direct', 'eigen', 'power',	Method used for solving for the steady-state density matrix.	
	'iterative-gmres','iterative-		
	lgmres', 'svd'		
sparse	True, False	Use sparse version of direct solver.	
weight	None	Allows the user to define the weighting factor used in the	
		'direct', 'GMRES', and 'LGMRES' solvers.	
permc_sp	ećCOLAMD', 'NATURAL'	Column ordering used in the sparse LU decomposition.	
use_rcm	False, True	Use a Reverse Cuthill-Mckee reordering to minimize the band-	
		width of the modified Liouvillian used in the LU decomposi-	
		tion. If use_rcm=True then the column ordering is set to	
		'Natural' automatically unless explicitly set.	
use_preco	nHalse, True	Attempt to generate a preconditioner when using the	
		'iterative-gmres' and 'iterative-lgmres'	
		methods.	
М	None, sparse_matrix, Linear-	A user defined preconditioner, if any.	
	Operator		
use_wbm	False, True	Use a Weighted Bipartite Matching algorithm to attempt to make	
		the modified Liouvillian more diagonally dominate, and thus for	
		favorable for preconditioning. Set to True automatically when	
		using a iterative method, unless explicitly set.	
tol	1e-9	Tolerance used in finding the solution for all methods expect	
		'direct' and 'svd'.	
maxiter	10000	Maximum number of iterations to perform for all methods expect	
		'direct' and 'svd'.	
fill_factor	10	Upper-bound on the allowed fill-in for the approximate inverse	
		preconditioner. This value may need to be set much higher than	
		this in some cases.	
drop_tol	1e-3	Sets the threshold for the relative magnitude of preconditioner el-	
		ements that should be dropped. A lower number yields a more ac-	
		curate approximate inverse at the expense of fill-in and increased	
		runtime.	
diag_pivo	t_Nonesh	Sets the threshold between $[0, 1]$ for which diagonal elements are	
		considered acceptable pivot points when using a preconditioner.	
ILU_MIL	U'smilu_2'	Selects the incomplete LU decomposition method algorithm	
		used.	


Further information can be found in the *qutip.steadystate.steadystate* docstrings.

3.6.5 Example: Harmonic Oscillator in Thermal Bath

A simple example of a system that reaches a steady state is a harmonic oscillator coupled to a thermal environment. Below we consider a harmonic oscillator, initially in the $|10\rangle$ number state, and weakly coupled to a thermal environment characterized by an average particle expectation value of $\langle n \rangle = 2$. We calculate the evolution via master equation and Monte Carlo methods, and see that they converge to the steady-state solution. Here we choose to perform only a few Monte Carlo trajectories so we can distinguish this evolution from the master-equation solution.

```
import numpy as np
import pylab as plt
from qutip import *
# Define paramters
N = 20 # number of basis states to consider
a = destroy(N)
H = a.dag() * a
psi0 = basis(N, 10) # initial state
```

```
kappa = 0.1 # coupling to oscillator
# collapse operators
c_op_list = []
n_th_a = 2 # temperature with average of 2 excitations
rate = kappa * (1 + n_th_a)
if rate > 0.0:
   c_op_list.append(np.sqrt(rate) * a) # decay operators
rate = kappa * n_th_a
if rate > 0.0:
   c_op_list.append(np.sqrt(rate) * a.dag()) # excitation operators
# find steady-state solution
final_state = steadystate(H, c_op_list)
# find expectation value for particle number in steady state
fexpt = expect(a.dag() * a, final_state)
tlist = np.linspace(0, 50, 100)
# monte-carlo
mcdata = mcsolve(H, psi0, tlist, c_op_list, [a.dag() * a], ntraj=100)
# master eq.
medata = mesolve(H, psi0, tlist, c_op_list, [a.dag() * a])
plt.plot(tlist, mcdata.expect[0], tlist, medata.expect[0], lw=2)
# plot steady-state expt. value as horizontal line (should be = 2)
plt.axhline(y=fexpt, color='r', lw=1.5)
plt.ylim([0, 10])
plt.xlabel('Time', fontsize=14)
plt.ylabel('Number of excitations', fontsize=14)
plt.legend(('Monte-Carlo', 'Master Equation', 'Steady State'))
plt.title('Decay of Fock state $\left|10\\rangle\\right.$' +
      ' in a thermal environment with $\langle n\\rangle=2$')
plt.show()
```



3.7 An Overview of the Eseries Class

3.7.1 Exponential-series representation of time-dependent quantum objects

The eseries object in QuTiP is a representation of an exponential-series expansion of time-dependent quantum objects (a concept borrowed from the quantum optics toolbox).

An exponential series is parameterized by its amplitude coefficients c_i and rates r_i , so that the series takes the form $E(t) = \sum_i c_i e^{r_i t}$. The coefficients are typically quantum objects (type Qobj: states, operators, etc.), so that the value of the eseries also is a quantum object, and the rates can be either real or complex numbers (describing decay rates and oscillation frequencies, respectively). Note that all amplitude coefficients in an exponential series must be of the same dimensions and composition.

In QuTiP, an exponential series object is constructed by creating an instance of the class qutip.eseries:

In [1]: es1 = eseries(sigmax(), 1j)

where the first argument is the amplitude coefficient (here, the sigma-X operator), and the second argument is the rate. The eseries in this example represents the time-dependent operator $\sigma_x e^{it}$.

To add more terms to an *qutip.eseries* object we simply add objects using the + operator:

The *qutip.eseries* in this example represents the operator $0.5\sigma_x e^{i\omega t} + 0.5\sigma_x e^{-i\omega t}$, which is the exponential series representation of $\sigma_x \cos(\omega t)$. Alternatively, we can also specify a list of amplitudes and rates when the *qutip.eseries* is created:

In [4]: es2 = eseries([0.5 * sigmax(), 0.5 * sigmax()], [1j * omega, -1j * omega])

We can inspect the structure of an *qutip*.eseries object by printing it to the standard output console:

```
In [5]: es2
Out[5]:
ESERIES object: 2 terms
Hilbert space dimensions: [[2], [2]]
Exponent #0 = -1j
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 0.5]
[0.5 0. ]]
Exponent #1 = 1j
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 0.5]
[0.5 0. ]]
```

and we can evaluate it at time t by using the qutip.eseries.esval function:

In [6]: esval(es2, 0.0) # equivalent to es2.value(0.0)
Out[6]:
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[0. 1.]
[1. 0.]]

or for a list of times [0.0, 1.0 * pi, 2.0 * pi]:

```
In [7]: times = [0.0, 1.0 * pi, 2.0 * pi]
In [8]: esval(es2, times)  # equivalent to es2.value(times)
Out[8]:
array([Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm =_
⇔True
Qobj data =
[[0. 1.]
[1. 0.]],
       Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm =_
⊶True
Qobj data =
[[ 0. -1.]
[-1. 0.]],
       Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm =_
⇔True
Qobj data =
[[0. 1.]
[1. 0.]]], dtype=object)
```

To calculate the expectation value of an time-dependent operator represented by an *qutip.eseries*, we use the *qutip.expect* function. For example, consider the operator $\sigma_x \cos(\omega t) + \sigma_z \sin(\omega t)$, and say we would like to know the expectation value of this operator for a spin in its excited state (rho = fock_dm(2,1) produce this state):

Note the expectation value of the *qutip.eseries* object, expect(rho, es3), itself is an *qutip.eseries*, but with amplitude coefficients that are C-numbers instead of quantum operators. To evaluate the C-number *qutip.eseries* at the times *times* we use esval(es3_expect, times), or, equivalently, es3_expect.value(times).

3.7.2 Applications of exponential series

The exponential series formalism can be useful for the time-evolution of quantum systems. One approach to calculating the time evolution of a quantum system is to diagonalize its Hamiltonian (or Liouvillian, for dissipative systems) and to express the propagator (e.g., $\exp(-iHt)\rho\exp(iHt)$) as an exponential series.

The QuTiP function *qutip.essolve.ode2es* and *qutip.essolve* use this method to evolve quantum systems in time. The exponential series approach is particularly suitable for cases when the same system is to be evolved for many different initial states, since the diagonalization only needs to be performed once (as opposed to e.g. the ode solver that would need to be ran independently for each initial state).

As an example, consider a spin-1/2 with a Hamiltonian pointing in the σ_z direction, and that is subject to noise causing relaxation. For a spin originally is in the up state, we can create an *qutip.eseries* object describing its dynamics by using the qutip.es2ode function:

```
In [14]: psi0 = basis(2,1)
In [15]: H = sigmaz()
In [16]: L = liouvillian(H, [sqrt(1.0) * destroy(2)])
In [17]: es = ode2es(L, psi0)
```

The *qutip.essolve.ode2es* function diagonalizes the Liouvillian L and creates an exponential series with the correct eigenfrequencies and amplitudes for the initial state ψ_0 (*psi0*).

We can examine the resulting *qutip.eseries* object by printing a text representation:

```
In [18]: es
Out[18]:
ESERIES object: 2 terms
Hilbert space dimensions: [[2], [2]]
Exponent #0 = (-1+0j)
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[-1. 0.]
[ 0. 1.]]
```

```
Exponent #1 = 0j
Quantum object: dims = [[2], [2]], shape = (2, 2), type = oper, isherm = True
Qobj data =
[[1. 0.]
[0. 0.]]
```

or by evaluating it and arbitrary points in time (here at 0.0 and 1.0):


and the expectation value of the exponential series can be calculated using the *qutip.expect* function:

In [20]: es_expect = expect(sigmaz(), es)

The result *es_expect* is now an exponential series with c-numbers as amplitudes, which easily can be evaluated at arbitrary times:

```
In [21]: es_expect.value([0.0, 1.0, 2.0, 3.0])
Out[21]: array([-1. , 0.26424112, 0.72932943, 0.90042586])
```

In [22]: times = linspace(0.0, 10.0, 100)
In [23]: sz_expect = es_expect.value(times)
In [24]: from pylab import *
In [25]: plot(times, sz_expect, lw=2);
In [26]: xlabel("Time", fontsize=16)
....: ylabel("Expectation value of sigma-z", fontsize=16);
....:
In [27]: title("The expectation value of the \$\sigma_{z}\$ operator", fontsize=16);



3.8 Two-time correlation functions

With the QuTiP time-evolution functions (for example *qutip.mesolve* and *qutip.mcsolve*), a state vector or density matrix can be evolved from an initial state at t_0 to an arbitrary time t, $\rho(t) = V(t, t_0) \{\rho(t_0)\}$, where $V(t, t_0)$ is the propagator defined by the equation of motion. The resulting density matrix can then be used to evaluate the expectation values of arbitrary combinations of *same-time* operators.

To calculate *two-time* correlation functions on the form $\langle A(t + \tau)B(t)\rangle$, we can use the quantum regression theorem (see, e.g., [Gar03]) to write

$$\langle A(t+\tau)B(t)\rangle = \operatorname{Tr}\left[AV(t+\tau,t)\left\{B\rho(t)\right\}\right] = \operatorname{Tr}\left[AV(t+\tau,t)\left\{BV(t,0)\left\{\rho(0)\right\}\right\}\right]$$

We therefore first calculate $\rho(t) = V(t,0) \{\rho(0)\}$ using one of the QuTiP evolution solvers with $\rho(0)$ as initial state, and then again use the same solver to calculate $V(t + \tau, t) \{B\rho(t)\}$ using $B\rho(t)$ as initial state.

Note that if the initial state is the steady state, then $\rho(t) = V(t,0) \{\rho_{ss}\} = \rho_{ss}$ and

$$\langle A(t+\tau)B(t)\rangle = \operatorname{Tr}\left[AV(t+\tau,t)\left\{B\rho_{\rm ss}\right\}\right] = \operatorname{Tr}\left[AV(\tau,0)\left\{B\rho_{\rm ss}\right\}\right] = \langle A(\tau)B(0)\rangle,$$

which is independent of t, so that we only have one time coordinate τ .

QuTiP provides a family of functions that assists in the process of calculating two-time correlation functions. The available functions and their usage is shown in the table below. Each of these functions can use one of the following evolution solvers: Master-equation, Exponential series and the Monte-Carlo. The choice of solver is defined by the optional argument solver.


QuTiP function	Correlation function
qutip.correlation.correlation or qutip.correlation.	$\langle A(t+\tau)B(t)\rangle$ or
correlation_2op_2t	$\langle A(t)B(t+\tau)\rangle.$
qutip.correlation.correlation_ss or qutip.correlation.	$\langle A(\tau)B(0)\rangle$ or
correlation_2op_1t	$\langle A(0)B(\tau)\rangle.$
<pre>qutip.correlation.correlation_4op_1t</pre>	$\langle A(0)B(\tau)C(\tau)D(0)\rangle.$
<pre>qutip.correlation.correlation_4op_2t</pre>	$\langle A(t)B(t+\tau)C(t+\tau)D(t)\rangle$

The most common use-case is to calculate correlation functions of the kind $\langle A(\tau)B(0)\rangle$, in which case we use the correlation function solvers that start from the steady state, e.g., the *qutip.correlation*. *correlation_2op_1t* function. These correlation function solvers return a vector or matrix (in general complex) with the correlations as a function of the delays times.

3.8.1 Steadystate correlation function

The following code demonstrates how to calculate the $\langle x(t)x(0)\rangle$ correlation for a leaky cavity with three different relaxation rates.

```
In [1]: times = np.linspace(0,10.0,200)
In [2]: a = destroy(10)
In [3]: x = a.dag() + a
In [4]: H = a.dag() * a
In [5]: corr1 = correlation_2op_1t(H, None, times, [np.sqrt(0.5) * a], x, x)
In [6]: corr2 = correlation_2op_1t(H, None, times, [np.sqrt(1.0) * a], x, x)
In [7]: corr3 = correlation_2op_1t(H, None, times, [np.sqrt(2.0) * a], x, x)
In [8]: figure()
Out[8]: <Figure size 640x480 with 0 Axes>
In [9]: plot(times, np.real(corr1), times, np.real(corr2), times, np.real(corr3))
[<matplotlib.lines.Line2D at 0x2acc53794f60>,
<matplotlib.lines.Line2D at 0x2acc53794dd8>,
<matplotlib.lines.Line2D at 0x2acc4fb5dfd0>]
In [10]: legend(['0.5','1.0','2.0'])
↔<matplotlib.legend.Legend at 0x2acc537f20b8>
In [11]: xlabel(r'Time $t$')
→Text(0.5,0,'Time $t$')
In [12]: ylabel(r'Correlation $\left<x(t)x(0)\right>$')
\rightarrow Text(0,0.5,'Correlation \low (0) \\ right>$')
In [13]: show()
```



3.8.2 Emission spectrum

Given a correlation function $\langle A(\tau)B(0)\rangle$ we can define the corresponding power spectrum as


$$S(\omega) = \int_{-\infty}^{\infty} \left\langle A(\tau)B(0) \right\rangle e^{-i\omega\tau} d\tau$$

In QuTiP, we can calculate $S(\omega)$ using either *qutip.correlation.spectrum_ss*, which first calculates the correlation function using the *qutip.essolve.essolve* solver and then performs the Fourier transform semi-analytically, or we can use the function *qutip.correlation.spectrum_correlation_fft* to numerically calculate the Fourier transform of a given correlation data using FFT.

The following example demonstrates how these two functions can be used to obtain the emission power spectrum.

```
import numpy as np
import pylab as plt
from qutip import *
N = 4
                        # number of cavity fock states
wc = wa = 1.0 * 2 * np.pi # cavity and atom frequency
g = 0.1 * 2 * np.pi
                          # coupling strength
kappa = 0.75
                        # cavity dissipation rate
gamma = 0.25
                        # atom dissipation rate
# Jaynes-Cummings Hamiltonian
a = tensor(destroy(N), qeye(2))
sm = tensor(qeye(N), destroy(2))
H = wc * a.dag() * a + wa * sm.dag() * sm + g * (a.dag() * sm + a * sm.dag())
# collapse operators
n_{th} = 0.25
c_ops = [np.sqrt(kappa * (1 + n_th)) * a, np.sqrt(kappa * n_th) * a.dag(), np.
⇔sqrt(gamma) * sm]
# calculate the correlation function using the mesolve solver, and then fft to
# obtain the spectrum. Here we need to make sure to evaluate the correlation
```

```
# function for a sufficient long time and sufficiently high sampling rate so
# that the discrete Fourier transform (FFT) captures all the features in the
# resulting spectrum.
tlist = np.linspace(0, 100, 5000)
corr = correlation_2op_1t(H, None, tlist, c_ops, a.dag(), a)
wlist1, spec1 = spectrum_correlation_fft(tlist, corr)
# calculate the power spectrum using spectrum, which internally uses essolve
# to solve for the dynamics (by default)
wlist2 = np.linspace(0.25, 1.75, 200) * 2 * np.pi
spec2 = spectrum(H, wlist2, c_ops, a.dag(), a)
# plot the spectra
fig, ax = plt.subplots(1, 1)
ax.plot(wlist1 / (2 * np.pi), spec1, 'b', lw=2, label='eseries method')
ax.plot(wlist2 / (2 * np.pi), spec2, 'r--', lw=2, label='me+fft method')
ax.legend()
ax.set_xlabel('Frequency')
ax.set_ylabel('Power spectrum')
ax.set_title('Vacuum Rabi splitting')
ax.set_xlim(wlist2[0]/(2*np.pi), wlist2[-1]/(2*np.pi))
plt.show()
```





3.8.3 Non-steadystate correlation function

More generally, we can also calculate correlation functions of the kind $\langle A(t_1 + t_2)B(t_1)\rangle$, i.e., the correlation function of a system that is not in its steadystate. In QuTiP, we can evoluate such correlation functions using the function *qutip.correlation_correlation_2op_2t*. The default behavior of this function is to return a matrix with the correlations as a function of the two time coordinates (t_1 and t_2).

import numpy as np
import pylab as plt

```
from qutip import *
times = np.linspace(0, 10.0, 200)
a = destroy(10)
x = a.dag() + a
H = a.dag() * a
alpha = 2.5
rho0 = coherent_dm(10, alpha)
corr = correlation_2op_2t(H, rho0, times, times, [np.sqrt(0.25) * a], x, x)
plt.pcolor(np.real(corr))
plt.xlabel(r'Time $t_2$')
plt.ylabel(r'Time $t_1$')
plt.title(r'Correlation $\left<x(t)x(0)\right>$')
plt.show()
```







Example: first-order optical coherence function

This example demonstrates how to calculate a correlation function on the form $\langle A(\tau)B(0)\rangle$ for a non-steady initial state. Consider an oscillator that is interacting with a thermal environment. If the oscillator initially is in a coherent state, it will gradually decay to a thermal (incoherent) state. The amount of coherence can be quantified using the first-order optical coherence function $g^{(1)}(\tau) = \frac{\langle a^{\dagger}(\tau)a(0)\rangle}{\sqrt{\langle a^{\dagger}(\tau)a(\tau)\rangle\langle a^{\dagger}(0)a(0)\rangle}}$. For a coherent state $|g^{(1)}(\tau)| = 1$, and for a completely incoherent (thermal) state $g^{(1)}(\tau) = 0$. The following code calculates and plots $g^{(1)}(\tau)$ as a function of τ .

```
import numpy as np
import pylab as plt
from qutip import *
N = 15
taus = np.linspace(0, 10.0, 200)
a = destroy(N)
H = 2 * np.pi * a.dag() * a
# collapse operator
G1 = 0.75
n_th = 2.00 # bath temperature in terms of excitation number
c_ops = [np.sqrt(G1 * (1 + n_th)) * a, np.sqrt(G1 * n_th) * a.dag()]
# start with a coherent state
rho0 = coherent_dm(N, 2.0)
# first calculate the occupation number as a function of time
n = mesolve(H, rho0, taus, c_ops, [a.dag() * a]).expect[0]
# calculate the correlation function G1 and normalize with n to obtain g1
G1 = correlation_2op_2t(H, rho0, None, taus, c_ops, a.dag(), a)
g1 = G1 / np.sqrt(n[0] * n)
plt.plot(taus, np.real(g1), 'b', lw=2)
plt.plot(taus, n, 'r', lw=2)
plt.title('Decay of a coherent state to an incoherent (thermal) state')
plt.xlabel(r'$\tau$')
plt.legend((r'First-order coherence function $g^{(1)}(\tau)$',
        r'occupation number $n(\tau)$'))
plt.show()
```





Example: second-order optical coherence function

The second-order optical coherence function, with time-delay τ , is defined as


$$g^{(2)}(\tau) = \frac{\langle a^{\dagger}(0)a^{\dagger}(\tau)a(\tau)a(0)\rangle}{\langle a^{\dagger}(0)a(0)\rangle^2}$$

For a coherent state $g^{(2)}(\tau) = 1$, for a thermal state $g^{(2)}(\tau = 0) = 2$ and it decreases as a function of time (bunched photons, they tend to appear together), and for a Fock state with n photons $g^{(2)}(\tau = 0) = n(n-1)/n^2 < 1$ and it increases with time (anti-bunched photons, more likely to arrive separated in time).

To calculate this type of correlation function with QuTiP, we can use qutip.correlation. $correlation_4op_1t$, which computes a correlation function on the form $\langle A(0)B(\tau)C(\tau)D(0)\rangle$ (four operators, one delay-time vector).

The following code calculates and plots $g^{(2)}(\tau)$ as a function of τ for a coherent, thermal and fock state.

```
import numpy as np
import pylab as plt
from qutip import *
N = 25
taus = np.linspace(0, 25.0, 200)
a = destroy(N)
H = 2 * np.pi * a.dag() * a
kappa = 0.25
n_th = 2.0 # bath temperature in terms of excitation number
c_ops = [np.sqrt(kappa * (1 + n_th)) * a, np.sqrt(kappa * n_th) * a.dag()]
states = [{'state': coherent_dm(N, np.sqrt(2)), 'label': "coherent state"},
         {'state': thermal_dm(N, 2), 'label': "thermal state"},
          {'state': fock_dm(N, 2), 'label': "Fock state"}]
fig, ax = plt.subplots(1, 1)
for state in states:
   rho0 = state['state']
    # first calculate the occupation number as a function of time
   n = mesolve(H, rho0, taus, c_ops, [a.dag() * a]).expect[0]
    # calculate the correlation function G2 and normalize with n(0)n(t) to
    # obtain g2
   G2 = correlation_3op_1t(H, rho0, taus, c_ops, a.dag(), a.dag() \star a, a)
   g2 = G2 / (n[0] * n)
   ax.plot(taus, np.real(g2), label=state['label'], lw=2)
ax.legend(loc=0)
ax.set_xlabel(r'$\tau$')
ax.set_ylabel(r'$g^{(2)}(\tau)$')
plt.show()
```



For convenience, the steps for calculating the second-order coherence function have been collected in the function *qutip.correlation.coherence_function_g2*.

3.9 Quantum Optimal Control

3.9.1 Introduction

In quantum control we look to prepare some specific state, effect some state-to-state transfer, or effect some transformation (or gate) on a quantum system. For a given quantum system there will always be factors that effect the dynamics that are outside of our control. As examples, the interactions between elements of the system or a magnetic field required to trap the system. However, there may be methods of affecting the dynamics in a controlled way, such as the time varying amplitude of the electric component of an interacting laser field. And so this leads to some questions; given a specific quantum system with known time-independent dynamics generator (referred to as the *drift* dynamics generators) and set of externally controllable fields for which the interaction can be described by *control* dynamics generators:

- 1. what states or transformations can we achieve (if any)?
- 2. what is the shape of the control pulse required to achieve this?

These questions are addressed as *controllability* and *quantum optimal control* [dAless08]. The answer to question of *controllability* is determined by the commutability of the dynamics generators and is formalised as the *Lie Algebra Rank Criterion* and is discussed in detail in [dAless08]. The solutions to the second question can be determined through optimal control algorithms, or control pulse optimisation.




Fig. 2: Schematic showing the principle of quantum control.

Quantum Control has many applications including NMR, quantum metrology, control of chemical reactions, and quantum information processing.

To explain the physics behind these algorithms we will first consider only finite-dimensional, closed quantum systems.

3.9.2 Closed Quantum Systems

In closed quantum systems the states can be represented by kets, and the transformations on these states are unitary operators. The dynamics generators are Hamiltonians. The combined Hamiltonian for the system is given by

$$H(t) = H_0 + \sum_{j=1}^{N} u_j(t) H_j$$

where H_0 is the drift Hamiltonian and the H_j are the control Hamiltonians. The u_j are time varying amplitude functions for the specific control.

The dynamics of the system are governed by Schrödingers equation.

$$\frac{d}{dt}\left|\psi\right\rangle = -iH(t)\left|\psi\right\rangle$$

Note we use units where $\hbar = 1$ throughout. The solutions to Schrödinger's equation are of the form:

$$\left|\psi(t)\right\rangle = U(t)\left|\psi_{0}\right\rangle$$

where ψ_0 is the state of the system at t = 0 and U(t) is a unitary operator on the Hilbert space containing the states. U(t) is a solution to the Schrödinger operator equation

$$\frac{d}{dt}U = -iH(t)U, \quad U(0) = \mathscr{W}$$

We can use optimal control algorithms to determine a set of u_j that will drive our system from $|\psi_0\rangle$ to $|\psi_1\rangle$, this is state-to-state transfer, or drive the system from some arbitrary state to a given state $|\psi_1\rangle$, which is state preparation, or effect some unitary transformation U_{target} , called gate synthesis. The latter of these is most important in quantum computation.

3.9.3 The GRAPE algorithm

The **GR**adient Ascent Pulse Engineering was first proposed in [2]. Solutions to Schrödinger's equation for a time-dependent Hamiltonian are not generally possible to obtain analytically. Therefore, a piecewise constant approximation to the pulse amplitudes is made. Time allowed for the system to evolve T is split into M timeslots

(typically these are of equal duration), during which the control amplitude is assumed to remain constant. The combined Hamiltonian can then be approximated as:

$$H(t) \approx H(t_k) = H_0 + \sum_{j=1}^N u_{jk} H_j$$

where k is a timeslot index, j is the control index, and N is the number of controls. Hence t_k is the evolution time at the start of the timeslot, and u_{jk} is the amplitude of control j throughout timeslot k. The time evolution operator, or propagator, within the timeslot can then be calculated as:

$$X_k := e^{-iH(t_k)\Delta t_k}$$

where Δt_k is the duration of the timeslot. The evolution up to (and including) any timeslot k (including the full evolution k = M) can the be calculated as

$$X(t_k) := X_k X_{k-1} \cdots X_1 X_0$$

If the objective is state-to-state transfer then $X_0 = |\psi_0\rangle$ and the target $X_{targ} = |\psi_1\rangle$, for gate synthesis $X_0 = U(0) = \mathbb{K}$ and the target $X_{targ} = U_{targ}$.

A *figure of merit* or *fidelity* is some measure of how close the evolution is to the target, based on the control amplitudes in the timeslots. The typical figure of merit for unitary systems is the normalised overlap of the evolution and the target.

$$f_{PSU} = \frac{1}{d} \left| \operatorname{tr} \{ X_{targ}^{\dagger} X(T) \} \right|$$

where d is the system dimension. In this figure of merit the absolute value is taken to ignore any differences in global phase, and $0 \le f \le 1$. Typically the fidelity error (or *infidelity*) is more useful, in this case defined as $\varepsilon = 1 - f_{PSU}$. There are many other possible objectives, and hence figures of merit.

As there are now $N \times M$ variables (the u_{ik}) and one parameter to minimise ε , then the problem becomes a finite multi-variable optimisation problem, for which there are many established methods, often referred to as 'hillclimbing' methods. The simplest of these to understand is that of steepest ascent (or descent). The gradient of the fidelity with respect to all the variables is calculated (or approximated) and a step is made in the variable space in the direction of steepest ascent (or descent). This method is a first order gradient method. In two dimensions this describes a method of climbing a hill by heading in the direction where the ground rises fastest. This analogy also clearly illustrates one of the main challenges in multi-variable optimisation, which is that all methods have a tendency to get stuck in local maxima. It is hard to determine whether one has found a global maximum or not - a local peak is likely not to be the highest mountain in the region. In quantum optimal control we can typically define an infidelity that has a lower bound of zero. We can then look to minimise the infidelity (from here on we will only consider optimising for infidelity minima). This means that we can terminate any pulse optimisation when the infidelity reaches zero (to a sufficient precision). This is however only possible for fully controllable systems; otherwise it is hard (if not impossible) to know that the minimum possible infidelity has been achieved. In the hill walking analogy the step size is roughly fixed to a stride, however, in computations the step size must be chosen. Clearly there is a trade-off here between the number of steps (or iterations) required to reach the minima and the possibility that we might step over a minima. In practice it is difficult to determine an efficient and effective step size.

The second order differentials of the infidelity with respect to the variables can be used to approximate the local landscape to a parabola. This way a step (or jump) can be made to where the minima would be if it were parabolic. This typically vastly reduces the number of iterations, and removes the need to guess a step size. The method where all the second differentials are calculated explicitly is called the *Newton-Raphson* method. However, calculating the second-order differentials (the Hessian matrix) can be computationally expensive, and so there are a class of methods known as *quasi-Newton* that approximate the Hessian based on successive iterations. The most popular of these (in quantum optimal control) is the Broyden–Fletcher–Goldfarb–Shanno algorithm (BFGS). The default method in the QuTiP Qtrl GRAPE implementation is the L-BFGS-B method in Scipy, which is a wrapper to the implementation described in [Byrd95]. This limited memory and bounded method does not need to store the entire Hessian, which reduces the computer memory required, and allows bounds to be set for variable values, which considering these are field amplitudes is often physical.

The pulse optimisation is typically far more efficient if the gradients can be calculated exactly, rather than approximated. For simple fidelity measures such as f_{PSU} this is possible. Firstly the propagator gradient for each timeslot

with respect to the control amplitudes is calculated. For closed systems, with unitary dynamics, a method using the eigendecomposition is used, which is efficient as it is also used in the propagator calculation (to exponentiate the combined Hamiltonian). More generally (for example open systems and symplectic dynamics) the Frechet derivative (or augmented matrix) method is used, which is described in [Flo12]. For other optimisation goals it may not be possible to calculate analytic gradients. In these cases it is necessary to approximate the gradients, but this can be very expensive, and can lead to other algorithms out-performing GRAPE.

3.9.4 The CRAB Algorithm

It has been shown [Lloyd14], the dimension of a quantum optimal control problem is a polynomial function of the dimension of the manifold of the time-polynomial reachable states, when allowing for a finite control precision and evolution time. You can think of this as the information content of the pulse (as being the only effective input) being very limited e.g. the pulse is compressible to a few bytes without loosing the target.

This is where the Chopped RAndom Basis (CRAB) algorithm [Doria11], [Caneva11] comes into play: Since the pulse complexity is usually very low, it is sufficient to transform the optimal control problem to a few parameter search by introducing a physically motivated function basis that builds up the pulse. Compared to the number of time slices needed to accurately simulate quantum dynamics (often equals basis dimension for Gradient based algorithms), this number is lower by orders of magnitude, allowing CRAB to efficiently optimize smooth pulses with realistic experimental constraints. It is important to point out, that CRAB does not make any suggestion on the basis function to be used. The basis must be chosen carefully considered, taking into account a priori knowledge of the system (such as symmetries, magnitudes of scales,...) and solution (e.g. sign, smoothness, bang-bang behavior, singularities, maximum excursion or rate of change,...). By doing so, this algorithm allows for native integration of experimental constraints such as maximum frequencies allowed, maximum amplitude, smooth ramping up and down of the pulse and many more. Moreover initial guesses, if they are available, can (however not have to) be included to speed up convergence.

As mentioned in the GRAPE paragraph, for CRAB local minima arising from algorithmic design can occur, too. However, for CRAB a 'dressed' version has recently been introduced [Rach15] that allows to escape local minima.

For some control objectives and/or dynamical quantum descriptions, it is either not possible to derive the gradient for the cost functional with respect to each time slice or it is computationally expensive to do so. The same can apply for the necessary (reverse) propagation of the co-state. All this trouble does not occur within CRAB as those elements are not in use here. CRAB, instead, takes the time evolution as a black-box where the pulse goes as an input and the cost (e.g. infidelity) value will be returned as an output. This concept, on top, allows for direct integration in a closed loop experimental environment where both the preliminarily open loop optimization, as well as the final adoption, and integration to the lab (to account for modeling errors, experimental systematic noise, ...) can be done all in one, using this algorithm.

3.9.5 Optimal Quantum Control in QuTiP

There are two separate implementations of optimal control inside QuTiP. The first is an implementation of first order GRAPE, and is not further described here, but there are the example notebooks. The second is referred to as Qtrl (when a distinction needs to be made) as this was its name before it was integrated into QuTiP. Qtrl uses the Scipy optimize functions to perform the multi-variable optimisation, typically the L-BFGS-B method for GRAPE and Nelder-Mead for CRAB. The GRAPE implementation in Qtrl was initially based on the open-source package DYNAMO, which is a MATLAB implementation, and is described in [DYNAMO]. It has since been restructured and extended for flexibility and compatibility within QuTiP.

The rest of this section describes the Qtrl implementation and how to use it.

Object Model The Qtrl code is organised in a hierarchical object model in order to try and maximise configurability whilst maintaining some clarity. It is not necessary to understand the model in order to use the pulse optimisation functions, but it is the most flexible method of using Qtrl. If you just want to use a simple single function call interface, then jump to *Using the pulseoptim functions*




Fig. 3: Qtrl code object model.

The object's properties and methods are described in detail in the documentation, so that will not be repeated here.

- **OptimConfig** The OptimConfig object is used simply to hold configuration parameters used by all the objects. Typically this is the subclass types for the other objects and parameters for the users specific requirements. The loadparams module can be used read parameter values from a configuration file.
- **Optimizer** This acts as a wrapper to the Scipy.optimize functions that perform the work of the pulse optimisation algorithms. Using the main classes the user can specify which of the optimisation methods are to be used. There are subclasses specifically for the BFGS and L-BFGS-B methods. There is another subclass for using the CRAB algorithm.
- **Dynamics** This is mainly a container for the lists that hold the dynamics generators, propagators, and time evolution operators in each timeslot. The combining of dynamics generators is also complete by this object. Different subclasses support a range of types of quantum systems, including closed systems with unitary dynamics, systems with quadratic Hamiltonians that have Gaussian states and symplectic transforms, and a general subclass that can be used for open system dynamics with Lindbladian operators.
- **PulseGen** There are many subclasses of pulse generators that generate different types of pulses as the initial amplitudes for the optimisation. Often the goal cannot be achieved from all starting conditions, and then typically some kind of random pulse is used and repeated optimisations are performed until the desired infidelity is reached or the minimum infidelity found is reported. There is a specific subclass that is used by the CRAB algorithm to generate the pulses based on the basis coefficients that are being optimised.
- **TerminationConditions** This is simply a convenient place to hold all the properties that will determine when the single optimisation run terminates. Limits can be set for number of iterations, time, and of course the target infidelity.
- **Stats** Performance data are optionally collected during the optimisation. This object is shared to a single location to store, calculate and report run statistics.
- **FidelityComputer** The subclass of the fidelity computer determines the type of fidelity measure. These are closely linked to the type of dynamics in use. These are also the most commonly user customised subclasses.
- **PropagatorComputer** This object computes propagators from one timeslot to the next and also the propagator gradient. The options are using the spectral decomposition or Frechet derivative, as discussed above.
- TimeslotComputer Here the time evolution is computed by calling the methods of the other computer objects.
- **OptimResult** The result of a pulse optimisation run is returned as an object with properties for the outcome in terms of the infidelity, reason for termination, performance statistics, final evolution, and more.

3.9.6 Using the pulseoptim functions

The simplest method for optimising a control pulse is to call one of the functions in the pulseoptim module. This automates the creation and configuration of the necessary objects, generation of initial pulses, running the optimisation and returning the result. There are functions specifically for unitary dynamics, and also specifically for the CRAB algorithm (GRAPE is the default). The optimise_pulse function can in fact be used for unitary

dynamics and / or the CRAB algorithm, the more specific functions simply have parameter names that are more familiar in that application.

A semi-automated method is to use the create_optimizer_objects function to generate and configure all the objects, then manually set the initial pulse and call the optimisation. This would be more efficient when repeating runs with different starting conditions.

3.10 Plotting on the Bloch Sphere

Important: Updated in QuTiP version 3.0.

3.10.1 Introduction

When studying the dynamics of a two-level system, it is often convent to visualize the state of the system by plotting the state-vector or density matrix on the Bloch sphere. In QuTiP, we have created two different classes to allow for easy creation and manipulation of data sets, both vectors and data points, on the Bloch sphere. The qutip.Bloch class, uses Matplotlib to render the Bloch sphere, where as qutip.Bloch3d uses the Mayavi rendering engine to generate a more faithful 3D reconstruction of the Bloch sphere.

3.10.2 The Bloch and Bloch3d Classes

In QuTiP, creating a Bloch sphere is accomplished by calling either:


```
In [1]: b = Bloch()
```

which will load an instance of the qutip.Bloch class, or using:


>>> b3d = Bloch3d()

that loads the qutip.Bloch3d version. Before getting into the details of these objects, we can simply plot the blank Bloch sphere associated with these instances via:

In [2]: b.show()




or



In addition to the show() command, the Bloch class has the following functions:


Name	Input Parameters (#=optional)	Description
add_points(pnts,#meth)	pnts list/array of (x,y,z) points, meth='m' (default	Adds a single or set of data points to be
	meth='s') will plot a collection of points as multi-	plotted on the sphere.
	colored data points.	
add_states(state,#kind)	state Qobj or list/array of Qobj's representing state	Input multiple states as a list or array
	or density matrix of a two-level system, kind (op-	
	tional) string specifying if state should be plotted	
	as point ('point') or vector (default).	
add_vectors(vec)	<i>vec</i> list/array of (x,y,z) points giving direction and	adds single or multiple vectors to plot.
	length of state vectors.	
clear()		Removes all data from Bloch sphere.
		Keeps customized figure properties.
save(#format,#dirc)	<i>format</i> format (default='png') of output file, <i>dirc</i>	Saves Bloch sphere to a file.
	(default=cwd) output directory	
show()		Generates Bloch sphere with given data.

As an example, we can add a single data point:




and then a single vector:

In [6]: vec = [0,1,0]
In [7]: b.add_vectors(vec)
In [8]: b.show()
<Figure size 500x500 with 1 Axes>



and then add another vector corresponding to the $|\mathrm{up}\rangle$ state:

```
In [9]: up = basis(2,0)
In [10]: b.add_states(up)
In [11]: b.show()
<Figure size 500x500 with 1 Axes>
```




Notice that when we add more than a single vector (or data point), a different color will automatically be applied to the later data set (mod 4). In total, the code for constructing our Bloch sphere with one vector, one state, and a single data point is:


In [12]: b = Bloch()

(continues on next page)

```
(continued from previous page)
In [13]: pnt = [1./np.sqrt(3), 1./np.sqrt(3), 1./np.sqrt(3)]
In [14]: b.add_points(pnt)
In [15]: vec = [0,1,0]
In [16]: b.add_vectors(vec)
In [17]: up = basis(2,0)
In [18]: b.add_states(up)
In [19]: b.show()
```




where we have removed the extra show() commands. Replacing b=Bloch() with b=Bloch3d() in the above code generates the following 3D Bloch sphere.




We can also plot multiple points, vectors, and states at the same time by passing list or arrays instead of individual elements. Before giving an example, we can use the *clear()* command to remove the current data from our Bloch sphere instead of creating a new instance:

```
In [20]: b.clear()
In [21]: b.show()
<Figure size 500x500 with 1 Axes>
```




Now on the same Bloch sphere, we can plot the three states associated with the x, y, and z directions:

```
In [22]: x = (basis(2,0)+(1+0j)*basis(2,1)).unit()
In [23]: y = (basis(2,0)+(0+1j)*basis(2,1)).unit()
In [24]: z = (basis(2,0)+(0+0j)*basis(2,1)).unit()
In [25]: b.add_states([x,y,z])
In [26]: b.show()
<Figure size 500x500 with 1 Axes>
```




a similar method works for adding vectors:

In [27]: b.clear()
In [28]: vec = [[1,0,0],[0,1,0],[0,0,1]]
In [29]: b.add_vectors(vec)
In [30]: b.show()
<Figure size 500x500 with 1 Axes>




Adding multiple points to the Bloch sphere works slightly differently than adding multiple states or vectors. For example, lets add a set of 20 points around the equator (after calling *clear()*):

```
In [31]: xp = [np.cos(th) for th in np.linspace(0, 2*pi, 20)]
In [32]: yp = [np.sin(th) for th in np.linspace(0, 2*pi, 20)]
In [33]: zp = np.zeros(20)
In [34]: pnts = [xp, yp, zp]
In [35]: b.add_points(pnts)
In [36]: b.show()
<Figure size 500x500 with 1 Axes>
```




Notice that, in contrast to states or vectors, each point remains the same color as the initial point. This is because adding multiple data points using the add_points function is interpreted, by default, to correspond to a single data point (single qubit state) plotted at different times. This is very useful when visualizing the dynamics of a qubit. An example of this is given in the example . If we want to plot additional qubit states we can call additional *add_points* functions:

```
In [37]: xz = np.zeros(20)
In [38]: yz = [np.sin(th) for th in np.linspace(0, pi, 20)]
In [39]: zz = [np.cos(th) for th in np.linspace(0, pi, 20)]
In [40]: b.add_points([xz, yz, zz])
In [41]: b.show()
<Figure size 500x500 with 1 Axes>
```




The color and shape of the data points is varied automatically by the Bloch class. Notice how the color and point markers change for each set of data. Again, we have had to call add_points twice because adding more than one set of multiple data points is *not* supported by the add_points function.

What if we want to vary the color of our points. We can tell the qutip.Bloch class to vary the color of each point according to the colors listed in the b.point_color list (see *Configuring the Bloch sphere* below). Again after clear():




Now, the data points cycle through a variety of predefined colors. Now lets add another set of points, but this time we want the set to be a single color, representing say a qubit going from the $|up\rangle$ state to the $|down\rangle$ state in the y-z plane:

```
In [48]: xz = np.zeros(20)
In [49]: yz = [np.sin(th) for th in np.linspace(0, pi ,20)]
In [50]: zz = [np.cos(th) for th in np.linspace(0, pi, 20)]
In [51]: b.add_points([xz, yz, zz]) # no 'm'
In [52]: b.show()
<Figure size 500x500 with 1 Axes>
```



Again, the same plot can be generated using the qutip.Bloch3d class by replacing Bloch with Bloch3d:



A more slick way of using this 'multi' color feature is also given in the example, where we set the color of the markers as a function of time.

Differences Between Bloch and Bloch3d

While in general the Bloch and Bloch3d classes are interchangeable, there are some important differences to consider when choosing between them.

- The Bloch class uses Matplotlib to generate figures. As such, the data plotted on the sphere is in reality just a 2D object. In contrast the Bloch3d class uses the 3D rendering engine from VTK via mayavi to generate the sphere and the included data. In this sense the Bloch3d class is much more advanced, as objects are rendered in 3D leading to a higher quality figure.
- Only the Bloch class can be embedded in a Matplotlib figure window. Thus if you want to combine a Bloch sphere with another figure generated in QuTiP, you can not use Bloch3d. Of course you can always post-process your figures using other software to get the desired result.
- Due to limitations in the rendering engine, the Bloch3d class does not support LaTex for text. Again, you can get around this by post-processing.
- The user customizable attributes for the Bloch and Bloch3d classes are not identical. Therefore, if you change the properties of one of the classes, these changes will cause an exception if the class is switched.

3.10.3 Configuring the Bloch sphere

Bloch Class Options

At the end of the last section we saw that the colors and marker shapes of the data plotted on the Bloch sphere are automatically varied according to the number of points and vectors added. But what if you want a different choice of color, or you want your sphere to be purple with different axes labels? Well then you are in luck as the Bloch class has 22 attributes which one can control. Assuming b=Bloch():

Attribute	Function	Default Setting
b.axes	Matplotlib axes instance for animations. Set by	None
	axes keyword arg.	
b.fig	User supplied Matplotlib Figure instance. Set by	None
	fig keyword arg.	
b.font_color	Color of fonts	'black'
b.font_size	Size of fonts	20
b.frame_alpha	Transparency of wireframe	0.1
b.frame_color	Color of wireframe	'gray'
b.frame_width	Width of wireframe	1
b.point_color	List of colors for Bloch point markers to cycle	['b','r','g','#CC6600']
	through	
b.point_marker	List of point marker shapes to cycle through	['o','s','d','^']
b.point_size	List of point marker sizes (not all markers look the	[55,62,65,75]
	same size when plotted)	
b.sphere_alpha	Transparency of Bloch sphere	0.2
b.sphere_color	Color of Bloch sphere	'#FFDDDD'
b.size	Sets size of figure window	[7,7] (700x700 pixels)
b.vector_color	List of colors for Bloch vectors to cycle through	['g','#CC6600','b','r']
b.vector_width	Width of Bloch vectors	4
b.view	Azimuthal and Elevation viewing angles	[-60,30]
b.xlabel	Labels for x-axis	[' x ,''] +x and -x (labels use LaTeX)
b.xlpos	Position of x-axis labels	[1.1,-1.1]
b.ylabel	Labels for y-axis	['\$y\$',''] +y and -y (labels use LaTeX)
b.ylpos	Position of y-axis labels	[1.2,-1.2]
b.zlabel	Labels for z-axis	[' $left 0\right>$ ',' $left 1\right>$ '] +z and -z (la-
		bels use LaTeX)
b.zlpos	Position of z-axis labels	[1.2,-1.2]

Bloch3d Class Options

The Bloch3d sphere is also customizable. Note however that the attributes for the Bloch3d class are not in one-to-one correspondence to those of the Bloch class due to the different underlying rendering engines. Assuming b=Bloch3d():

Attribute	Function	Default Setting
b.fig	User supplied Mayavi Figure instance. Set by	None
	fig keyword arg.	
b.font_color	Color of fonts	'black'
b.font_scale	Scale of fonts	0.08
b.frame	Draw wireframe for sphere?	True
b.frame_alpha	Transparency of wireframe	0.05
b.frame_color	Color of wireframe	'gray'
b.frame_num	Number of wireframe elements to draw	8
b.frame_radius	Radius of wireframe lines	0.005
b.point_color	List of colors for Bloch point markers to cycle	['r', 'g', 'b', 'y']
	through	
b.point_mode	Type of point markers to draw	sphere
b.point_size	Size of points	0.075
b.sphere_alpha	Transparency of Bloch sphere	0.1
b.sphere_color	Color of Bloch sphere	ʻ#808080'
b.size	Sets size of figure window	[500,500] (500x500 pixels)
b.vector_color	List of colors for Bloch vectors to cycle through	['r', 'g', 'b', 'y']
b.vector_width	Width of Bloch vectors	3
b.view	Azimuthal and Elevation viewing angles	[45,65]
b.xlabel	Labels for x-axis	[' x>', ''] +x and -x
b.xlpos	Position of x-axis labels	[1.07,-1.07]
b.ylabel	Labels for y-axis	['\$y\$',''] +y and -y
b.ylpos	Position of y-axis labels	[1.07,-1.07]
b.zlabel	Labels for z-axis	[' 0>', ' 1>'] +z and -z
b.zlpos	Position of z-axis labels	[1.07,-1.07]

These properties can also be accessed via the print command:

```
In [53]: b = Bloch()
In [54]: print(b)
Bloch data:
_____
Number of points: 0
Number of vectors: 0
Bloch sphere properties:
            _____
        ___
font_color: black
font_size: 20
frame_alpha: 0.2
frame_color: gray
frame_width: 1
point_color: ['b', 'r', 'g', '#CC6600']
point_marker: ['o', 's', 'd', '^']
point_size: [25_32_35_45]
                     [25, 32, 35, 45]
point_size:
sphere_alpha: 0.2
sphere_color: #FFDDDD
                     [5, 5]
figsize:
vector_color: ['g', '#CC6600', 'b', 'r']
vector_width: 3
vector_style:
                       - | >
vector_mutation: 20
                      [-60, 30]
view:
                      ['$x$', '']
xlabel:
                     [1.2, -1.2]
xlpos:
                      ['$y$', '']
ylabel:
```

(continues on next page)

(continued from previous page)

```
ylpos: [1.2, -1.2]
zlabel: ['$\\left|0\\right>$', '$\\left|1\\right>$']
zlpos: [1.2, -1.2]
```

3.10.4 Animating with the Bloch sphere

The Bloch class was designed from the outset to generate animations. To animate a set of vectors or data points the basic idea is: plot the data at time t1, save the sphere, clear the sphere, plot data at t2,... The Bloch sphere will automatically number the output file based on how many times the object has been saved (this is stored in b.savenum). The easiest way to animate data on the Bloch sphere is to use the save() method and generate a series of images to convert into an animation. However, as of Matplotlib version 1.1, creating animations is built-in. We will demonstrate both methods by looking at the decay of a qubit on the bloch sphere.

Example: Qubit Decay

The code for calculating the expectation values for the Pauli spin operators of a qubit decay is given below. This code is common to both animation examples.

```
from qutip import *
from scipy import *
def qubit_integrate(w, theta, gamma1, gamma2, psi0, tlist):
    # operators and the hamiltonian
    sx = sigmax(); sy = sigmay(); sz = sigmaz(); sm = sigmam()
    H = w * (cos(theta) * sz + sin(theta) * sx)
    # collapse operators
    c_{op_list} = []
    n_th = 0.5 # temperature
    rate = gamma1 * (n_th + 1)
    if rate > 0.0: c_op_list.append(sqrt(rate) * sm)
    rate = gamma1 * n_th
    if rate > 0.0: c_op_list.append(sqrt(rate) * sm.dag())
    rate = gamma2
    if rate > 0.0: c_op_list.append(sqrt(rate) * sz)
    # evolve and calculate expectation values
    output = mesolve(H, psi0, tlist, c_op_list, [sx, sy, sz])
    return output.expect[0], output.expect[1], output.expect[2]
## calculate the dynamics
w = 1.0 * 2 * pi # qubit angular frequency
theta = 0.2 * pi  # qubit angle from sigma_z axis (toward sigma_x axis)
gamma1 = 0.5  # qubit relaxation rate
gamma2 = 0.2  # gubit dophasing unit
gamma2 = 0.2
                  # qubit dephasing rate
# initial state
a = 1.0
psi0 = (a \times basis(2,0) + (1-a) \times basis(2,1)) / (sqrt(a \times 2 + (1-a) \times 2))
tlist = linspace(0, 4, 250)
#expectation values for ploting
sx, sy, sz = qubit_integrate(w, theta, gamma1, gamma2, psi0, tlist)
```

Generating Images for Animation

An example of generating images for generating an animation outside of Python is given below:

```
import numpy as np
b = Bloch()
b.vector_color = ['r']
b.view = [-40,30]
for i in range(len(sx)):
    b.clear()
    b.add_vectors([np.sin(theta),0,np.cos(theta)])
    b.add_points([sx[:i+1],sy[:i+1],sz[:i+1]])
    b.save(dirc='temp') #saving images to temp directory in current working_
    directory
```

Generating an animation using ffmpeg (for example) is fairly simple:

ffmpeg -r 20 -b 1800 -i bloch_%01d.png bloch.mp4

Directly Generating an Animation

Important: Generating animations directly from Matplotlib requires installing either mencoder or ffmpeg. While either choice works on linux, it is best to choose ffmpeg when running on the Mac. If using macports just do: sudo port install ffmpeg.

The code to directly generate an mp4 movie of the Qubit decay is as follows:

```
from pylab import *
import matplotlib.animation as animation
from mpl_toolkits.mplot3d import Axes3D
fiq = fiqure()
ax = Axes3D(fiq,azim=-40,elev=30)
sphere = Bloch(axes=ax)
def animate(i):
    sphere.clear()
    sphere.add_vectors([np.sin(theta),0,np.cos(theta)])
    sphere.add_points([sx[:i+1], sy[:i+1], sz[:i+1]])
    sphere.make_sphere()
    return ax
def init():
    sphere.vector color = ['r']
    return ax
ani = animation.FuncAnimation(fig, animate, np.arange(len(sx)),
                            init_func=init, blit=True, repeat=False)
ani.save('bloch_sphere.mp4', fps=20)
```

The resulting movie may be viewed here: bloch_decay.mp4

3.11 Visualization of quantum states and processes

Visualization is often an important complement to a simulation of a quantum mechanical system. The first method of visualization that come to mind might be to plot the expectation values of a few selected operators. But on top

of that, it can often be instructive to visualize for example the state vectors or density matices that describe the state of the system, or how the state is transformed as a function of time (see process tomography below). In this section we demonstrate how QuTiP and matplotlib can be used to perform a few types of visualizations that often can provide additional understanding of quantum system.

3.11.1 Fock-basis probability distribution

In quantum mechanics probability distributions plays an important role, and as in statistics, the expectation values computed from a probability distribution does not reveal the full story. For example, consider an quantum harmonic oscillator mode with Hamiltonian $H = \hbar \omega a^{\dagger} a$, which is in a state described by its density matrix ρ , and which on average is occupied by two photons, $\text{Tr}[\rho a^{\dagger} a] = 2$. Given this information we cannot say whether the oscillator is in a Fock state, a thermal state, a coherent state, etc. By visualizing the photon distribution in the Fock state basis important clues about the underlying state can be obtained.


One convenient way to visualize a probability distribution is to use histograms. Consider the following histogram visualization of the number-basis probability distribution, which can be obtained from the diagonal of the density matrix, for a few possible oscillator states with on average occupation of two photons.

First we generate the density matrices for the coherent, thermal and fock states.

```
In [1]: N = 20
In [2]: rho_coherent = coherent_dm(N, np.sqrt(2))
In [3]: rho_thermal = thermal_dm(N, 2)
In [4]: rho_fock = fock_dm(N, 2)
```


Next, we plot histograms of the diagonals of the density matrices:


```
In [5]: fig, axes = plt.subplots(1, 3, figsize=(12,3))
In [6]: bar0 = axes[0].bar(np.arange(0, N)-.5, rho_coherent.diag())
In [7]: lbl0 = axes[0].set_title("Coherent state")
In [8]: lim0 = axes[0].set_xlim([-.5, N])
In [9]: bar1 = axes[1].bar(np.arange(0, N)-.5, rho_thermal.diag())
In [10]: lbl1 = axes[1].set_title("Thermal state")
In [11]: lim1 = axes[1].set_xlim([-.5, N])
In [12]: bar2 = axes[2].bar(np.arange(0, N)-.5, rho_fock.diag())
In [13]: lbl2 = axes[2].set_title("Fock state")
In [14]: lim2 = axes[2].set_xlim([-.5, N])
```



All these states correspond to an average of two photons, but by visualizing the photon distribution in Fock basis the differences between these states are easily appreciated.

One frequently need to visualize the Fock-distribution in the way described above, so QuTiP provides a convenience function for doing this, see *qutip.visualization.plot_fock_distribution*, and the following example:





3.11.2 Quasi-probability distributions

The probability distribution in the number (Fock) basis only describes the occupation probabilities for a discrete set of states. A more complete phase-space probability-distribution-like function for harmonic modes are the Wigner and Husumi Q-functions, which are full descriptions of the quantum state (equivalent to the density matrix). These are called quasi-distribution functions because unlike real probability distribution functions they can for example be negative. In addition to being more complete descriptions of a state (compared to only the occupation probabilities plotted above), these distributions are also great for demonstrating if a quantum state is quantum mechanical, since for example a negative Wigner function is a definite indicator that a state is distinctly nonclassical.

Wigner function


In QuTiP, the Wigner function for a harmonic mode can be calculated with the function *qutip.wigner*. *wigner*. It takes a ket or a density matrix as input, together with arrays that define the ranges of the phase-space coordinates (in the x-y plane). In the following example the Wigner functions are calculated and plotted for the same three states as in the previous section.

```
In [22]: xvec = np.linspace(-5,5,200)
In [23]: W_coherent = wigner(rho_coherent, xvec, xvec)
In [24]: W_thermal = wigner(rho_thermal, xvec, xvec)
In [25]: W_fock = wigner(rho_fock, xvec, xvec)
In [26]: # plot the results
```

(continues on next page)

(continued from previous page)

```
In [27]: fig, axes = plt.subplots(1, 3, figsize=(12,3))
In [28]: cont0 = axes[0].contourf(xvec, xvec, W_coherent, 100)
In [29]: lbl0 = axes[0].set_title("Coherent state")
In [30]: cont1 = axes[1].contourf(xvec, xvec, W_thermal, 100)
In [31]: lbl1 = axes[1].set_title("Thermal state")
In [32]: cont0 = axes[2].contourf(xvec, xvec, W_fock, 100)
In [33]: lbl2 = axes[2].set_title("Fock state")
In [34]: plt.show()
```





Custom Color Maps

The main objective when plotting a Wigner function is to demonstrate that the underlying state is nonclassical, as indicated by negative values in the Wigner function. Therefore, making these negative values stand out in a figure is helpful for both analysis and publication purposes. Unfortunately, all of the color schemes used in Matplotlib (or any other plotting software) are linear colormaps where small negative values tend to be near the same color as the zero values, and are thus hidden. To fix this dilemma, QuTiP includes a nonlinear colormap function utilities.wigner_cmap that colors all negative values differently than positive or zero values. Below is a demonstration of how to use this function in your Wigner figures:

```
In [35]: import matplotlib as mpl
In [36]: from matplotlib import cm
In [37]: psi = (basis(10, 0) + basis(10, 3) + basis(10, 9)).unit()
In [38]: xvec = np.linspace(-5, 5, 500)
In [39]: W = wigner(psi, xvec, xvec)
In [40]: wmap = wigner_cmap(W)  # Generate Wigner colormap
In [41]: nrm = mpl.colors.Normalize(-W.max(), W.max())
In [42]: fig, axes = plt.subplots(1, 2, figsize=(10, 4))
In [43]: plt1 = axes[0].contourf(xvec, xvec, W, 100, cmap=cm.RdBu, norm=nrm)
In [44]: axes[0].set_title("Standard Colormap");
In [45]: cb1 = fig.colorbar(plt1, ax=axes[0])
```

(continues on next page)






Husimi Q-function

The Husimi Q function is, like the Wigner function, a quasiprobability distribution for harmonic modes. It is defined as

$$Q(\alpha) = \frac{1}{\pi} \left\langle \alpha | \rho | \alpha \right\rangle$$

where $|\alpha\rangle$ is a coherent state and $\alpha = x + iy$. In QuTiP, the Husimi Q function can be computed given a state ket or density matrix using the function *qutip.wigner.qfunc*, as demonstrated below.

```
In [51]: Q_coherent = qfunc(rho_coherent, xvec, xvec)
In [52]: Q_thermal = qfunc(rho_thermal, xvec, xvec)
In [53]: Q_fock = qfunc(rho_fock, xvec, xvec)
In [54]: fig, axes = plt.subplots(1, 3, figsize=(12,3))
In [55]: cont0 = axes[0].contourf(xvec, xvec, Q_coherent, 100)
In [56]: lbl0 = axes[0].set_title("Coherent state")
In [57]: cont1 = axes[1].contourf(xvec, xvec, Q_thermal, 100)
In [58]: lbl1 = axes[1].set_title("Thermal state")
In [59]: cont0 = axes[2].contourf(xvec, xvec, Q_fock, 100)
In [60]: lbl2 = axes[2].set_title("Fock state")
In [61]: plt.show()
```




3.11.3 Visualizing operators

Sometimes, it may also be useful to directly visualizing the underlying matrix representation of an operator. The density matrix, for example, is an operator whose elements can give insights about the state it represents, but one might also be interesting in plotting the matrix of an Hamiltonian to inspect the structure and relative importance of various elements.


QuTiP offers a few functions for quickly visualizing matrix data in the form of histograms, qutip.visualization.matrix_histogram and qutip.visualization. matrix_histogram_complex, and as Hinton diagram of weighted squares, qutip.visualization. hinton. These functions takes a qutip.Qobj.Qobj as first argument, and optional arguments to, for example, set the axis labels and figure title (see the function's documentation for details).

For example, to illustrate the use of *qutip.visualization.matrix_histogram*, let's visualize of the Jaynes-Cummings Hamiltonian:

```
In [62]: N = 5
In [63]: a = tensor(destroy(N), qeye(2))
In [64]: b = tensor(qeye(N), destroy(2))
In [65]: sx = tensor(geve(N), sigmax())
In [66]: H = a.dag() * a + sx - 0.5 * (a * b.dag() + a.dag() * b)
In [67]: # visualize H
In [68]: lbls_list = [[str(d) for d in range(N)], ["u", "d"]]
In [69]: xlabels = []
In [70]: for inds in tomography._index_permutations([len(lbls) for lbls in lbls_
\rightarrow list]):
             xlabels.append("".join([lbls_list[k][inds[k]]
   . . . . :
                                      for k in range(len(lbls_list))]))
   . . . . :
   . . . . :
In [71]: fig, ax = matrix_histogram(H, xlabels, xlabels, limits=[-4,4])
In [72]: ax.view_init(azim=-55, elev=45)
In [73]: plt.show()
```



Similarly, we can use the function *qutip.visualization.hinton*, which is used below to visualize the corresponding steadystate density matrix:



$|0,0|0,1|1,0|1,1|2,0|2,1|3,0|3,1|4,0|4,1\rangle$

3.11.4 Quantum process tomography

Quantum process tomography (QPT) is a useful technique for characterizing experimental implementations of quantum gates involving a small number of qubits. It can also be a useful theoretical tool that can give insight in how a process transforms states, and it can be used for example to study how noise or other imperfections deteriorate a gate. Whereas a fidelity or distance measure can give a single number that indicates how far from ideal a gate is, a quantum process tomography analysis can give detailed information about exactly what kind of errors various imperfections introduce.

The idea is to construct a transformation matrix for a quantum process (for example a quantum gate) that describes how the density matrix of a system is transformed by the process. We can then decompose the transformation in some operator basis that represent well-defined and easily interpreted transformations of the input states.

To see how this works (see e.g. [Moh08] for more details), consider a process that is described by quantum map $\epsilon(\rho_{\rm in}) = \rho_{\rm out}$, which can be written

$$\epsilon(\rho_{\rm in}) = \rho_{\rm out} = \sum_{i}^{N^2} A_i \rho_{\rm in} A_i^{\dagger}, \qquad (3.32)$$

where N is the number of states of the system (that is, ρ is represented by an $[N \times N]$ matrix). Given an orthogonal operator basis of our choice $\{B_i\}_i^{N^2}$, which satisfies $\text{Tr}[B_i^{\dagger}B_j] = N\delta_{ij}$, we can write the map as

$$\epsilon(\rho_{\rm in}) = \rho_{\rm out} = \sum_{mn} \chi_{mn} B_m \rho_{\rm in} B_n^{\dagger}.$$
(3.33)

where $\chi_{mn} = \sum_{ij} b_{im} b_{jn}^*$ and $A_i = \sum_m b_{im} B_m$. Here, matrix χ is the transformation matrix we are after, since it describes how much $B_m \rho_{in} B_n^{\dagger}$ contributes to ρ_{out} .

In a numerical simulation of a quantum process we usually do not have access to the quantum map in the form Eq. (3.32). Instead, what we usually can do is to calculate the propagator U for the density matrix in superoperator form, using for example the QuTiP function qutip.propagator.propagator. We can then write

$$\epsilon(\tilde{\rho}_{\rm in}) = U\tilde{\rho}_{\rm in} = \tilde{\rho}_{\rm out}$$

where $\tilde{\rho}$ is the vector representation of the density matrix ρ . If we write Eq. (3.33) in superoperator form as well we obtain

$$\tilde{\rho}_{\rm out} = \sum_{mn} \chi_{mn} \tilde{B}_m \tilde{B}_n^{\dagger} \tilde{\rho}_{\rm in} = U \tilde{\rho}_{\rm in}$$

so we can identify

$$U = \sum_{mn} \chi_{mn} \tilde{B}_m \tilde{B}_n^{\dagger}.$$

Now this is a linear equation systems for the $N^2 \times N^2$ elements in χ . We can solve it by writing χ and the superoperator propagator as $[N^4]$ vectors, and likewise write the superoperator product $\tilde{B}_m \tilde{B}_n^{\dagger}$ as a $[N^4 \times N^4]$ matrix M:

$$U_I = \sum_J^{N^4} M_{IJ} \chi_J$$

with the solution

$$\chi = M^{-1}U$$

Note that to obtain χ with this method we have to construct a matrix M with a size that is the square of the size of the superoperator for the system. Obviously, this scales very badly with increasing system size, but this method can still be a very useful for small systems (such as system comprised of a small number of coupled qubits).

Implementation in QuTiP

In QuTiP, the procedure described above is implemented in the function qutip.tomography.qpt, which returns the χ matrix given a density matrix propagator. To illustrate how to use this function, let's consider the *i*-SWAP gate for two qubits. In QuTiP the function qutip.gates.iswap generates the unitary transformation for the state kets:

In [77]: U_psi = iswap()

To be able to use this unitary transformation matrix as input to the function *qutip.tomography.qpt*, we first need to convert it to a transformation matrix for the corresponding density matrix:

In [78]: U_rho = spre(U_psi) * spost(U_psi.dag())


Next, we construct a list of operators that define the basis $\{B_i\}$ in the form of a list of operators for each composite system. At the same time, we also construct a list of corresponding labels that will be used when plotting the χ matrix.

```
In [79]: op_basis = [[qeye(2), sigmax(), sigmay(), sigmaz()]] * 2
```

```
In [80]: op_label = [["i", "x", "y", "z"]] * 2
```

We are now ready to compute χ using *qutip.tomography.qpt*, and to plot it using *qutip.tomography.qpt_plot_combined*.

```
In [81]: chi = qpt(U_rho, op_basis)
In [82]: fig = qpt_plot_combined(chi, op_label, r'$i$SWAP')
In [83]: plt.show()
```



For a slightly more advanced example, where the density matrix propagator is calculated from the dynamics of a system defined by its Hamiltonian and collapse operators using the function *qutip.propagator*. *propagator*, see notebook "Time-dependent master equation: Landau-Zener transitions" on the tutorials section on the QuTiP web site.

3.12 Parallel computation

3.12.1 Parallel map and parallel for-loop

Often one is interested in the output of a given function as a single-parameter is varied. For instance, we can calculate the steady-state response of our system as the driving frequency is varied. In cases such as this, where each iteration is independent of the others, we can speedup the calculation by performing the iterations in parallel. In QuTiP, parallel computations may be performed using the *qutip.parallel.parallel.map* function or the *qutip.parallel.parallel.parallel.parfor* (parallel-for-loop) function.

To use the these functions we need to define a function of one or more variables, and the range over which one of these variables are to be evaluated. For example:

or

Note that the return values are arranged differently for the *qutip.parallel.parallel_map* and the *qutip.parallel.parfor* functions, as illustrated below. In particular, the return value of *qutip.parallel.parallel_map* is not enforced to be NumPy arrays, which can avoid unnecessary copying if all that is needed is to iterate over the resulting list:

```
In [11]: result = parfor(func1, range(5))
In [12]: print(result)
[array([0, 1, 2, 3, 4]), array([ 0, 1, 4, 9, 16]), array([ 0, 1, 8, 27, 64])]
In [13]: result = parallel_map(func1, range(5))
In [14]: print(result)
[(0, 0, 0), (1, 1, 1), (2, 4, 8), (3, 9, 27), (4, 16, 64)]
```

The *qutip.parallel.parallel_map* and *qutip.parallel.parfor* functions are not limited to just numbers, but also works for a variety of outputs:

```
In [15]: def func2(x): return x, Qobj(x), 'a' * x
In [16]: a, b, c = parfor(func2, range(5))
In [17]: print(a)
[0 1 2 3 4]
In [18]: print(b)
\\\\\\\\\\[Quantum object: dims = [[1], [1]], shape = (1, 1), type = bra
Oobi data =
[[0.]]
Quantum object: dims = [[1], [1]], shape = (1, 1), type = bra
Qobj data =
[[1.]]
Quantum object: dims = [[1], [1]], shape = (1, 1), type = bra
Qobj data =
[[2.]]
Quantum object: dims = [[1], [1]], shape = (1, 1), type = bra
Qobj data =
[[3.]]
Quantum object: dims = [[1], [1]], shape = (1, 1), type = bra
Qobj data =
[[4.]]]
In [19]: print(c)
→'' 'a' 'aa' 'aaa' 'aaaa']
```

Note: New in QuTiP 3.

One can also define functions with **multiple** input arguments and even keyword arguments. Here the *qutip.parallel.parallel_map* and *qutip.parallel.parfor* functions behaves differently: While *qutip.parallel.parallel_map* only iterate over the values *arguments*, the *qutip.parallel.parallel.parfor* function simultaneously iterates over all arguments:

Note that the keyword arguments can be anything you like, but the keyword values are **not** iterated over. The keyword argument *num_cpus* is reserved as it sets the number of CPU's used by parfor. By default, this value is set to the total number of physical processors on your system. You can change this number to a lower value, however setting it higher than the number of CPU's will cause a drop in performance. In *qutip.parallel. parallel_map*, keyword arguments to the task function are specified using *task_kwargs* argument, so there is no special reserved keyword arguments.

The *qutip.parallel.parallel_map* function also supports progressbar, using the keyword argument *progress_bar* which can be set to *True* or to an instance of *qutip.ui.progressbar*. BaseProgressBar. There is a function called *qutip.parallel.serial_map* that works as a non-parallel drop-in replacement for *qutip.parallel.parallel_map*, which allows easy switching between serial and parallel computation.

```
In [23]: import time
In [24]: def func(x): time.sleep(1)
In [25]: result = parallel_map(func, range(50), progress_bar=True)
10.0%. Run time:
                 2.03s. Est. time left: 00:00:00:18
20.0%. Run time:
                 3.04s. Est. time left: 00:00:00:12
30.0%. Run time: 4.04s. Est. time left: 00:00:00:09
40.0%. Run time: 5.04s. Est. time left: 00:00:00:07
50.0%. Run time: 7.04s. Est. time left: 00:00:00:07
60.0%. Run time: 8.04s. Est. time left: 00:00:00:05
70.0%. Run time: 9.04s. Est. time left: 00:00:00:03
80.0%. Run time: 10.04s. Est. time left: 00:00:00:02
90.0%. Run time: 12.05s. Est. time left: 00:00:00:01
100.0%. Run time: 13.05s. Est. time left: 00:00:00:00
Total run time: 13.06s
```

Parallel processing is useful for repeated tasks such as generating plots corresponding to the dynamical evolution of your system, or simultaneously simulating different parameter configurations.

3.12.2 IPython-based parallel_map

Note: New in QuTiP 3.

When QuTiP is used with IPython interpreter, there is an alternative parallel for-loop implementation in the QuTiP module *qutip.ipynbtools*, see *qutip.ipynbtools.parallel_map*. The advantage of this parallel_map implementation is based on IPythons powerful framework for parallelization, so the compute processes are not confined to run on the same host as the main process.

3.13 Saving QuTiP Objects and Data Sets

With time-consuming calculations it is often necessary to store the results to files on disk, so it can be postprocessed and archived. In QuTiP there are two facilities for storing data: Quantum objects can be stored to files and later read back as python pickles, and numerical data (vectors and matrices) can be exported as plain text files in for example CSV (comma-separated values), TSV (tab-separated values), etc. The former method is preferred when further calculations will be performed with the data, and the latter when the calculations are completed and data is to be imported into a post-processing tool (e.g. for generating figures).

3.13.1 Storing and loading QuTiP objects

To store and load arbitrary QuTiP related objects (*qutip.Qobj*, *qutip.solver.Result*, etc.) there are two functions: *qutip.fileio.qsave* and *qutip.fileio.qload*. The function *qutip.fileio.qsave* takes an arbitrary object as first parameter and an optional filename as second parameter (default filename is *qutip_data.qu*). The filename extension is always.*qu*. The function *qutip.fileio.qload* takes a mandatory filename as first argument and loads and returns the objects in the file.

To illustrate how these functions can be used, consider a simple calculation of the steadystate of the harmonic oscillator:

```
In [1]: a = destroy(10); H = a.dag() * a ; c_ops = [np.sqrt(0.5) * a, np.sqrt(0.

→25) * a.dag()]
In [2]: rho_ss = steadystate(H, c_ops)
```

The steadystate density matrix *rho_ss* is an instance of *qutip.Qobj*. It can be stored to a file *steadystate.qu* using

```
In [3]: qsave(rho_ss, 'steadystate')
In [4]: ls *.qu
density_matrix_vs_time.qu steadystate.qu
```

and it can later be loaded again, and used in further calculations:

```
In [5]: rho_ss_loaded = qload('steadystate')
Loaded Qobj object:
Quantum object: dims = [[10], [10]], shape = (10, 10), type = oper, isHerm = True
In [6]: a = destroy(10)
In [7]: expect(a.dag() * a, rho_ss_loaded)
Out[7]: 0.9902248289345063
```

The nice thing about the *qutip.fileio.qsave* and *qutip.fileio.qload* functions is that almost any object can be stored and load again later on. We can for example store a list of density matrices as returned by *qutip.mesolve*:

```
In [8]: a = destroy(10); H = a.dag() * a; c_ops = [np.sqrt(0.5) * a, np.sqrt(0.

→25) * a.dag()]
In [9]: psi0 = rand_ket(10)
In [10]: times = np.linspace(0, 10, 10)
In [11]: dm_list = mesolve(H, psi0, times, c_ops, [])
In [12]: qsave(dm_list, 'density_matrix_vs_time')
```

And it can then be loaded and used again, for example in an other program:

3.13.2 Storing and loading datasets

The *qutip.fileio.qsave* and *qutip.fileio.qload* are great, but the file format used is only understood by QuTiP (python) programs. When data must be exported to other programs the preferred method is to store the data in the commonly used plain-text file formats. With the QuTiP functions *qutip.fileio. file_data_store* and *qutip.fileio.file_data_read* we can store and load **numpy** arrays and matrices to files on disk using a deliminator-separated value format (for example comma-separated values CSV). Almost any program can handle this file format.

The *qutip.fileio.file_data_store* takes two mandatory and three optional arguments:

where *filename* is the name of the file, *data* is the data to be written to the file (must be a *numpy* array), *numtype* (optional) is a flag indicating numerical type that can take values *complex* or *real*, *numformat* (optional) specifies the numerical format that can take the values *exp* for the format *1.0e1* and *decimal* for the format *10.0*, and *sep* (optional) is an arbitrary single-character field separator (usually a tab, space, comma, semicolon, etc.).

A common use for the *qutip.fileio.file_data_store* function is to store the expectation values of a set of operators for a sequence of times, e.g., as returned by the *qutip.mesolve* function, which is what the following example does:

```
In [16]: a = destroy(10); H = a.dag() * a ; c_ops = [np.sqrt(0.5) * a, np.sqrt(0.
→25) * a.dag()]
In [17]: psi0 = rand_ket(10)
In [18]: times = np.linspace(0, 100, 100)
In [19]: medata = mesolve(H, psi0, times, c_ops, [a.dag() * a, a + a.dag(), -1j *...
↔(a - a.dag())])
           shape(medata.expect)
In [20]:
Out[20]: (3, 100)
In [21]: shape(times)
In [22]: output_data = np.vstack((times, medata.expect))  # join time and expt_
→data
In [23]: file_data_store('expect.dat', output_data.T) # Note the .T for transpose!
In [24]: ls *.dat
expect.dat
In [25]: !head expect.dat
\\\\\\\\\\# Generated by QuTiP: 100x4 complex matrix in decimal format [','...
\rightarrow separated values].
0.000000000+0.0000000000000,3.8919697814+0.00000000000,1.4693223632+0.0000000000,1.
↔6316004623+0.000000000j
1.0101010101+0.0000000000j,3.2021827812+0.0000000000j,1.8098286946+0.0000000000j,-
↔0.2916776075+0.000000000j
2.0202020202+0.0000000000j,2.6815988750+0.0000000000j,0.6201568347+0.0000000000j,-
→1.4433846856+0.000000000j
3.0303030303+0.0000000000j,2.2865113238+0.0000000000j,-0.7693506823+0.0000000000j,-
→1.1183766557+0.0000000000j
4.0404040404+0.0000000000j,1.9852293983+0.0000000000j,-1.1773535978+0.000000000j,
→0.0485809163+0.000000000j
5.0505050505+0.0000000000j,1.7547523094+0.0000000000j,-0.5094210478+0.000000000j,
↔0.8903670221+0.000000000j
6.0606060606+0.0000000000j,1.5780725315+0.0000000000j,0.4213125439+0.000000000j,0.
↔7892379131+0.000000000j
7.0707070707+0.000000000j,1.4424424762+0.000000000j,0.7793180248+0.000000000j,0.
↔0549339318+0.000000000j
8.0808080808+0.0000000000j,1.3382239424+0.0000000000j,0.4028666401+0.0000000000j,-
→0.5513100605+0.0000000000j
```


In this case we didn't really need to store both the real and imaginary parts, so instead we could use the *num-type="real"* option:

In [26]: file_data_store('expect.dat', output_data.T, numtype="real")
In [27]: !head -n5 expect.dat
Generated by QuTiP: 100x4 real matrix in decimal format [',' separated values].
0.0000000000,3.8919697814,1.4693223632,1.6316004623
1.0101010101,3.2021827812,1.8098286946,-0.2916776075
2.020202022,2.6815988750,0.6201568347,-1.4433846856
3.0303030303,2.2865113238,-0.7693506823,-1.1183766557

and if we prefer scientific notation we can request that using the *numformat="exp"* option

Loading data previously stored using *qutip.fileio.file_data_store* (or some other software) is a even easier. Regardless of which deliminator was used, if data was stored as complex or real numbers, if it is in decimal or exponential form, the data can be loaded using the *qutip.fileio.file_data_read*, which only takes the filename as mandatory argument.

```
In [30]: input_data = file_data_read('expect.dat')
In [31]: shape(input_data)
Out[31]: (100, 4)
In [32]: plot(input_data[:,0], input_data[:,1]); # plot the data
```



(If a particularly obscure choice of deliminator was used it might be necessary to use the optional second argument, for example $sep="_"$ if _ is the deliminator).

3.14 Generating Random Quantum States & Operators

QuTiP includes a collection of random state, unitary and channel generators for simulations, Monte Carlo evaluation, theorem evaluation, and code testing. Each of these objects can be sampled from one of several different distributions including the default distributions used by QuTiP versions prior to 3.2.0.

For example, a random Hermitian operator can be sampled by calling *rand_herm* function:

```
In [1]: rand_herm(5)
Out[1]:
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
[[ 0.60851057+0.j
                        0.
                                  +0.j
                                               0.
                                                         +0.j
                                  +0.j
  0.41985122-0.16895027j 0.
                                              1
           +0.j
[ 0.
                        0.19674014+0.j
                                              -0.04903517-0.09195531j
  0.
           +0.j
                      -0.0115201 -0.56807658j]
                       -0.04903517+0.09195531j 0.
 [ 0.
           +0.j
                                                         +0.j
           +0.j -0.39352611+0.3849372j]
  0.
 [ 0.41985122+0.16895027j 0.
                                  +0.j
                                               0.
                                                         +0.j
  0.36389089+0.j
                       0.16438324+0.13293274j]
      +0.j
                       -0.0115201 +0.56807658j -0.39352611-0.3849372j
 [ 0.
  0.16438324-0.13293274j 0.27194037+0.j
                                              11
```

Random	Sampling Func-	Dimensions
Variable	tions	
Туре		
State vector	rand_ket,	$N \times 1$
(ket)	rand_ket_haar	
Hermitian op-	rand_herm	$N \times 1$
erator (oper)		
Density oper-	rand_dm,	$N \times N$
ator (oper)	rand_dm_hs,	
	rand_dm_ginibre	
Unitary oper-	rand_unitary,	$N \times N$
ator (oper)	rand_unitary_haar	
CPTP channel	rand_super,	$(N \times N) \times (N \times N)$
(super)	rand_super_bcsz	

In all cases, these functions can be called with a single parameter N that dimension of the relevant Hilbert space. The optional dims keyword argument allows for the dimensions of a random state, unitary or channel to be broken down into subsystems.

Several of the distributions supported by QuTiP support additional parameters as well, namely *density* and *rank*. In particular, the *rand_herm* and *rand_dm* functions return quantum objects such that a fraction of the elements are identically equal to zero. The ratio of nonzero elements is passed as the density keyword argument. By contrast, the *rand_dm_ginibre* and *rand_super_bcsz* take as an argument the rank of the generated object, such that passing rank=1 returns a random pure state or unitary channel, respectively. Passing rank=None specifies that the generated object should be full-rank for the given dimension.

For example,

```
0.
           +0.i
                        0.
                                 +0.j
                                           ]
                                +0.j
 [-0.02624329+0.03911698j 0.
                                             0.2722923 +0.j
 -0.14270369+0.14705046j -0.01102504-0.01795494j]
 [ 0.1174978 -0.16906407j 0.
                                +0.j
                                            -0.14270369-0.14705046j
                      -0.0063791 +0.00746525j]
  0.41156608+0.j
      +0.j
[ 0.
                       0.
                                            -0.01102504+0.01795494j
                                +0.j
 -0.0063791 -0.00746525j 0.01969855+0.j
                                           ]]
In [5]: rand_dm_ginibre(5, rank=2)
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Qobj data =
                       -0.35122731+0.05778841j 0.14041483-0.06052796j
[[ 0.51889755+0.j
  0.00781814+0.0357842j -0.10745475-0.07350835j]
[-0.35122731-0.05778841j 0.26322411+0.j
                                            -0.08652594+0.03141177j
 -0.02909989-0.02398621j 0.03237348+0.08501385j]
[ 0.14041483+0.06052796j -0.08652594-0.03141177j 0.05921609+0.j
 -0.02396346+0.02034985j -0.03883603-0.00350674j]
[ 0.00781814-0.0357842j -0.02909989+0.02398621j -0.02396346-0.02034985j
  0.04319394+0.j
                       0.04159719-0.02580653j]
[-0.10745475+0.07350835j 0.03237348-0.08501385j -0.03883603+0.00350674j
  0.04159719+0.02580653j 0.11546831+0.j
                                           ]]
```

See the API documentation: Random Operators and States for details.

Warning: When using the density keyword argument, setting the density too low may result in not enough diagonal elements to satisfy trace constraints.

3.14.1 Random objects with a given eigen spectrum

Note: New in QuTiP 3.2

It is also possible to generate random Hamiltonian (rand_herm) and densitiy matrices (rand_dm) with a given eigen spectrum. This is done by passing an array of eigenvalues as the first argument to either function. For example,

```
In [6]: eigs = np.arange(5)
In [7]: H = rand_herm(eigs, density=0.5)
In [8]: H
Out[8]:
Quantum object: dims = [[5], [5]], shape = (5, 5), type = oper, isherm = True
Oobi data =
[[ 1.5
            +5.55111512e-17j 0.11791791+3.33309715e-01j
  1.
            +5.55111512e-17j -0.11791791+3.33309715e-01j
  0.
            +0.00000000e+00j]
 [ 0.11791791-3.33309715e-01j 0.5
                                        +0.00000000e+00j
  -0.11791791+3.33309715e-01j 0.
                                        +0.00000000e+00j
  Ο.
           +0.00000000e+00j]
            +5.55111512e-17j -0.11791791-3.33309715e-01j
 [ 1.
            +5.55111512e-17j -0.11791791+3.33309715e-01j
  1.5
            +0.0000000e+00j]
  Ο.
 [-0.11791791-3.33309715e-01j 0.
                                        +0.00000000e+00j
  -0.11791791-3.33309715e-01j 2.5
                                        -5.55111512e-17j
```

(continues on next page)

(continued from previous page)

(continued from previous page)

In order to generate a random object with a given spectrum QuTiP applies a series of random complex Jacobi rotations. This technique requires many steps to build the desired quantum object, and is thus suitable only for objects with Hilbert dimensionality ≤ 1000 .

3.14.2 Composite random objects

In many cases, one is interested in generating random quantum objects that correspond to composite systems generated using the *qutip.tensor.tensor* function. Specifying the tensor structure of a quantum object is done using the *dims* keyword argument in the same fashion as one would do for a *qutip.Qobj* object:

```
In [10]: rand_dm(4, 0.5, dims=[[2,2], [2,2]])
Out[10]:
Quantum object: dims = [[2, 2], [2, 2]], shape = (4, 4), type = oper, isherm = True
Qobj data =
[[ 0.1791655 +0.j
                          0.0375456 +0.11396355j -0.02556688-0.09439071j
  0.06209366+0.12761988j]
[ 0.0375456 -0.11396355j 0.20524395+0.j
                                                0.08142619+0.03268325j
  0.15675233-0.02122358j]
[-0.02556688+0.09439071j 0.08142619-0.03268325j 0.42849069+0.j
  0.
           +0.j
                       ]
 [ 0.06209366-0.12761988j 0.15675233+0.02122358j 0.
                                                           +0.j
  0.18709986+0.j ]]
```

3.15 Modifying Internal QuTiP Settings

3.15.1 User Accessible Parameters

In this section we show how to modify a few of the internal parameters used by QuTiP. The settings that can be modified are given in the following table:

Setting	Description	Options
auto_herm	Automatically calculate the hermic-	True / False
	ity of quantum objects.	
auto_tidyup	Automatically tidyup quantum ob-	True / False
	jects.	
auto_tidyup_atol	Tolerance used by tidyup	any <i>float</i> value > 0
atol	General tolerance	any <i>float</i> value > 0
num_cpus	Number of CPU's used for multi-	<i>int</i> between 1 and # cpu's
	processing.	
debug	Show debug printouts.	True / False
openmp_thresh	NNZ matrix must have for	Int
	OPENMP.	

3.15.2 Example: Changing Settings

The two most important settings are auto_tidyup and auto_tidyup_atol as they control whether the small elements of a quantum object should be removed, and what number should be considered as the cut-off tolerance. Modifying these, or any other parameters, is quite simple:

```
>>> qutip.settings.auto_tidyup = False
```

These settings will be used for the current QuTiP session only and will need to be modified again when restarting QuTiP. If running QuTiP from a script file, then place the *qutip.setings.xxxx* commands immediately after *from qutip import* * at the top of the script file. If you want to reset the parameters back to their default values then call the reset command:

```
>>> qutip.settings.reset()
```

3.15.3 Persistent Settings

When QuTiP is imported, it looks for a file named qutiprc in a folder called .qutip user's home directory. If this file is found, it will be loaded and overwrite the QuTiP default settings, which allows for persistent changes in the QuTiP settings to be made. A sample qutiprc file is show below. The syntax is a simple key-value format, where the keys and possible values are described in the table above:

```
[qutip]
auto_tidyup=True
auto_herm=True
auto_tidyup_atol=1e-12
num_cpus=4
debug=False
```

Note that the openmp_thresh value is automatically generated by QuTiP. It is also possible to set a specific compiler for QuTiP to use when generating runtime Cython code for time-dependent problems. For example, the following section in the qutiprc file will set the compiler to be clang-3.9:

```
[compiler]
cc = clang-3.9
cxx = clang-3.9
```

Chapter 4

API documentation

This chapter contains automatically generated API documentation, including a complete list of QuTiP's public classes and functions.

4.1 Classes

4.1.1 Qobj

class Qobj (inpt=None, dims=[[], []], shape=[], type=None, isherm=None, copy=True, fast=False, superrep=None, isunitary=None)

A class for representing quantum objects, such as quantum operators and states.

The Qobj class is the QuTiP representation of quantum operators and state vectors. This class also implements math operations +,-,* between Qobj instances (and / by a C-number), as well as a collection of common operator/state operations. The Qobj constructor optionally takes a dimension list and/or shape list as arguments.

Parameters

inpt [array_like] Data for vector/matrix representation of the quantum object.

- dims [list] Dimensions of object used for tensor products.
- shape [list] Shape of underlying data structure (matrix shape).
- **copy** [bool] Flag specifying whether Qobj should get a copy of the input data, or use the original.
- **fast** [bool] Flag for fast qobj creation when running ode solvers. This parameter is used internally only.

Attributes

data [array_like] Sparse matrix characterizing the quantum object.

- dims [list] List of dimensions keeping track of the tensor structure.
- shape [list] Shape of the underlying *data* array.
- **type** [str] Type of quantum object: 'bra', 'ket', 'oper', 'operator-ket', 'operator-bra', or 'super'.
- **superrep** [str] Representation used if *type* is 'super'. One of 'super' (Liouville form) or 'choi' (Choi matrix with tr = dimension).

isherm [bool] Indicates if quantum object represents Hermitian operator.

isunitary [bool] Indictaes if quantum object represents unitary operator.

- **iscp** [bool] Indicates if the quantum object represents a map, and if that map is completely positive (CP).
- **ishp** [bool] Indicates if the quantum object represents a map, and if that map is hermicity preserving (HP).
- **istp** [bool] Indicates if the quantum object represents a map, and if that map is trace preserving (TP).
- **iscptp** [bool] Indicates if the quantum object represents a map that is completely positive and trace preserving (CPTP).
- isket [bool] Indicates if the quantum object represents a ket.
- isbra [bool] Indicates if the quantum object represents a bra.
- isoper [bool] Indicates if the quantum object represents an operator.
- issuper [bool] Indicates if the quantum object represents a superoperator.
- **isoperket** [bool] Indicates if the quantum object represents an operator in column vector form.
- isoperbra [bool] Indicates if the quantum object represents an operator in row vector form.

Methods

copy()	Create copy of Qobj
conj()	Conjugate of quantum object.
cosm()	Cosine of quantum object.
dag()	Adjoint (dagger) of quantum object.
dnorm()	Diamond norm of quantum operator.
dual_chan()	Dual channel of quantum object representing a CP
_ ~	map.
eigenenergies(sparse=False, sort='low',	Returns eigenenergies (eigenvalues) of a quantum
eigvals=0, tol=0, maxiter=100000)	object.
eigenstates(sparse=False, sort='low',	Returns eigenenergies and eigenstates of quantum
eigvals=0, tol=0, maxiter=100000)	object.
expm()	Matrix exponential of quantum object.
full(order='C')	Returns dense array of quantum object data attribute.
groundstate(sparse=False, tol=0, max-	Returns eigenvalue and eigenket for the groundstate
iter=100000)	of a quantum object.
matrix_element(bra, ket)	Returns the matrix element of operator between bra
	and <i>ket</i> vectors.
norm(norm='tr', sparse=False, tol=0, max-	Returns norm of a ket or an operator.
iter=100000)	
permute(order)	Returns composite qobj with indices reordered.
proj()	Computes the projector for a ket or bra vector.
ptrace(sel)	Returns quantum object for selected dimensions after
	performing partial trace.
sinm()	Sine of quantum object.
sqrtm()	Matrix square root of quantum object.
tidyup(atol=1e-12)	Removes small elements from quantum object.
tr()	Trace of quantum object.
trans()	Transpose of quantum object.
transform(inpt, inverse=False)	Performs a basis transformation defined by inpt ma-
	trix.
trunc_neg(method='clip')	Removes negative eigenvalues and returns a new
	Qobj that is a valid density operator.
unit(norm='tr', sparse=False, tol=0, max-	Returns normalized quantum object.
iter=100000)	

check_herm(self)

Check if the quantum object is hermitian.

Returns

isherm [bool] Returns the new value of isherm property.

check_isunitary(self)

Checks whether qobj is a unitary matrix

conj(self)

Conjugate operator of quantum object.

copy (self)

Create identical copy

cosm(self)

Cosine of a quantum operator.

Operator must be square.

Returns

oper [qutip.Qobj] Matrix cosine of operator.

Raises

TypeError Quantum object is not square.

Notes

Uses the Q.expm() method.

dag(self)

Adjoint operator of quantum object.

diag(self)

Diagonal elements of quantum object.

Returns

diags [array] Returns array of real values if operators is Hermitian, otherwise complex values are returned.

dnorm (self, B=None)

Calculates the diamond norm, or the diamond distance to another operator.

Parameters

B [*qutip.Qobj* or None] If B is not None, the diamond distance d(A, B) = dnorm(A - B) between this operator and B is returned instead of the diamond norm.

Returns

d [float] Either the diamond norm of this operator, or the diamond distance from this operator to B.

dual_chan(self)

Dual channel of quantum object representing a completely positive map.

eigenenergies (*self*, *sparse=False*, *sort='low'*, *eigvals=0*, *tol=0*, *maxiter=100000*) Eigenenergies of a quantum object.

Eigenenergies (eigenvalues) are defined for operators or superoperators only.

Parameters

sparse [bool] Use sparse Eigensolver

sort [str] Sort eigenvalues 'low' to high, or 'high' to low.

eigvals [int] Number of requested eigenvalues. Default is all eigenvalues.

- **tol** [float] Tolerance used by sparse Eigensolver (0=machine precision). The sparse solver may not converge if the tolerance is set too low.
- maxiter [int] Maximum number of iterations performed by sparse solver (if used).

Returns

eigvals [array] Array of eigenvalues for operator.

Notes

The sparse eigensolver is much slower than the dense version. Use sparse only if memory requirements demand it.

eigenstates (self, sparse=False, sort='low', eigvals=0, tol=0, maxiter=100000) Eigenstates and eigenenergies.

Eigenstates and eigenenergies are defined for operators and superoperators only.

Parameters

sparse [bool] Use sparse Eigensolver

sort [str] Sort eigenvalues (and vectors) 'low' to high, or 'high' to low.

eigvals [int] Number of requested eigenvalues. Default is all eigenvalues.

tol [float] Tolerance used by sparse Eigensolver (0 = machine precision). The sparse solver may not converge if the tolerance is set too low.

maxiter [int] Maximum number of iterations performed by sparse solver (if used).

Returns

eigvals [array] Array of eigenvalues for operator.

eigvecs [array] Array of quantum operators representing the oprator eigenkets. Order of eigenkets is determined by order of eigenvalues.

Notes

The sparse eigensolver is much slower than the dense version. Use sparse only if memory requirements demand it.

eliminate_states (self, states_inds, normalize=False)

Creates a new quantum object with states in state_inds eliminated.

Parameters

states_inds [list of integer] The states that should be removed.

normalize [True / False] Weather or not the new Qobj instance should be normalized (default is False). For Qobjs that represents density matrices or state vectors normalized should probably be set to True, but for Qobjs that represents operators in for example an Hamiltonian, normalize should be False.

Returns

q [qutip.Qobj] A new instance of qutip.Qobj that contains only the states corresponding to indices that are **not** in *state_inds*.

Notes

Experimental.

```
static evaluate(qobj_list, t, args)
```

Evaluate a time-dependent quantum object in list format. For example,

 $qobj_list = [H0, [H1, func_t]]$

is evaluated to

 $Qobj(t) = H0 + H1 * func_t(t, args)$

and

```
qobj_list = [H0, [H1, 'sin(w * t)']]
```

is evaluated to

Qobj(t) = H0 + H1 * sin(args['w'] * t)

Parameters

qobj_list [list] A nested list of Qobj instances and corresponding time-dependent coefficients.

- t [float] The time for which to evaluate the time-dependent Qobj instance.
- **args** [dictionary] A dictionary with parameter values required to evaluate the timedependent Qobj intance.

Returns

output [qutip.Qobj] A Qobj instance that represents the value of qobj_list at time t.

expm (self, method='dense')

Matrix exponential of quantum operator.

Input operator must be square.

Parameters

method [str { 'dense', 'sparse' }] Use set method to use to calculate the matrix exponentiation. The available choices includes 'dense' and 'sparse'. Since the exponential of a matrix is nearly always dense, method='dense' is set as default.s

Returns

oper [qutip.Qobj] Exponentiated quantum operator.

Raises

TypeError Quantum operator is not square.

extract_states (self, states_inds, normalize=False)

Qobj with states in state_inds only.

Parameters

states_inds [list of integer] The states that should be kept.

normalize [True / False] Weather or not the new Qobj instance should be normalized (default is False). For Qobjs that represents density matrices or state vectors normalized should probably be set to True, but for Qobjs that represents operators in for example an Hamiltonian, normalize should be False.

Returns

q [qutip.Qobj] A new instance of qutip.Qobj that contains only the states corresponding to the indices in *state_inds*.

Notes

Experimental.

full (self, order='C', squeeze=False)
Dense array from quantum object.

Parameters

order [str {'C', 'F'}] Return array in C (default) or Fortran ordering.

squeeze [bool {False, True}] Squeeze output array.

Returns

data [array] Array of complex data from quantum objects data attribute.

groundstate (self, sparse=False, tol=0, maxiter=100000, safe=True) Ground state Eigenvalue and Eigenvector.

Defined for quantum operators or superoperators only.

Parameters

sparse [bool] Use sparse Eigensolver

tol [float] Tolerance used by sparse Eigensolver (0 = machine precision). The sparse solver may not converge if the tolerance is set too low.

maxiter [int] Maximum number of iterations performed by sparse solver (if used).

safe [bool (default=True)] Check for degenerate ground state

Returns

eigval [float] Eigenvalue for the ground state of quantum operator.

eigvec [qutip.Qobj] Eigenket for the ground state of quantum operator.

Notes

The sparse eigensolver is much slower than the dense version. Use sparse only if memory requirements demand it.

matrix_element (self, bra, ket)

Calculates a matrix element.

Gives the matrix element for the quantum object sandwiched between a bra and ket vector.

Parameters

bra [qutip.Qobj] Quantum object of type 'bra' or 'ket'

ket [qutip.Qobj] Quantum object of type 'ket'.

Returns

elem [complex] Complex valued matrix element.

norm (*self*, *norm=None*, *sparse=False*, *tol=0*, *maxiter=100000*) Norm of a quantum object.

rionn of a quantum object.

Default norm is L2-norm for kets and trace-norm for operators. Other ket and operator norms may be specified using the *norm* and argument.

Parameters

norm [str] Which norm to use for ket/bra vectors: L2 '12', max norm 'max', or for operators: trace 'tr', Frobius 'fro', one 'one', or max 'max'.

- **sparse** [bool] Use sparse eigenvalue solver for trace norm. Other norms are not affected by this parameter.
- **tol** [float] Tolerance for sparse solver (if used) for trace norm. The sparse solver may not converge if the tolerance is set too low.
- **maxiter** [int] Maximum number of iterations performed by sparse solver (if used) for trace norm.

Returns

norm [float] The requested norm of the operator or state quantum object.

Notes

The sparse eigensolver is much slower than the dense version. Use sparse only if memory requirements demand it.

overlap (self, other)

Overlap between two state vectors or two operators.

Gives the overlap (inner product) between the current bra or ket Qobj and and another bra or ket Qobj. It gives the Hilbert-Schmidt overlap when one of the Qobj is an operator/density matrix.

Parameters

other [qutip.Qobj] Quantum object for a state vector of type 'ket', 'bra' or density matrix.

Returns

overlap [complex] Complex valued overlap.

Raises

TypeError Can only calculate overlap between a bra, ket and density matrix quantum objects.

Notes

Since QuTiP mainly deals with ket vectors, the most efficient inner product call is the ket-ket version that computes the product <selflother> with both vectors expressed as kets.

permute (self, order)

Permutes a composite quantum object.

Parameters

order [list/array] List specifying new tensor order.

Returns

P [qutip.Qobj] Permuted quantum object.

proj(self)

Form the projector from a given ket or bra vector.

Parameters

Q [qutip.Qobj] Input bra or ket vector

Returns

P [qutip.Qobj] Projection operator.

ptrace (self, sel)

Partial trace of the quantum object.

Parameters

sel [int/list] An int or list of components to keep after partial trace.

Returns

oper [*qutip.Qobj*] Quantum object representing partial trace with selected components remaining.

Notes

This function is identical to the qutip.qobj.ptrace function that has been deprecated.

sinm(self)

Sine of a quantum operator.

Operator must be square.

Returns

oper [qutip.Qobj] Matrix sine of operator.

Raises

TypeError Quantum object is not square.

Notes

Uses the Q.expm() method.

```
sqrtm (self, sparse=False, tol=0, maxiter=100000)
Sqrt of a quantum operator.
```

Operator must be square.

Parameters

sparse [bool] Use sparse eigenvalue/vector solver.

tol [float] Tolerance used by sparse solver (0 = machine precision).

maxiter [int] Maximum number of iterations used by sparse solver.

Returns

oper [qutip.Qobj] Matrix square root of operator.

Raises

TypeError Quantum object is not square.

Notes

The sparse eigensolver is much slower than the dense version. Use sparse only if memory requirements demand it.

```
tidyup (self, atol=1e-12)
```

Removes small elements from the quantum object.

Parameters

atol [float] Absolute tolerance used by tidyup. Default is set via qutip global settings parameters.

Returns

oper [qutip.Qobj] Quantum object with small elements removed.

tr(self)

Trace of a quantum object.

Returns

trace [float] Returns real if operator is Hermitian, returns complex otherwise.

trans(self)

Transposed operator.

Returns

oper [qutip.Qobj] Transpose of input operator.

transform (self, inpt, inverse=False, sparse=True)

Basis transform defined by input array.

Input array can be a matrix defining the transformation, or a list of kets that defines the new basis.

Parameters

inpt [array_like] A matrix or list of kets defining the transformation.

inverse [bool] Whether to return inverse transformation.

sparse [bool] Use sparse matrices when possible. Can be slower.

Returns

oper [qutip.Qobj] Operator in new basis.

Notes

This function is still in development.

```
trunc_neg (self, method='clip')
```

Truncates negative eigenvalues and renormalizes.

Returns a new Qobj by removing the negative eigenvalues of this instance, then renormalizing to obtain a valid density operator.

Parameters

method [str] Algorithm to use to remove negative eigenvalues. "clip" simply discards negative eigenvalues, then renormalizes. "sgs" uses the SGS algorithm (doi:10/bb76) to find the positive operator that is nearest in the Shatten 2-norm.

Returns

oper [qutip.Qobj] A valid density operator.

unit (*self*, *inplace=False*, *norm=None*, *sparse=False*, *tol=0*, *maxiter=100000*) Operator or state normalized to unity.

Uses norm from Qobj.norm().

Parameters

inplace [bool] Do an in-place normalization

norm [str] Requested norm for states / operators.

sparse [bool] Use sparse eigensolver for trace norm. Does not affect other norms.

tol [float] Tolerance used by sparse eigensolver.

maxiter [int] Number of maximum iterations performed by sparse eigensolver.

Returns

oper [qutip.Qobj] Normalized quantum object if not in-place, else None.

4.1.2 QobjEvo

class QobjEvo (*Q_object=[]*, *args={}*, *tlist=None*, *copy=True*)

A class for representing time-dependent quantum objects, such as quantum operators and states.

The QobjEvo class is a representation of time-dependent Qutip quantum objects (Qobj). This class implements math operations :

+,-: QobjEvo, Qobj *: Qobj, C-number /: C-number

and some common linear operator/state operations. The QobjEvo are constructed from a nested list of Qobj with their time-dependent coefficients. The time-dependent coefficients are either a funciton, a string or a numpy array.

For function format, the function signature must be f(t, args). Examples

def f1_t(t, args): return np.exp(-1j * t * args["w1"])

def f2_t(t, args): return np.cos(t * args["w2"])

H = QobjEvo([H0, [H1, f1_t], [H2, f2_t]], args={"w1":1., "w2":2.})

For string based coefficients, the string must be a compilable python code resulting in a complex. The following symbols are defined:

sin cos tan asin acos atan pi sinh cosh tanh asinh acosh atanh exp log log10 erf zerf sqrt real imag conj abs norm arg proj numpy as np, and scipy.special as spe.

Examples

```
H = QobjEvo([H0, [H1, 'exp(-1j*w1*t)'], [H2, 'cos(w2*t)']], args={"w1":1.,"w2":2.})
```

For numpy array format, the array must be an 1d of dtype float or complex. A list of times (float64) at which the coefficients must be given (tlist). The coefficients array must have the same len as the tlist. The time of the tlist do not need to be equidistant, but must be sorted. *Examples*

tlist = np.logspace(-5,0,100) H = QobjEvo([H0, [H1, np.exp(-1j*tlist)], [H2, np.cos(2.*tlist)]],

tlist=tlist)

args is a dict of (name:object). The name must be a valid variables string. Some solvers support arguments that update at each call: sesolve, mesolve, mcsolve:

state can be obtained with: name+"=vec":Qobj => args[name] == state as 1D np.ndarray
name+"=mat":Qobj => args[name] == state as 2D np.ndarray name+"=Qobj":Qobj =>
args[name] == state as Qobj

This Qobj is the initial value.

expectation values: name+"=expect":O (Qobj/QobjEvo) => args[name] == expect(O, state) expect is <philOlpsi> or tr(state * O) depending on state dimensions

mcsolve:

collapse can be obtained with: name+"=collapse":list => args[name] == list of collapse each collapse will be appended to the list as (time, which c_ops)

Mixing the formats is possible, but not recommended. Mixing tlist will cause problem.

Parameters

QobjEvo(Q_object=[], args={}, tlist=None)

Q_object [array_like] Data for vector/matrix representation of the quantum object.

args [dictionary that contain the arguments for]

tlist [array_like] List of times at which the numpy-array coefficients are applied. Times must be equidistant and start from 0.

Attributes

cte [Qobj] Constant part of the QobjEvo

ops [list] List of Qobj and the coefficients. [(Qobj, coefficient as a function, original coefficient,

type, local arguments), ...]

type: 1: function 2: string 3: np.array 4: Cubic_Spline

args [map] arguments of the coefficients

tlist [array_like] List of times at which the numpy-array coefficients are applied.

compiled [int] Has the cython version of the QobjEvo been created

compiled_qobjevo [cy_qobj (CQobjCte or CQobjEvoTd)] Cython version of the QobjEvo

dummy_cte [bool] is self.cte a dummy Qobj

const [bool] Indicates if quantum object is Constant

type [int]

information about the type of coefficient "string", "func", "array", "spline", "mixed_callable", "mixed_compilable"

num_obj [int] number of Qobj in the QobjEvo : len(ops) + (1 if not dummy_cte)

Methods

copy():	Create copy of Qobj		
argu-	Update the args of the object		
ments(new			
Math:	+/- QobjEvo, Qobj, scalar: Addition is possible between QobjEvo and with Qobj or scalar -: Negation operator * Qobj, scalar: Product is possible with Qobj or scalar / scalar: It is possible to divide by scalar only		
conj()	Return the conjugate of quantum object.		
dag()	Return the adjoint (dagger) of quantum object.		
trans()	Return the transpose of quantum object.		
norm()	Return self.dag() * self. Only possible if num_obj == 1		
per-	Return self.dag() * self. Only possible if hum_obj == 1 Returns composite qobj with indices reordered.		
mute(order			
ptrace(sel)			
apply(f,	Apply the function f to every Qobj. f(Qobj) -> Qobj Return a modified QobjEvo and let the		
*args,	original one untouched		
**kw_args			
ap-	inplace_np=False, **kw_args): Apply the decorator to each function of the ops. The		
-	tor(decorator, *kw_args are passed to the decorator. new_coeff_function = decora-		
*args,	tor(coeff_function, *args, **kw_args) str_mod : list of 2 elements replace the string :		
0,	=Noste_mod[0] + original_string + str_mod[1] *exemple: str_mod = ["exp(",")"] inplace_np:		
su_mou_i	Change the numpy array instead of applying the decorator to the function reading the array.		
	Some decorators create incorrect array. Transformations $f'(t) = f(g(t))$ create a missmatch		
	between the array and the associated time list.		
tidyup(atol	=Removes small elements from quantum object.		
12)	1 5		
com-	Merge ops which are based on the same quantum object and coeff type.		
press():			
com-	Create the associated cython object for faster usage. code: return the code generated for		
pile(code=l	False pilation of the strings. matched: the compiled object use sparse matrix with matching		
matched=F	alselices. (experimental, no real advantage) dense: the compiled object use dense matrix.		
dense=Fals	eomp: (int) number of thread: the compiled object use spmvpy_openmp.		
omp=0):			
call(t,			
data=False			
state=None	·,		
args={}):			
	Product of this at t time with the dense matrix mat. *Faster after compilation		
mat):			
mul_vec(t,	Apply the quantum object (if operator, no check) to psi. More generaly, return the product		
psi):	of the object at t with psi. *Faster after compilation		
expect(t,	Calculates the expectation value for the quantum object (if operator, no check) and state		
psi,	psi. Return only the real part if herm. *Faster after compilation		
herm=Fals	,		
to_list():	Return the time-dependent quantum object as a list		

4.1.3 eseries

class eseries (q=None, s=array([], dtype=float64))

Class representation of an exponential-series expansion of time-dependent quantum objects.

Attributes

ampl [ndarray] Array of amplitudes for exponential series.

rates [ndarray] Array of rates for exponential series.

dims [list] Dimensions of exponential series components

shape [list] Shape corresponding to exponential series components

Methods

value(tlist)	Evaluate an exponential series at the times listed in tlist	
spec(wlist)	Evaluate the spectrum of an exponential series at frequencies in wlist.	
tidyup()	Returns a tidier version of the exponential series	

spec (self, wlist)

Evaluate the spectrum of an exponential series at frequencies in wlist.

Parameters

wlist [array_like] Array/list of frequenies.

Returns

val_list [ndarray] Values of exponential series at frequencies in wlist.

tidyup (*self*, **args*) Returns a tidier version of exponential series.

value (*self*, *tlist*)

Evaluates an exponential series at the times listed in tlist.

Parameters

tlist [ndarray] Times at which to evaluate exponential series.

Returns

val_list [ndarray] Values of exponential at times in tlist.

4.1.4 Bloch sphere

class Bloch (*fig=None*, *axes=None*, *view=None*, *figsize=None*, *background=False*)

Class for plotting data on the Bloch sphere. Valid data can be either points, vectors, or qobj objects.

Attributes

axes [instance {None}] User supplied Matplotlib axes for Bloch sphere animation.

fig [instance {None}] User supplied Matplotlib Figure instance for plotting Bloch sphere.

font_color [str { 'black' }] Color of font used for Bloch sphere labels.

font_size [int {20}] Size of font used for Bloch sphere labels.

frame_alpha [float {0.1}] Sets transparency of Bloch sphere frame.

frame_color [str {'gray'}] Color of sphere wireframe.

frame_width [int {1}] Width of wireframe.

point_color [list {["b","r","g","#CC6600"]}] List of colors for Bloch sphere point markers to cycle through. i.e. By default, points 0 and 4 will both be blue ('b').

point_marker [list {["o","s","d","^"]}] List of point marker shapes to cycle through.

point_size [list {[25,32,35,45]}] List of point marker sizes. Note, not all point markers look the same size when plotted!

sphere_alpha [float {0.2}] Transparency of Bloch sphere itself.

sphere_color [str {'#FFDDDD'}] Color of Bloch sphere.

figsize [list {[7,7]}] Figure size of Bloch sphere plot. Best to have both numbers the same; otherwise you will have a Bloch sphere that looks like a football.

vector_color [list {["g","#CC6600","b","r"]}] List of vector colors to cycle through.

vector_width [int {5}] Width of displayed vectors.

- **vector_style** [str {'-l>', 'simple', 'fancy', ''}] Vector arrowhead style (from matplotlib's arrow style).
- vector_mutation [int {20}] Width of vectors arrowhead.

view [list {[-60,30]}] Azimuthal and Elevation viewing angles.

- **xlabel** [list {["\$x\$",""]}] List of strings corresponding to +x and -x axes labels, respectively.
- **xlpos** [list {[1.1,-1.1]}] Positions of +x and -x labels respectively.
- ylabel [list {["\$y\$",""]}] List of strings corresponding to +y and -y axes labels, respectively.
- ylpos [list {[1.2,-1.2]}] Positions of +y and -y labels respectively.
- **zlabel** [list {[r'\$\left|0\right>\$',r'\$\left|1\right>\$']}] List of strings corresponding to +z and -z axes labels, respectively.

zlpos [list {[1.2,-1.2]}] Positions of +z and -z labels respectively.

add_annotation (self, state_or_vector, text, **kwargs)

Add a text or LaTeX annotation to Bloch sphere, parametrized by a qubit state or a vector.

Parameters

- **state_or_vector** [Qobj/array/list/tuple] Position for the annotaion. Qobj of a qubit or a vector of 3 elements.
- **text** [str/unicode] Annotation text. You can use LaTeX, but remember to use raw string e.g. r"\$langle x rangle\$" or escape backslashes e.g. "\$\langle x \rangle ".
- ****kwargs :** Options as for mplot3d.axes3d.text, including: fontsize, color, horizontalalignment, verticalalignment.

add_points (self, points, meth='s') Add a list of data points to bloch sphere.

Parameters

points [array/list] Collection of data points.

meth [str {'s', 'm', 'l'}] Type of points to plot, use 'm' for multicolored, 'l' for points connected with a line.

add_states (self, state, kind='vector')

Add a state vector Qobj to Bloch sphere.

Parameters

state [qobj] Input state vector.

kind [str {'vector','point'}] Type of object to plot.

add_vectors (self, vectors)

Add a list of vectors to Bloch sphere.

Parameters

vectors [array_like] Array with vectors of unit length or smaller.

clear (self)

Resets Bloch sphere data sets to empty.

make_sphere (self)

Plots Bloch sphere and data sets.

render (*self*, *fig=None*, *axes=None*)

Render the Bloch sphere and its data sets in on given figure and axes.

save (self, name=None, format='png', dirc=None)

Saves Bloch sphere to file of type format in directory dirc.

Parameters

name [str] Name of saved image. Must include path and format as well. i.e. '/Users/Paul/Desktop/bloch.png' This overrides the 'format' and 'dirc' arguments.

format [str] Format of output image.

dirc [str] Directory for output images. Defaults to current working directory.

Returns

File containing plot of Bloch sphere.

set_label_convention (self, convention)

Set x, y and z labels according to one of conventions.

Parameters

convention [string] One of the following:

- "original"
- "xyz"
- "sx sy sz"
- "01"
- "polarization jones"
- "polarization jones letters" see also: http://en.wikipedia.org/wiki/Jones_calculus
- "polarization stokes" see also: http://en.wikipedia.org/wiki/Stokes_parameters

show(self)

Display Bloch sphere and corresponding data sets.

vector_mutation = None

Sets the width of the vectors arrowhead

vector_style = None

Style of Bloch vectors, default = '-|>' (or 'simple')

```
vector_width = None
```

Width of Bloch vectors, default = 5

4.1.5 Cubic Spline

class Cubic_Spline (*a*, *b*, *y*, *alpha=0*, *beta=0*)

Calculates coefficients for a cubic spline interpolation of a given data set.

This function assumes that the data is sampled uniformly over a given interval.

Parameters

- **a** [float] Lower bound of the interval.
- **b** [float] Upper bound of the interval.
- y [ndarray] Function values at interval points.

alpha [float] Second-order derivative at a. Default is 0.

beta [float] Second-order derivative at b. Default is 0.

Notes

This object can be called like a normal function with a single or array of input points at which to evaluate the interplating function.

Habermann & Kindermann, "Multidimensional Spline Interpolation: Theory and Applications", Comput Econ 30, 153 (2007).

Attributes

- **a** [float] Lower bound of the interval.
- **b** [float] Upper bound of the interval.

coeffs [ndarray] Array of coeffcients defining cubic spline.

4.1.6 Non-Markovian Solvers

class HEOMSolver

This is superclass for all solvers that use the HEOM method for calculating the dynamics evolution. There are many references for this. A good introduction, and perhaps closest to the notation used here is: DOI:10.1103/PhysRevLett.104.250401 A more canonical reference, with full derivation is: DOI: 10.1103/PhysRevA.41.6676 The method can compute open system dynamics without using any Markovian or rotating wave approximation (RWA) for systems where the bath correlations can be approximated to a sum of complex eponentials. The method builds a matrix of linked differential equations, which are then solved used the same ODE solvers as other qutip solvers (e.g. mesolve)

This class should be treated as abstract. Currently the only subclass implemented is that for the Drude-Lorentz spectral density. This covers the majority of the work that has been done using this model, and there are some performance advantages to assuming this model where it is appropriate.

There are opportunities to develop a more general spectral density code.

Attributes

H_sys [Qobj] System Hamiltonian

coup_op [Qobj] Operator describing the coupling between system and bath.

coup_strength [float] Coupling strength.

temperature [float] Bath temperature, in units corresponding to planck

N_cut [int] Cutoff parameter for the bath

N_exp [int] Number of exponential terms used to approximate the bath correlation functions

planck [float] reduced Planck constant

boltzmann [float] Boltzmann's constant

- **options** [*qutip.solver.Options*] Generic solver options. If set to None the default options will be used
- **progress_bar: BaseProgressBar** Optional instance of BaseProgressBar, or a subclass thereof, for showing the progress of the simulation.
- **stats** [*qutip.solver.Stats*] optional container for holding performance statitics If None is set, then statistics are not collected There may be an overhead in collecting statistics
- exp_coeff [list of complex] Coefficients for the exponential series terms

exp_freq [list of complex] Frequencies for the exponential series terms

Configure the solver using the passed parameters The parameters are described in the class attributes, unless there is some specific behaviour

Parameters

- **options** [*qutip.solver.Options*] Generic solver options. If set to None the default options will be used
- **progress_bar: BaseProgressBar** Optional instance of BaseProgressBar, or a subclass thereof, for showing the progress of the simulation. If set to None, then the default progress bar will be used Set to False for no progress bar
- **stats: :class: 'qutip.solver.Stats'** Optional instance of solver.Stats, or a subclass thereof, for storing performance statistics for the solver If set to True, then the default Stats for this class will be used Set to False for no stats

create_new_stats(self)

Creates a new stats object suitable for use with this solver Note: this solver expects the stats object to have sections

config integrate

reset (self)

Reset any attributes to default values

class HSolverDL (*H_sys, coup_op, coup_strength, temperature, N_cut, N_exp, cut_freq, planck=1.0, boltzmann=1.0, renorm=True, bnd_cut_approx=True, options=None, progress bar=None, stats=None)*

HEOM solver based on the Drude-Lorentz model for spectral density. Drude-Lorentz bath the correlation functions can be exactly analytically expressed as an infinite sum of exponentials which depend on the temperature, these are called the Matsubara terms or Matsubara frequencies

For practical computation purposes an approximation must be used based on a small number of Matsubara terms (typically < 4).

Attributes

cut_freq [float] Bath spectral density cutoff frequency.

renorm [bool] Apply renormalisation to coupling terms Can be useful if using SI units for planck and boltzmann

bnd_cut_approx [bool] Use boundary cut off approximation Can be

Calls configure from *HEOMSolver* and sets any attributes that are specific to this subclass

reset (self)

Reset any attributes to default values

run (self, rho0, tlist)

Function to solve for an open quantum system using the HEOM model.

Parameters

rho0 [Qobj] Initial state (density matrix) of the system.

tlist [list] Time over which system evolves.

Returns

results [qutip.solver.Result] Object storing all results from the simulation.

class MemoryCascade (*H_S*, *L1*, *L2*, *S_matrix=None*, *c_ops_markov=None*, *integra-tor='propagator'*, *parallel=False*, *options=None*)

Class for running memory cascade simulations of open quantum systems with time-delayed coherent feedback.

Attributes

H_S [qutip.Qobj] System Hamiltonian (can also be a Liouvillian)

- L1 [qutip.Qobj / list of qutip.Qobj] System operators coupling into the feedback loop. Can be a single operator or a list of operators.
- L2 [qutip.Qobj/list of qutip.Qobj] System operators coupling out of the feedback loop. Can be a single operator or a list of operators. L2 must have the same length as L1.
- **S_matrix: *array*** S matrix describing which operators in L1 are coupled to which operators in L2 by the feedback channel. Defaults to an n by n identity matrix where n is the number of elements in L1/L2.
- **c_ops_markov** [*qutip.Qobj* / list of *qutip.Qobj*] Decay operators describing conventional Markovian decay channels. Can be a single operator or a list of operators.
- **integrator** [str { 'propagator', 'mesolve' }] Integrator method to use. Defaults to 'propagator' which tends to be faster for long times (i.e., large Hilbert space).
- **parallel** [bool] Run integrator in parallel if True. Only implemented for 'propagator' as the integrator method.

options [qutip.solver.Options] Generic solver options.

outfieldcorr (self, rho0, blist, tlist, tau, c1=None, c2=None)

Compute output field expectation value $<O_n(tn)...O_2(t2)O_1(t1)>$ for times t1,t2,... and $O_i = I$, b_out, b_out^dagger, b_loop^dagger

Parameters

- **rho0** [qutip.Qobj] initial density matrix or state vector (ket).
- **blist** [array_like] List of integers specifying the field operators: 0: I (nothing) 1: b_out 2: b_out^dagger 3: b_loop^4: b_loop^dagger
- **tlist** [array_like] list of corresponding times t1,...,tn at which to evaluate the field operators
- tau [float] time-delay
- **c1** [*qutip.Qobj*] system collapse operator that couples to the in-loop field in question (only needs to be specified if self.L1 has more than one element)
- **c2** [*qutip.Qobj*] system collapse operator that couples to the output field in question (only needs to be specified if self.L2 has more than one element)

Returns

: complex expectation value of field correlation function

outfieldpropagator (*self*, *blist*, *tlist*, *tau*, *c1=None*, *c2=None*, *notrace=False*)

Compute propagator for computing output field expectation values $<O_n(tn)...O_2(t2)O_1(t1)>$ for times t1,t2,... and $O_i = I$, b_out, b_out^dagger, b_loop, b_loop^dagger

Parameters

blist [array_like] List of integers specifying the field operators: 0: I (nothing) 1: b_out 2: b_out^dagger 3: b_loop 4: b_loop^dagger

tlist [array_like] list of corresponding times t1,...,tn at which to evaluate the field operators

tau [float] time-delay

- **c1** [*qutip.Qobj*] system collapse operator that couples to the in-loop field in question (only needs to be specified if self.L1 has more than one element)
- **c2** [*qutip.Qobj*] system collapse operator that couples to the output field in question (only needs to be specified if self.L2 has more than one element)
- **notrace** [bool {False}] If this optional is set to True, a propagator is returned for a cascade of k systems, where (k 1)tau < t < ktau. If set to False (default), a generalized partial trace is performed and a propagator for a single system is returned.

Returns

: qutip. Qobj time-propagator for computing field correlation function

propagator (self, t, tau, notrace=False)

Compute propagator for time t and time-delay tau

Parameters

t [float] current time

tau [float] time-delay

notrace [bool {False}] If this optional is set to True, a propagator is returned for a cascade of k systems, where (k - 1)tau < t < ktau. If set to False (default), a generalized partial trace is performed and a propagator for a single system is returned.

Returns

: :class:'qutip.Qobj' time-propagator for reduced system dynamics

rhot (*self*, *rho0*, *t*, *tau*)

Compute the reduced system density matrix $\rho(t)$

Parameters

rho0 [qutip.Qobj] initial density matrix or state vector (ket)

t [float] current time

tau [float] time-delay

Returns

: qutip. Qobj density matrix at time t

class TTMSolverOptions (*dynmaps=None*, *times=[]*, *learningtimes=[]*, *thres=0.0*, *options=None*) Class of options for the Transfer Tensor Method solver.

Attributes

dynmaps [list of *qutip.Qobj*] List of precomputed dynamical maps (superoperators), or a callback function that returns the superoperator at a given time.

times [array_like] List of times t_n at which to calculate $\rho(t_n)$

learningtimes [array_like] List of times t_k to use as learning times if argument *dynmaps* is a callback function.

three [float] Threshold for halting. Halts if $||T_n - T_{n-1}||$ is below treshold.

options [qutip.solver.Options] Generic solver options.

4.1.7 Solver Options and Results

opts = Options(order=10, ...)

or by changing the class attributes after creation:

```
opts = Options()
opts.order = 10
```

Returns options class to be used as options in evolution solvers.

Attributes

atol [float {1e-8}] Absolute tolerance.

rtol [float {1e-6}] Relative tolerance.

method [str {'adams','bdf'}] Integration method.

order [int {12}] Order of integrator (<=12 'adams', <=5 'bdf')

nsteps [int {2500}] Max. number of internal steps/call.

first_step [float $\{0\}$] Size of initial step (0 = automatic).

min_step [float $\{0\}$] Minimum step size (0 = automatic).

max_step [float {0}] Maximum step size (0 = automatic)

tidy [bool {True,False}] Tidyup Hamiltonian and initial state by removing small terms.

num_cpus [int] Number of cpus used by mcsolver (default = # of cpus).

- norm_tol [float] Tolerance used when finding wavefunction norm in mcsolve.
- **norm_steps** [int] Max. number of steps used to find wavefunction norm to within norm_tol in mcsolve.
- average_states [bool {False}] Average states values over trajectories in stochastic solvers.
- **average_expect** [bool {True}] Average expectation values over trajectories for stochastic solvers.
- **mc_corr_eps** [float {1e-10}] Arbitrarily small value for eliminating any divide-by-zero errors in correlation calculations when using mcsolve.

ntraj [int {500}] Number of trajectories in stochastic solvers.

openmp_threads [int] Number of OPENMP threads to use. Default is number of cpu cores.

rhs_reuse [bool {False,True}] Reuse Hamiltonian data.

rhs_with_state [bool {False,True}] Whether or not to include the state in the Hamiltonian function callback signature.

rhs_filename [str] Name for compiled Cython file.

seeds [ndarray] Array containing random number seeds for mcsolver.

store_final_state [bool {False, True}] Whether or not to store the final state of the evolution in the result class.

- **store_states** [bool {False, True}] Whether or not to store the state vectors or density matrices in the result class, even if expectation values operators are given. If no expectation are provided, then states are stored by default and this option has no effect.
- **use_openmp** [bool {True, False}] Use OPENMP for sparse matrix vector multiplication. Default None means auto check.

class Result

Class for storing simulation results from any of the dynamics solvers.

Attributes

solver [str] Which solver was used [e.g., 'mesolve', 'mcsolve', 'brmesolve', ...]

times [list/array] Times at which simulation data was collected.

expect [list/array] Expectation values (if requested) for simulation.

states [array] State of the simulation (density matrix or ket) evaluated at times.

num_expect [int] Number of expectation value operators in simulation.

num_collapse [int] Number of collapse operators in simualation.

- **ntraj** [int/list] Number of trajectories (for stochastic solvers). A list indicates that averaging of expectation values was done over a subset of total number of trajectories.
- col_times [list] Times at which state collpase occurred. Only for Monte Carlo solver.
- **col_which** [list] Which collapse operator was responsible for each collapse in col_times. Only for Monte Carlo solver.

class Stats (section_names=None)

Statistical information on the solver performance Statistics can be grouped into sections. If no section names are given in the the contructor, then all statistics will be added to one section 'main'

Parameters

section_names [list] list of keys that will be used as keys for the sections These keys will also be used as names for the sections The text in the output can be overidden by setting the header property of the section If no names are given then one section called 'main' is created

Attributes

- **sections** [OrderedDict of _StatsSection] These are the sections that are created automatically on instantiation or added using add_section
- header [string] Some text that will be used as the heading in the report By default there is None
- **total_time** [float] Time in seconds for the solver to complete processing Can be None, meaning that total timing percentages will be reported

Methods

add_section(self, name)	Add another section with the given name
<pre>add_count(self, key, value[, section])</pre>	Add value to count.
<pre>add_timing(self, key, value[, section])</pre>	Add value to timing.
add_message(self, key, value[, section, sep])	Add value to message.

report: Output the statistics report to console or file.

add_count (self, key, value, section=None)

Add value to count. If key does not already exist in section then it is created with this value. If key

already exists it is increased by the give value value is expected to be an integer

Parameters

key [string] key for the section.counts dictionary reusing a key will result in numerical addition of value

value [int] Initial value of the count, or added to an existing count

section: string or 'class' [_StatsSection] Section which to add the count to. If None given, the default (first) section will be used

add_message (self, key, value, section=None, sep=';')

Add value to message. If key does not already exist in section then it is created with this value. If key already exists the value is added to the message The value will be converted to a string

Parameters

key [string] key for the section.messages dictionary reusing a key will result in concatenation of value

value [int] Initial value of the message, or added to an existing message

sep [string] Message will be prefixed with this string when concatenating

section: string or 'class' [_StatsSection] Section which to add the message to. If None given, the default (first) section will be used

add_section (self, name)

Add another section with the given name

Parameters

name [string] will be used as key for sections dict will also be the header for the section

Returns

section [class] The new section

add_timing(self, key, value, section=None)

Add value to timing. If key does not already exist in section then it is created with this value. If key already exists it is increased by the give value value is expected to be a float, and given in seconds.

Parameters

- **key** [string] key for the section.timings dictionary reusing a key will result in numerical addition of value
- value [int] Initial value of the timing, or added to an existing timing
- **section: string or 'class'** [_StatsSection] Section which to add the timing to. If None given, the default (first) section will be used

clear (self)

Clear counts, timings and messages from all sections

report (*self*, *output*=<_*io*.*TextIOWrapper name*='<*stdout*>' *mode*='w' *encoding*='UTF-8'>)

Report the counts, timings and messages from the sections. Sections are reported in the order that the names were supplied in the constructor. The counts, timings and messages are reported in the order that they are added to the sections. The output can be written to anything that supports a write method, e.g. a file or the console (default). The output is intended to in markdown format

Parameters

output [stream] file or console stream - anything that support write - where the output will be written

set_total_time (self, value, section=None)

Sets the total time for the complete solve or for a specific section value is expected to be a float, and given in seconds

Parameters

value [float] Time in seconds to complete the solver section

section [string or *class*] Section which to set the total_time for If None given, the total_time for complete solve is set

class StochasticSolverOptions (me, H=None, $c_ops=[],$ $sc_ops=[],$ state0=None, $e_ops=[],$ m_ops=None, store_all_expect=False, store measurement=False, dW factors=None, solver=None, method='homodyne', normalize=None, times=None, nsubsteps=1, ntraj=1, tol=None, generate noise=None, noise=None, progress bar=None, *map_func=None*, *map_kwargs=None*, $args = \{\},\$ op*tions=None*, *noiseDepth=20*) Class of options for stochastic solvers such as gutip.stochastic.ssesolve, gutip.

stochastic.smesolve, etc.

The stochastic solvers qutip.stochastic.general_stochastic, qutip. stochastic.ssesolve, qutip.stochastic.smesolve, qutip.stochastic. photocurrent_sesolve and qutip.stochastic.photocurrent_mesolve all take the same keyword arguments as the constructor of these class, and internally they use these arguments to construct an instance of this class, so it is rarely needed to explicitly create an instance of this class.

Attributes

- H [qutip.Qobj, time-dependent Qobj as a list*] System Hamiltonian.
- state0 [qutip.Qobj] Initial state vector (ket) or density matrix.
- times [list / array] List of times for t. Must be uniformly spaced.
- **c_ops** [list of *qutip.Qobj*, *qutip.QobjEvo* or [Qobj, coeff*]] List of deterministic collapse operators.
- **sc_ops** [list of *qutip.Qobj*, *qutip.QobjEvo* or [Qobj, coeff*]] List of stochastic collapse operators. Each stochastic collapse operator will give a deterministic and stochastic contribution to the equation of motion according to how the d1 and d2 functions are defined.
- **e_ops** [list of *qutip.Qobj*] Single operator or list of operators for which to evaluate expectation values.
- **m_ops** [list of *qutip.Qobj*] List of operators representing the measurement operators. The expected format is a nested list with one measurement operator for each stochastic increament, for each stochastic collapse operator.
- args [dict] Dictionary of parameters for time dependent systems.
- tol [float] Tolerance of the solver for implicit methods.
- ntraj [int] Number of trajectors.
- nsubsteps [int] Number of sub steps between each time-spep given in times.
- **dW_factors** [array] Array of length len(sc_ops), containing scaling factors for each measurement operator in m_ops.
- solver [string] Name of the solver method to use for solving the stochastic equations. Valid values are: order 1/2 algorithms: 'euler-maruyama', 'pc-euler', 'pc-euler-imp' order 1 algorithms: 'milstein', 'platen', 'milstein-imp', 'rouchon' order 3/2 algorithms: 'taylor1.5', 'taylor1.5-imp', 'explicit1.5' order 2 algorithms: 'taylor2.0' call help of qutip.stochastic.stochastic_solvers for a description of the solvers. Implicit methods can adjust tolerance via the kw 'tol' default is {'tol':1e-6}
- **method** [string ('homodyne', 'heterodyne')] The name of the type of measurement process that give rise to the stochastic equation to solve.

- **store_all_expect** [bool (default False)] Whether or not to store the e_ops expect values for all paths.
- **store_measurement** [bool (default False)] Whether or not to store the measurement results in the *qutip.solver.Result* instance returned by the solver.
- noise [int, array[int, 1d], array[double, 4d]] int : seed of the noise array[int, 1d], length
 = ntraj, seeds for each trajectories array[double, 4d] (ntraj, len(times), nsubsteps,
 len(sc_ops)*[1l2])

vector for the noise, the len of the last dimensions is doubled for solvers of order 1.5. The correspond to results.noise

- **noiseDepth** [int] Number of terms kept of the truncated series used to create the noise used by taylor2.0 solver.
- **normalize** [bool] (default True for (photo)ssesolve, False for (photo)smesolve) Whether or not to normalize the wave function during the evolution. Normalizing density matrices introduce numerical errors.
- **options** [*qutip.solver.Options*] Generic solver options. Only options.average_states and options.store_states are used.
- map_func: function A map function or managing the calls to single-trajactory solvers.

map_kwargs: dictionary Optional keyword arguments to the map_func function function.

progress_bar [qutip.ui.BaseProgressBar] Optional progress bar class instance.

time-dependent Qobj can be used for H, c_ops and sc_ops.

The format for time-dependent system hamiltonian is:

- $\mathbf{H} = [\mathbf{Qobj0}, [\mathbf{Qobj1}, \mathbf{coeff1}], [\mathbf{Qobj2}, \mathbf{coeff2}], \dots] = \mathbf{Qobj0} + \mathbf{Qobj1} * \mathbf{coeff1}(t) + \mathbf{Qobj2} * \mathbf{coeff2}(t)$
- **coeff function can be:** function: coeff(t, args) -> complex str: "sin(1j*w*t)" np.array[complex, 1d] of length equal to the times array
- The argument args for the function coeff is the args keyword argument of the stochastic solver.
- Likewisem in str cases, the parameters ('w' in this case) are taken from the args keywords argument.

While mixing coeff type does not results in errors, it is not recommended.

For the collapse operators (c_ops, sc_ops):

Each operators can only be composed of 1 Qobj.

c_ops = [c_op1, c_op2, ...]

where, c_opN = Qobj or [Qobj,coeff]

The coeff format is the same as for the Hamiltonian.

4.1.8 Permutational Invariance

class Dicke (*N*, hamiltonian=None, emission=0.0, dephasing=0.0, pumping=0.0, collective_emission=0.0, collective_dephasing=0.0, collective_pumping=0.0)

The Dicke class which builds the Lindbladian and Liouvillian matrix.

Parameters

N: int The number of two-level systems.

hamiltonian [qutip.Qobj] A Hamiltonian in the Dicke basis.

The matrix dimensions are (nds, nds), with nds being the number of Dicke states. The Hamiltonian can be built with the operators given by the *jspin* functions.

emission: float Incoherent emission coefficient (also nonradiative emission). default: 0.0

dephasing: float Local dephasing coefficient. default: 0.0

pumping: float Incoherent pumping coefficient. default: 0.0

collective_emission: float Collective (superradiant) emmission coefficient. default: 0.0

collective_pumping: float Collective pumping coefficient. default: 0.0

collective_dephasing: float Collective dephasing coefficient. default: 0.0

Attributes

N: int The number of two-level systems.

hamiltonian [qutip.Qobj] A Hamiltonian in the Dicke basis.

The matrix dimensions are (nds, nds), with nds being the number of Dicke states. The Hamiltonian can be built with the operators given by the *jspin* function in the "dicke" basis.

emission: float Incoherent emission coefficient (also nonradiative emission). default: 0.0

dephasing: float Local dephasing coefficient. default: 0.0

pumping: float Incoherent pumping coefficient. default: 0.0

collective_emission: float Collective (superradiant) emmission coefficient. default: 0.0

collective_dephasing: float Collective dephasing coefficient. default: 0.0

collective_pumping: float Collective pumping coefficient. default: 0.0

nds: int The number of Dicke states.

dshape: tuple The shape of the Hilbert space in the Dicke or uncoupled basis. default: (nds, nds).

c_ops (self)

Build collapse operators in the full Hilbert space 2^N.

Returns

c_ops_list: list The list with the collapse operators in the 2^N Hilbert space.

coefficient_matrix(self)

Build coefficient matrix for ODE for a diagonal problem.

Returns

M: ndarray The matrix M of the coefficients for the ODE dp/dt = Mp. p is the vector of the diagonal matrix elements of the density matrix rho in the Dicke basis.

lindbladian (self)

Build the Lindbladian superoperator of the dissipative dynamics.

Returns

lindbladian [qutip.Qobj] The Lindbladian matrix as a qutip.Qobj.

liouvillian (*self*)

Build the total Liouvillian using the Dicke basis.

Returns

liouv [*qutip.Qobj*] The Liouvillian matrix for the system.

pisolve (self, initial_state, tlist, options=None)

Solve for diagonal Hamiltonians and initial states faster.

Parameters

initial_state [*qutip.Qobj*] An initial state specified as a density matrix of *qutip.Qbj* type.

tlist: ndarray A 1D numpy array of list of timesteps to integrate

options [qutip.solver.Options] The options for the solver.

Returns

result: list A dictionary of the type *qutip.solver.Result* which holds the results of the evolution.

class Pim (*N*, *emission=0.0*, *dephasing=0*, *pumping=0*, *collective_emission=0*, *collective_pumping=0*, *collective_dephasing=0*)

The Permutation Invariant Matrix class.

Initialize the class with the parameters for generating a Permutation Invariant matrix which evolves a given diagonal initial state *p* as:

dp/dt = Mp

Parameters

N: int The number of two-level systems.

emission: float Incoherent emission coefficient (also nonradiative emission). default: 0.0

dephasing: float Local dephasing coefficient. default: 0.0

pumping: float Incoherent pumping coefficient. default: 0.0

collective_emission: float Collective (superradiant) emmission coefficient. default: 0.0

collective_pumping: float Collective pumping coefficient. default: 0.0

collective_dephasing: float Collective dephasing coefficient. default: 0.0

Attributes

N: int The number of two-level systems.

emission: float Incoherent emission coefficient (also nonradiative emission). default: 0.0

dephasing: float Local dephasing coefficient. default: 0.0

pumping: float Incoherent pumping coefficient. default: 0.0

collective_emission: float Collective (superradiant) emmission coefficient. default: 0.0

collective_dephasing: float Collective dephasing coefficient. default: 0.0

collective_pumping: float Collective pumping coefficient. default: 0.0

M: dict A nested dictionary of the structure {row: {col: val}} which holds non zero elements of the matrix M

calculate_j_m (*self*, *dicke_row*, *dicke_col*)

Get the value of j and m for the particular Dicke space element.

Parameters

dicke_row, dicke_col: int The row and column from the Dicke space matrix

Returns

j, m: float The j and m values.

calculate_k (self, dicke_row, dicke_col)

Get k value from the current row and column element in the Dicke space.

Parameters

dicke_row, dicke_col: int The row and column from the Dicke space matrix.

Returns

k: int The row index for the matrix M for given Dicke space element.

coefficient_matrix(self)

Generate the matrix M governing the dynamics for diagonal cases.

If the initial density matrix and the Hamiltonian is diagonal, the evolution of the system is given by the simple ODE: dp/dt = Mp.

isdicke (self, dicke_row, dicke_col)

Check if an element in a matrix is a valid element in the Dicke space. Dicke row: j value index. Dicke column: m value index. The function returns True if the element exists in the Dicke space and False otherwise.

Parameters

dicke_row, dicke_col [int] Index of the element in Dicke space which needs to be checked

solve (self, rho0, tlist, options=None)

Solve the ODE for the evolution of diagonal states and Hamiltonians.

tau1(self, j, m)

Calculate coefficient matrix element relative to (j, m, m).

tau2 (*self*, *j*, *m*)

Calculate coefficient matrix element relative to (j, m+1, m+1).

tau3 (*self*, *j*, *m*)

Calculate coefficient matrix element relative to (j+1, m+1, m+1).

tau4 (*self*, *j*, *m*)

Calculate coefficient matrix element relative to (j-1, m+1, m+1).

tau5 (*self*, *j*, *m*)

Calculate coefficient matrix element relative to (j+1, m, m).

tau6 (*self*, *j*, *m*)

Calculate coefficient matrix element relative to (j-1, m, m).

tau7 (*self*, *j*, *m*)

Calculate coefficient matrix element relative to (j+1, m-1, m-1).

tau8 (*self*, *j*, *m*)

Calculate coefficient matrix element relative to (j, m-1, m-1).

tau9 (*self*, *j*, *m*)

Calculate coefficient matrix element relative to (j-1, m-1, m-1).

tau_valid (self, dicke_row, dicke_col)

Find the Tau functions which are valid for this value of (dicke_row, dicke_col) given the number of TLS. This calculates the valid tau values and reurns a dictionary specifying the tau function name and the value.

Parameters

dicke_row, dicke_col [int] Index of the element in Dicke space which needs to be checked.

Returns

taus: dict A dictionary of key, val as {tau: value} consisting of the valid taus for this row and column of the Dicke space element.

4.1.9 Distribution functions

```
class Distribution(data=None, xvecs=[], xlabels=[])
```

A class for representation spatial distribution functions.

The Distribution class can be used to prepresent spatial distribution functions of arbitray dimension (although only 1D and 2D distributions are used so far).

It is indented as a base class for specific distribution function, and provide implementation of basic functions that are shared among all Distribution functions, such as visualization, calculating marginal distributions, etc.

Parameters

data [array_like] Data for the distribution. The dimensions must match the lengths of the coordinate arrays in xvecs.

xvecs [list] List of arrays that spans the space for each coordinate.

xlabels [list] List of labels for each coordinate.

marginal (self, dim=0)

Calculate the marginal distribution function along the dimension *dim*. Return a new Distribution instance describing this reduced- dimensionality distribution.

Parameters

dim [int] The dimension (coordinate index) along which to obtain the marginal distribution.

Returns

d [Distributions] A new instances of Distribution that describes the marginal distribution.

project (self, dim=0)

Calculate the projection (max value) distribution function along the dimension *dim*. Return a new Distribution instance describing this reduced-dimensionality distribution.

Parameters

dim [int] The dimension (coordinate index) along which to obtain the projected distribution.

Returns

d [Distributions] A new instances of Distribution that describes the projection.

visualize (*self*, *fig=None*, *ax=None*, *figsize=*(8, 6), *colorbar=True*, *cmap=None*, *style='colormap'*, *show xlabel=True*, *show ylabel=True*)

Visualize the data of the distribution in 1D or 2D, depending on the dimensionality of the underlaying distribution.

Parameters:

fig [matplotlib Figure instance] If given, use this figure instance for the visualization,

ax [matplotlib Axes instance] If given, render the visualization using this axis instance.

figsize [tuple] Size of the new Figure instance, if one needs to be created.

colorbar: Bool Whether or not the colorbar (in 2D visualization) should be used.

cmap: matplotlib colormap instance If given, use this colormap for 2D visualizations.

style [string] Type of visualization: 'colormap' (default) or 'surface'.

Returns

fig, ax [tuple] A tuple of matplotlib figure and axes instances.

class WignerDistribution (rho=None, extent=[[-5, 5], [-5, 5]], steps=250)

class QDistribution (*rho=None*, *extent=*[[-5, 5], [-5, 5]], *steps=*250)

class TwoModeQuadratureCorrelation (state=None, theta1=0.0, theta2=0.0, extent=[[-5, 5], [-5, 5]], steps=250)

update (self, state)

calculate probability distribution for quadrature measurement outcomes given a two-mode wavefunction or density matrix

update_psi(self, psi)

calculate probability distribution for quadrature measurement outcomes given a two-mode wavefunction

update_rho(self, rho)

calculate probability distribution for quadrature measurement outcomes given a two-mode density matrix

class HarmonicOscillatorWaveFunction (psi=None, omega=1.0, extent=[-5, 5], steps=250)

update (*self*, *psi*) Calculate the wavefunction for the given state of an harmonic oscillator

update (self, rho)

Calculate the probability function for the given state of an harmonic oscillator (as density matrix)

4.1.10 Quantum information processing

class Gate (*name*, *targets=None*, *controls=None*, *arg_value=None*, *arg_label=None*) Representation of a quantum gate, with its required parametrs, and target and control qubits.

Parameters

name [string] Gate name.

targets [list or int] Gate targets.

controls [list or int] Gate controls.

arg_value [float] Argument value(phi).

arg_label [string] Label for gate representation.

class QubitCircuit (*N*, *input_states=None*, *output_states=None*, *reverse_states=True*, *user_gates=None*)

Representation of a quantum program/algorithm, maintaining a sequence of gates.

Parameters

N [int] Number of qubits in the system.

user_gates [dict] Define a dictionary of the custom gates. See examples for detail.

input_states [list] A list of string such as 0,'+', "A", "Y". Only used for latex.

Examples

```
>>> def user_gate():
... mat = np.array([[1., 0],
... [0., 1.j]])
... return Qobj(mat, dims=[[2], [2]])
>>> qc.QubitCircuit(2, user_gates={"T":user_gate})
>>> qc.add_gate("T", targets=[0])
```

add_lq_gate (self, name, start=0, end=None, qubits=None, arg_value=None, arg_label=None)
Adds a single qubit gate with specified parameters on a variable number of qubits in the circuit. By
default, it applies the given gate to all the qubits in the register.

Parameters

name [string] Gate name.

start [int] Starting location of qubits.

end [int] Last qubit for the gate.

qubits [list] Specific qubits for applying gates.

arg_value [float] Argument value(phi).

arg_label [string] Label for gate representation.

add_circuit (self, qc, start=0)

Adds a block of a qubit circuit to the main circuit. Globalphase gates are not added.

Parameters

qc [QubitCircuit] The circuit block to be added to the main circuit.

start [int] The qubit on which the first gate is applied.

add_gate (self, gate, targets=None, controls=None, arg_value=None, arg_label=None, index=None)

Adds a gate with specified parameters to the circuit.

Parameters

gate: string or 'Gate' Gate name. If gate is an instance of *Gate*, parameters are unpacked and added.

targets: list Gate targets.

controls: list Gate controls.

arg_value: float Argument value(phi).

arg_label: string Label for gate representation.

index [list] Positions to add the gate.

add_state (self, state, targets=None, state_type='input')

Add an input or ouput state to the circuit. By default all the input and output states will be initialized to *None*. A particular state can be added by specifying the state and the qubit where it has to be added along with the type as input or output.

Parameters

state: str The state that has to be added. It can be any string such as 0, '+', "A", "Y"

targets: list A list of qubit positions where the given state has to be added.

state_type: str One of either "input" or "output". This specifies whether the state to be
 added is an input or output. default: "input"

adjacent_gates (self)

Method to resolve two qubit gates with non-adjacent control/s or target/s in terms of gates with adjacent interactions.

Returns

qc [QubitCircuit] Return QubitCircuit of the gates for the qubit circuit with the resolved non-adjacent gates.

propagators (self)

Propagator matrix calculator for N qubits returning the individual steps as unitary matrices operating from left to right.

Returns

U_list [list] Return list of unitary matrices for the qubit circuit.

remove_gate (self, index=None, end=None, name=None, remove='first')

Remove a gate from a specific index or between two indexes or the first, last or all instances of a particular gate.

Parameters

index [int] Location of gate to be removed.

name [string] Gate name to be removed.

remove [string] If first or all gate are to be removed.

resolve_gates (self, basis=['CNOT', 'RX', 'RY', 'RZ'])

Unitary matrix calculator for N qubits returning the individual steps as unitary matrices operating from left to right in the specified basis.

Parameters

basis [list.] Basis of the resolved circuit.

Returns

qc [QubitCircuit] Return QubitCircuit of resolved gates for the qubit circuit in the desired basis.

reverse_circuit (self)

Reverse an entire circuit of unitary gates.

Returns

qc [QubitCircuit] Return QubitCircuit of resolved gates for the qubit circuit in the reverse order.

class CircuitProcessor(N, correct_global_phase)

Base class for representation of the physical implementation of a quantum program/algorithm on a specified qubit system.

adjacent_gates (self, qc, setup)

Function to take a quantum circuit/algorithm and convert it into the optimal form/basis for the desired physical system.

Parameters

qc: QubitCircuit Takes the quantum circuit to be implemented.

setup: String Takes the nature of the spin chain; linear or circular.

Returns

qc: QubitCircuit The resolved circuit representation.

get_ops_and_u(self)

Returns the Hamiltonian operators and corresponding values by stacking them together.

get_ops_labels(self)

Returns the Hamiltonian operators and corresponding labels by stacking them together.

load_circuit (self, qc)

Translates an abstract quantum circuit to its corresponding Hamiltonian for a specific model.

Parameters

qc: QubitCircuit Takes the quantum circuit to be implemented.

optimize_circuit (self, qc)

Function to take a quantum circuit/algorithm and convert it into the optimal form/basis for the desired physical system.

Parameters

qc: QubitCircuit Takes the quantum circuit to be implemented.

Returns

qc: QubitCircuit The optimal circuit representation.

plot_pulses (self)

Maps the physical interaction between the circuit components for the desired physical system.

Returns

fig, ax: Figure Maps the physical interaction between the circuit components.

pulse_matrix(self)

Generates the pulse matrix for the desired physical system.

Returns

t, u, labels: Returns the total time and label for every operation.

run (self, qc=None)

Generates the propagator matrix by running the Hamiltonian for the appropriate time duration for the desired physical system.

Parameters

qc: QubitCircuit Takes the quantum circuit to be implemented.

Returns

U_list: list The propagator matrix obtained from the physical implementation.

run_state (self, qc=None, states=None)

Generates the propagator matrix by running the Hamiltonian for the appropriate time duration for the desired physical system with the given initial state of the qubit register.

Parameters

qc: QubitCircuit Takes the quantum circuit to be implemented.

states: Qobj Initial state of the qubits in the register.

Returns

U_list: list The propagator matrix obtained from the physical implementation.

class SpinChain (*N*, *correct_global_phase=True*, *sx=None*, *sz=None*, *sxsy=None*)

Representation of the physical implementation of a quantum program/algorithm on a spin chain qubit system.

adjacent_gates (self, qc, setup='linear')

Method to resolve 2 qubit gates with non-adjacent control/s or target/s in terms of gates with adjacent interactions for linear/circular spin chain system.

Parameters

qc: QubitCircuit The circular spin chain circuit to be resolved

setup: Boolean Linear of Circular spin chain setup

Returns

qc: QubitCircuit Returns QubitCircuit of resolved gates for the qubit circuit in the desired basis.

get_ops_and_u(self)

Returns the Hamiltonian operators and corresponding values by stacking them together.

load_circuit (self, qc)

Translates an abstract quantum circuit to its corresponding Hamiltonian for a specific model.

Parameters

qc: QubitCircuit Takes the quantum circuit to be implemented.

optimize_circuit (self, qc)

Function to take a quantum circuit/algorithm and convert it into the optimal form/basis for the desired physical system.

Parameters

qc: QubitCircuit Takes the quantum circuit to be implemented.

Returns

qc: QubitCircuit The optimal circuit representation.

class LinearSpinChain (*N*, correct_global_phase=True, sx=None, sz=None, sxsy=None)

Representation of the physical implementation of a quantum program/algorithm on a spin chain qubit system arranged in a linear formation. It is a sub-class of SpinChain.

adjacent_gates (self, qc)

Method to resolve 2 qubit gates with non-adjacent control/s or target/s in terms of gates with adjacent interactions for linear/circular spin chain system.

Parameters

qc: QubitCircuit The circular spin chain circuit to be resolved

setup: Boolean Linear of Circular spin chain setup

Returns

qc: QubitCircuit Returns QubitCircuit of resolved gates for the qubit circuit in the desired basis.

get_ops_labels(self)

Returns the Hamiltonian operators and corresponding labels by stacking them together.

class CircularSpinChain (N, correct_global_phase=True, sx=None, sz=None, sxsy=None)

Representation of the physical implementation of a quantum program/algorithm on a spin chain qubit system arranged in a circular formation. It is a sub-class of SpinChain.

adjacent_gates (self, qc)

Method to resolve 2 qubit gates with non-adjacent control/s or target/s in terms of gates with adjacent interactions for linear/circular spin chain system.

Parameters

qc: QubitCircuit The circular spin chain circuit to be resolved

setup: Boolean Linear of Circular spin chain setup

Returns

qc: QubitCircuit Returns QubitCircuit of resolved gates for the qubit circuit in the desired basis.

get_ops_labels(self)

Returns the Hamiltonian operators and corresponding labels by stacking them together.

class DispersivecQED (*N*, correct_global_phase=True, Nres=None, deltamax=None, epsmax=None, w0=None, wq=None, eps=None, delta=None, g=None)

Representation of the physical implementation of a quantum program/algorithm on a dispersive cavity-QED system.

dispersive_gate_correction (*self*, *qc1*, *rwa=True*)

Method to resolve ISWAP and SQRTISWAP gates in a cQED system by adding single qubit gates to get the correct output matrix.

Parameters

qc: Qobj The circular spin chain circuit to be resolved

rwa: Boolean Specify if RWA is used or not.

Returns

qc: QubitCircuit Returns QubitCircuit of resolved gates for the qubit circuit in the desired basis.

get_ops_and_u(self)

Returns the Hamiltonian operators and corresponding values by stacking them together.

get_ops_labels(self)

Returns the Hamiltonian operators and corresponding labels by stacking them together.

load_circuit (self, qc)

Translates an abstract quantum circuit to its corresponding Hamiltonian for a specific model.

Parameters

qc: QubitCircuit Takes the quantum circuit to be implemented.

optimize_circuit (self, qc)

Function to take a quantum circuit/algorithm and convert it into the optimal form/basis for the desired physical system.

Parameters

qc: QubitCircuit Takes the quantum circuit to be implemented.

Returns

qc: QubitCircuit The optimal circuit representation.

4.1.11 Optimal control

class Optimizer(config, dyn, params=None)

Base class for all control pulse optimisers. This class should not be instantiated, use its subclasses This class implements the fidelity, gradient and interation callback functions. All subclass objects must be initialised with a

OptimConfig instance - various configuration options Dynamics instance - describes the dynamics of the (quantum) system

to be control optimised

Attributes

log_level [integer] level of messaging output from the logger. Options are attributes of qutip.logging_utils, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN

- **params: Dictionary** The key value pairs are the attribute name and value Note: attributes are created if they do not exist already, and are overwritten if they do.
- alg [string] Algorithm to use in pulse optimisation. Options are:

'GRAPE' (default) - GRadient Ascent Pulse Engineering 'CRAB' - Chopped RAndom Basis

- **alg_params** [Dictionary] options that are specific to the pulse optim algorithm that is GRAPE or CRAB
- **disp_conv_msg** [bool] Set true to display a convergence message (for scipy.optimize.minimize methods anyway)
- **optim_method** [string] a scipy.optimize.minimize method that will be used to optimise the pulse for minimum fidelity error
- **method_params** [Dictionary] Options for the optim_method. Note that where there is an equivalent attribute of this instance or the termination_conditions (for example maxiter) it will override an value in these options
- **approx_grad** [bool] If set True then the method will approximate the gradient itself (if it has requirement and facility for this) This will mean that the fid_err_grad_wrapper will not get called Note it should be left False when using the Dynamics to calculate approximate gradients Note it is set True automatically when the alg is CRAB
- **amp_lbound** [float or list of floats] lower boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control
- **amp_ubound** [float or list of floats] upper boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control
- **bounds** [List of floats] Bounds for the parameters. If not set before the run_optimization call then the list is built automatically based on the amp_lbound and amp_ubound attributes. Setting this attribute directly allows specific bounds to be set for individual parameters. Note: Only some methods use bounds
- **dynamics** [Dynamics (subclass instance)] describes the dynamics of the (quantum) system to be control optimised (see Dynamics classes for details)
- config [OptimConfig instance] various configuration options (see OptimConfig for details)
- **termination_conditions** [TerminationCondition instance] attributes determine when the optimisation will end
- pulse_generator [PulseGen (subclass instance)] (can be) used to create initial pulses not used by the class, but set by pulseoptim.create_pulse_optimizer
- **stats** [Stats] attributes of which give performance stats for the optimisation set to None to reduce overhead of calculating stats. Note it is (usually) shared with the Dynamics instance
- **dump** [dump.OptimDump] Container for data dumped during the optimisation. Can be set by specifying the dumping level or set directly. Note this is mainly intended for user and a development debugging but could be used for status information during a long optimisation.
- dumping [string] The level of data dumping that will occur during the optimisation -NONE : No processing data dumped (Default) - SUMMARY : A summary at each iteration will be recorded - FULL : All logs will be generated and dumped - CUSTOM : Some customised level of dumping When first set to CUSTOM this is equivalent to SUMMARY.
- dump_to_file [bool] If set True then data will be dumped to file during the optimisation
 dumping will be set to SUMMARY during init_optim if dump_to_file is True and dumping not set. Default is False

- **dump_dir** [string] Basically a link to dump.dump_dir. Exists so that it can be set through optim_params. If dump is None then will return None or will set dumping to SUM-MARY when setting a path
- **iter_summary** [OptimIterSummary] Summary of the most recent iteration. Note this is only set if dummping is on

apply_method_params (self, params=None)

Loops through all the method_params (either passed here or the method_params attribute) If the name matches an attribute of this object or the termination conditions object, then the value of this attribute is set. Otherwise it is assumed to a method_option for the scipy.optimize.minimize function

apply_params (self, params=None)

Set object attributes based on the dictionary (if any) passed in the instantiation, or passed as a parameter This is called during the instantiation automatically. The key value pairs are the attribute name and value Note: attributes are created if they do not exist already, and are overwritten if they do.

property dumping

The level of data dumping that will occur during the optimisation

- NONE : No processing data dumped (Default)
- SUMMARY : A summary at each iteration will be recorded
- FULL : All logs will be generated and dumped
- CUSTOM : Some customised level of dumping

When first set to CUSTOM this is equivalent to SUMMARY. It is then up to the user to specify which logs are dumped

fid_err_func_wrapper(self, *args)

Get the fidelity error achieved using the ctrl amplitudes passed in as the first argument.

This is called by generic optimisation algorithm as the func to the minimised. The argument is the current variable values, i.e. control amplitudes, passed as a flat array. Hence these are reshaped as $[nTimeslots, n_ctrls]$ and then used to update the stored ctrl values (if they have changed)

The error is checked against the target, and the optimisation is terminated if the target has been achieved.

fid_err_grad_wrapper(self, *args)

Get the gradient of the fidelity error with respect to all of the variables, i.e. the ctrl amplidutes in each timeslot

This is called by generic optimisation algorithm as the gradients of func to the minimised wrt the variables. The argument is the current variable values, i.e. control amplitudes, passed as a flat array. Hence these are reshaped as [nTimeslots, n_ctrls] and then used to update the stored ctrl values (if they have changed)

Although the optimisation algorithms have a check within them for function convergence, i.e. local minima, the sum of the squares of the normalised gradient is checked explicitly, and the optimisation is terminated if this is below the min_gradient_norm condition

init_optim(self, term_conds)

Check optimiser attribute status and passed parameters before running the optimisation. This is called by run_optimization, but could called independently to check the configuration.

iter_step_callback_func (self, *args)

Check the elapsed wall time for the optimisation run so far. Terminate if this has exceeded the maximum allowed time

run_optimization (self, term_conds=None)

This default function optimisation method is a wrapper to the scipy.optimize.minimize function.

It will attempt to minimise the fidelity error with respect to some parameters, which are determined by _get_optim_var_vals (see below)

The optimisation end when one of the passed termination conditions has been met, e.g. target achieved, wall time, or function call or iteration count exceeded. Note these conditions include gradient minimum met (local minima) for methods that use a gradient.

The function minimisation method is taken from the optim_method attribute. Note that not all of these methods have been tested. Note that some of these use a gradient and some do not. See the scipy documentation for details. Options specific to the method can be passed setting the method_params attribute.

If the parameter term_conds=None, then the termination_conditions attribute must already be set. It will be overwritten if the parameter is not None

The result is returned in an OptimResult object, which includes the final fidelity, time evolution, reason for termination etc

class OptimizerBFGS (config, dyn, params=None)

Implements the run_optimization method using the BFGS algorithm

run_optimization (self, term_conds=None)

Optimise the control pulse amplitudes to minimise the fidelity error using the BFGS (Broyden–Fletcher–Goldfarb–Shanno) algorithm The optimisation end when one of the passed termination conditions has been met, e.g. target achieved, gradient minimum met (local minima), wall time / iteration count exceeded.

Essentially this is wrapper to the: scipy.optimize.fmin_bfgs function

If the parameter term_conds=None, then the termination_conditions attribute must already be set. It will be overwritten if the parameter is not None

The result is returned in an OptimResult object, which includes the final fidelity, time evolution, reason for termination etc

class OptimizerLBFGSB(config, dyn, params=None)

Implements the run_optimization method using the L-BFGS-B algorithm

Attributes

max_metric_corr [integer] The maximum number of variable metric corrections used to define the limited memory matrix. That is the number of previous gradient values that are used to approximate the Hessian see the scipy.optimize.fmin_l_bfgs_b documentation for description of m argument

init_optim(self, term_conds)

Check optimiser attribute status and passed parameters before running the optimisation. This is called by run_optimization, but could called independently to check the configuration.

run_optimization (self, term_conds=None)

Optimise the control pulse amplitudes to minimise the fidelity error using the L-BFGS-B algorithm, which is the constrained (bounded amplitude values), limited memory, version of the Broyden–Fletcher–Goldfarb–Shanno algorithm.

The optimisation end when one of the passed termination conditions has been met, e.g. target achieved, gradient minimum met (local minima), wall time / iteration count exceeded.

Essentially this is wrapper to the: scipy.optimize.fmin_l_bfgs_b function This in turn is a warpper for well established implementation of the L-BFGS-B algorithm written in Fortran, which is therefore very fast. See SciPy documentation for credit and details on this function.

If the parameter term_conds=None, then the termination_conditions attribute must already be set. It will be overwritten if the parameter is not None

The result is returned in an OptimResult object, which includes the final fidelity, time evolution, reason for termination etc

class OptimizerCrab(config, dyn, params=None)

Optimises the pulse using the CRAB algorithm [1]. It uses the scipy.optimize.minimize function with the

method specified by the optim_method attribute. See Optimizer.run_optimization for details It minimises the fidelity error function with respect to the CRAB basis function coefficients.

AJGP ToDo: Add citation here

init_optim(self, term_conds)

Check optimiser attribute status and passed parameters before running the optimisation. This is called by run_optimization, but could called independently to check the configuration.

class OptimizerCrabFmin (config, dyn, params=None)

Optimises the pulse using the CRAB algorithm [1, 2]. It uses the scipy.optimize.fmin function which is effectively a wrapper for the Nelder-mead method. It minimises the fidelity error function with respect to the CRAB basis function coefficients. This is the default Optimizer for CRAB.

Notes

[1] P. Doria, T. Calarco & S. Montangero. Phys. Rev. Lett. 106, 190501 (2011).

[2] T. Caneva, T. Calarco, & S. Montangero. Phys. Rev. A 84, 022326 (2011).

run_optimization (self, term_conds=None)

This function optimisation method is a wrapper to the scipy.optimize.fmin function.

It will attempt to minimise the fidelity error with respect to some parameters, which are determined by _get_optim_var_vals which in the case of CRAB are the basis function coefficients

The optimisation end when one of the passed termination conditions has been met, e.g. target achieved, wall time, or function call or iteration count exceeded. Specifically to the fmin method, the optimisation will stop when change parameter values is less than xtol or the change in function value is below ftol.

If the parameter term_conds=None, then the termination_conditions attribute must already be set. It will be overwritten if the parameter is not None

The result is returned in an OptimResult object, which includes the final fidelity, time evolution, reason for termination etc

class OptimIterSummary

A summary of the most recent iteration of the pulse optimisation

Attributes

iter_num [int] Iteration number of the pulse optimisation

fid_func_call_num [int] Fidelity function call number of the pulse optimisation

grad_func_call_num [int] Gradient function call number of the pulse optimisation

fid_err [float] Fidelity error

- **grad_norm** [float] fidelity gradient (wrt the control parameters) vector norm that is the magnitude of the gradient
- wall_time [float] Time spent computing the pulse optimisation so far (in seconds of elapsed
 time)

class TerminationConditions

Base class for all termination conditions Used to determine when to stop the optimisation algorithm Note different subclasses should be used to match the type of optimisation being used

Attributes

fid_err_targ [float] Target fidelity error

fid_goal [float] goal fidelity, e.g. 1 - self.fid_err_targ It its typical to set this for unitary systems

max_wall_time [float] # maximum time for optimisation (seconds)

- min_gradient_norm [float] Minimum normalised gradient after which optimisation will
 terminate
- max_iterations [integer] Maximum iterations of the optimisation algorithm
- max_fid_func_calls [integer] Maximum number of calls to the fidelity function during the
 optimisation algorithm
- **accuracy_factor** [float] Determines the accuracy of the result. Typical values for accuracy_factor are: 1e12 for low accuracy; 1e7 for moderate accuracy; 10.0 for extremely high accuracy scipy.optimize.fmin_l_bfgs_b factr argument. Only set for specific methods (fmin_l_bfgs_b) that uses this Otherwise the same thing is passed as method_option ftol (although the scale is different) Hence it is not defined here, but may be set by the user

class OptimResult

Attributes give the result of the pulse optimisation attempt

Attributes

termination_reason [string] Description of the reason for terminating the optimisation

fidelity [float] final (normalised) fidelity that was achieved

initial_fid_err [float] fidelity error before optimisation starting

fid_err [float] final fidelity error that was achieved

goal_achieved [boolean] True is the fidely error achieved was below the target

- grad_norm_final [float] Final value of the sum of the squares of the (normalised) fidelity error gradients
- **grad_norm_min_reached** [float] True if the optimisation terminated due to the minimum value of the gradient being reached

num_iter [integer] Number of iterations of the optimisation algorithm completed

max_iter_exceeded [boolean] True if the iteration limit was reached

max_fid_func_exceeded [boolean] True if the fidelity function call limit was reached

wall_time [float] time elapsed during the optimisation

- wall_time_limit_exceeded [boolean] True if the wall time limit was reached
- **time** [array[num_tslots+1] of float] Time are the start of each timeslot with the final value being the total evolution time
- initial_amps [array[num_tslots, n_ctrls]] The amplitudes at the start of the optimisation
- final_amps [array[num_tslots, n_ctrls]] The amplitudes at the end of the optimisation

evo_full_final [Qobj] The evolution operator from t=0 to t=T based on the final amps

evo_full_initial [Qobj] The evolution operator from t=0 to t=T based on the initial amps

stats [Stats] Object containing the stats for the run (if any collected)

optimizer [Optimizer] Instance of the Optimizer used to generate the result

class Dynamics (*optimconfig*, *params=None*)

This is a base class only. See subclass descriptions and choose an appropriate one for the application.

Note that initialize_controls must be called before most of the methods can be used. init_timeslots can be called sometimes earlier in order to access timeslot related attributes

This acts as a container for the operators that are used to calculate time evolution of the system under study. That is the dynamics generators (Hamiltonians, Lindbladians etc), the propagators from one timeslot to the next, and the evolution operators. Due to the large number of matrix additions and multiplications, for small systems at least, the optimisation performance is much better using ndarrays to represent these operators. However

Attributes

- **log_level** [integer] level of messaging output from the logger. Options are attributes of qutip.logging_utils, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN
- **params: Dictionary** The key value pairs are the attribute name and value Note: attributes are created if they do not exist already, and are overwritten if they do.
- **stats** [Stats] Attributes of which give performance stats for the optimisation set to None to reduce overhead of calculating stats. Note it is (usually) shared with the Optimizer object
- **tslot_computer** [TimeslotComputer (subclass instance)] Used to manage when the timeslot dynamics generators, propagators, gradients etc are updated
- **prop_computer** [PropagatorComputer (subclass instance)] Used to compute the propagators and their gradients
- **fid_computer** [FidelityComputer (subclass instance)] Used to computer the fidelity error and the fidelity error gradient.
- **memory_optimization** [int] Level of memory optimisation. Setting to 0 (default) means that execution speed is prioritized over memory. Setting to 1 means that some memory prioritisation steps will be taken, for instance using Qobj (and hence sparse arrays) as the the internal operator data type, and not caching some operators Potentially further memory saving maybe made with memory_optimization > 1. The options are processed in _set_memory_optimizations, see this for more information. Individual memory saving options can be switched by setting them directly (see below)
- **oper_dtype** [type] Data type for internal dynamics generators, propagators and time evolution operators. This can be ndarray or Qobj, or (in theory) any other representation that supports typical matrix methods (e.g. dot) ndarray performs best for smaller quantum systems. Qobj may perform better for larger systems, and will also perform better when (custom) fidelity measures use Qobj methods such as partial trace. See _choose_oper_dtype for how this is chosen when not specified
- **cache_phased_dyn_gen** [bool] If True then the dynamics generators will be saved with and without the propagation prefactor (if there is one) Defaults to True when memory_optimization=0, otherwise False
- **cache_prop_grad** [bool] If the True then the propagator gradients (for exact gradients) will be computed when the propagator are computed and cache until the are used by the fidelity computer. If False then the fidelity computer will calculate them as needed. Defaults to True when memory_optimization=0, otherwise False
- **cache_dyn_gen_eigenvectors_adj: bool** If True then DynamicsUnitary will cached the adjoint of the Hamiltion eignvector matrix Defaults to True when memory_optimization=0, otherwise False
- sparse_eigen_decomp: bool If True then DynamicsUnitary will use the sparse eigenvalue decomposition. Defaults to True when memory_optimization<=1, otherwise False</pre>
- num_tslots [integer] Number of timeslots (aka timeslices)

num_ctrls [integer] calculate the of controls from the length of the control list

- evo_time [float] Total time for the evolution
- tau [array[num_tslots] of float] Duration of each timeslot Note that if this is set before initialize_controls is called then num_tslots and evo_time are calculated from tau, otherwise tau is generated from num_tslots and evo_time, that is equal size time slices

- **time** [array[num_tslots+1] of float] Cumulative time for the evolution, that is the time at the start of each time slice
- **drift_dyn_gen** [Qobj or list of Qobj] Drift or system dynamics generator (Hamiltonian) Matrix defining the underlying dynamics of the system Can also be a list of Qobj (length num_tslots) for time varying drift dynamics
- **ctrl_dyn_gen** [List of Qobj] Control dynamics generator (Hamiltonians) List of matrices defining the control dynamics
- **initial** [Qobj] Starting state / gate The matrix giving the initial state / gate, i.e. at time 0 Typically the identity for gate evolution
- target [Qobj] Target state / gate: The matrix giving the desired state / gate for the evolution
- **ctrl_amps** [array[num_tslots, num_ctrls] of float] Control amplitudes The amplitude (scale factor) for each control in each timeslot
- **initial_ctrl_scaling** [float] Scale factor applied to be applied the control amplitudes when they are initialised This is used by the PulseGens rather than in any functions in this class
- **initial_ctrl_offset** [float] Linear offset applied to be applied the control amplitudes when they are initialised This is used by the PulseGens rather than in any functions in this class
- dyn_gen [List of Qobj] List of combined dynamics generators (Qobj) for each timeslot
- prop [list of Qobj] List of propagators (Qobj) for each timeslot
- *prop_grad* [array[num_tslots, num_ctrls] of Qobj] Array of propagator gradients (Qobj) for each timeslot, control
- fwd_evo [List of Qobj] List of evolution operators (Qobj) from the initial to the given
- onwd_evo [List of Qobj] List of evolution operators (Qobj) from the initial to the given
- onto_evo [List of Qobj] List of evolution operators (Qobj) from the initial to the given
- **evo_current** [Boolean] Used to flag that the dynamics used to calculate the evolution operators is current. It is set to False when the amplitudes change
- fact_mat_round_prec [float] Rounding precision used when calculating the factor matrix to determine if two eigenvalues are equivalent Only used when the PropagatorComputer uses diagonalisation
- def_amps_fname [string] Default name for the output used when save_amps is called
- **unitarity_check_level** [int] If > 0 then unitarity of the system evolution is checked at at evolution recomputation. level 1 checks all propagators level 2 checks eigen basis as well Default is 0
- unitarity_tol: Tolerance used in checking if operator is unitary Default is 1e-10
- **dump** [dump.DynamicsDump] Store of historical calculation data. Set to None (Default) for no storing of historical data Use dumping property to set level of data dumping
- *dumping* [string] The level of data dumping that will occur during the time evolution calculation.
- dump_to_file [bool] If set True then data will be dumped to file during the calculations
 dumping will be set to SUMMARY during init_evo if dump_to_file is True and dumping
 not set. Default is False
- **dump_dir** [string] Basically a link to dump.dump_dir. Exists so that it can be set through dyn_params. If dump is None then will return None or will set dumping to SUMMARY when setting a path

apply_params (self, params=None)

Set object attributes based on the dictionary (if any) passed in the instantiation, or passed as a parameter This is called during the instantiation automatically. The key value pairs are the attribute name and value Note: attributes are created if they do not exist already, and are overwritten if they do.

combine_dyn_gen (self, k)

Computes the dynamics generator for a given timeslot The is the combined Hamiltion for unitary systems

compute_evolution (self)

Recalculate the time evolution operators Dynamics generators (e.g. Hamiltonian) and prop (propagators) are calculated as necessary Actual work is completed by the recompute_evolution method of the timeslot computer

property dumping

The level of data dumping that will occur during the time evolution calculation.

- NONE : No processing data dumped (Default)
- SUMMARY : A summary of each time evolution will be recorded
- FULL : All operators used or created in the calculation dumped
- CUSTOM : Some customised level of dumping

When first set to CUSTOM this is equivalent to SUMMARY. It is then up to the user to specify which operators are dumped WARNING: FULL could consume a lot of memory!

property dyn_gen

List of combined dynamics generators (Qobj) for each timeslot

property dyn_gen_phase

Some op that is applied to the dyn_gen before expontiating to get the propagator. See *phase_application* for how this is applied

flag_system_changed(self)

Flag evolution, fidelity and gradients as needing recalculation

property full_evo

Full evolution - time evolution at final time slot

property fwd_evo

List of evolution operators (Qobj) from the initial to the given timeslot

$get_ctrl_dyn_gen(self, j)$

Get the dynamics generator for the control Not implemented in the base class. Choose a subclass

get_drift_dim(self)

Returns the size of the matrix that defines the drift dynamics that is assuming the drift is NxN, then this returns N

get_dyn_gen (self, k)

Get the combined dynamics generator for the timeslot Not implemented in the base class. Choose a subclass

get_num_ctrls(self)

calculate the of controls from the length of the control list sets the num_ctrls property, which can be used alternatively subsequently

init_timeslots(self)

Generate the timeslot duration array 'tau' based on the evo_time and num_tslots attributes, unless the tau attribute is already set in which case this step in ignored Generate the cumulative time array 'time' based on the tau values

initialize_controls (self, amps, init_tslots=True)

Set the initial control amplitudes and time slices Note this must be called after the configuration is complete before any dynamics can be calculated

property num_ctrls

calculate the of controls from the length of the control list sets the num_ctrls property, which can be used alternatively subsequently

property onto_evo

List of evolution operators (Qobj) from the initial to the given timeslot

property onwd_evo

List of evolution operators (Qobj) from the initial to the given timeslot

property phase_application

scalar(string), default='preop' Determines how the phase is applied to the dynamics generators

- 'preop' : P = expm(phase*dyn_gen)
- 'postop' : P = expm(dyn_gen*phase)
- · 'custom' : Customised phase application

The 'custom' option assumes that the _apply_phase method has been set to a custom function

Type phase_application

property prop

List of propagators (Qobj) for each timeslot

property prop_grad

Array of propagator gradients (Qobj) for each timeslot, control

refresh_drift_attribs(self)

Reset the dyn_shape, dyn_dims and time_depend_drift attribs

save_amps (self, file_name=None, times=None, amps=None, verbose=False)

Save a file with the current control amplitudes in each timeslot The first column in the file will be the start time of the slot

Parameters

- **file_name** [string] Name of the file If None given the def_amps_fname attribuite will be used
- **times** [List type (or string)] List / array of the start times for each slot If None given this will be retrieved through get_amp_times() If 'exclude' then times will not be saved in the file, just the amplitudes
- **amps** [Array[num_tslots, num_ctrls]] Amplitudes to be saved If None given the ctrl_amps attribute will be used

verbose [Boolean] If True then an info message will be logged

unitarity_check(self)

Checks whether all propagators are unitary

update_ctrl_amps (self, new_amps)

Determine if any amplitudes have changed. If so, then mark the timeslots as needing recalculation The actual work is completed by the compare_amps method of the timeslot computer

class DynamicsGenMat(optimconfig, params=None)

This sub class can be used for any system where no additional operator is applied to the dynamics generator before calculating the propagator, e.g. classical dynamics, Lindbladian

class DynamicsUnitary(optimconfig, params=None)

This is the subclass to use for systems with dynamics described by unitary matrices. E.g. closed systems with Hermitian Hamiltonians Note a matrix diagonalisation is used to compute the exponent The eigen decomposition is also used to calculate the propagator gradient. The method is taken from DYNAMO (see file header)

Attributes

- **drift_ham** [Qobj] This is the drift Hamiltonian for unitary dynamics It is mapped to drift_dyn_gen during initialize_controls
- **ctrl_ham** [List of Qobj] These are the control Hamiltonians for unitary dynamics It is mapped to ctrl_dyn_gen during initialize_controls
- **H** [List of Qobj] The combined drift and control Hamiltonians for each timeslot These are the dynamics generators for unitary dynamics. It is mapped to dyn_gen during initialize_controls

check_unitarity(self)

Checks whether all propagators are unitary For propagators found not to be unitary, the potential underlying causes are investigated.

initialize_controls (self, amplitudes, init_tslots=True)

Set the initial control amplitudes and time slices Note this must be called after the configuration is complete before any dynamics can be calculated

property num_ctrls

calculate the of controls from the length of the control list sets the num_ctrls property, which can be used alternatively subsequently

class DynamicsSymplectic(optimconfig, params=None)

Symplectic systems This is the subclass to use for systems where the dynamics is described by symplectic matrices, e.g. coupled oscillators, quantum optics

Attributes

omega [array[drift_dyn_gen.shape]] matrix used in the calculation of propagators (time evolution) with symplectic systems.

property dyn_gen_phase

The phasing operator for the symplectic group generators usually refered to as Omega By default this is applied as 'postop' dyn_gen*-Omega If phase_application is 'preop' it is applied as Omega*dyn_gen

class PropagatorComputer(dynamics, params=None)

Base for all Propagator Computer classes that are used to calculate the propagators, and also the propagator gradient when exact gradient methods are used Note: they must be instantiated with a Dynamics object, that is the container for the data that the functions operate on This base class cannot be used directly. See subclass descriptions and choose the appropriate one for the application

Attributes

- **log_level** [integer] level of messaging output from the logger. Options are attributes of qutip_utils.logging, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN
- **grad_exact** [boolean] indicates whether the computer class instance is capable of computing propagator gradients. It is used to determine whether to create the Dynamics prop_grad array

apply_params (self, params=None)

Set object attributes based on the dictionary (if any) passed in the instantiation, or passed as a parameter This is called during the instantiation automatically. The key value pairs are the attribute name and value Note: attributes are created if they do not exist already, and are overwritten if they do.

reset (self)

reset any configuration data

class PropCompApproxGrad (dynamics, params=None)

This subclass can be used when the propagator is calculated simply by expm of the dynamics generator, i.e. when gradients will be calculated using approximate methods.

reset (self)

reset any configuration data

class PropCompDiag(dynamics, params=None)

Coumputes the propagator exponentiation using diagonalisation of of the dynamics generator

reset (self)

reset any configuration data

class PropCompFrechet (dynamics, params=None)

Frechet method for calculating the propagator: exponentiating the combined dynamics generator

and the propagator gradient It should work for all systems, e.g. unitary, open, symplectic There are other PropagatorComputer subclasses that may be more efficient

reset (self)

reset any configuration data

class FidelityComputer(dynamics, params=None)

Base class for all Fidelity Computers. This cannot be used directly. See subclass descriptions and choose one appropriate for the application Note: this must be instantiated with a Dynamics object, that is the container for the data that the methods operate on

Attributes

- **log_level** [integer] level of messaging output from the logger. Options are attributes of qutip.logging_utils, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN
- dimensional_norm [float] Normalisation constant
- fid_norm_func [function] Used to normalise the fidelity See SU and PSU options for the unitary dynamics
- grad_norm_func [function] Used to normalise the fidelity gradient See SU and PSU options for the unitary dynamics
- **uses_onwd_evo** [boolean] flag to specify whether the onwd_evo evolution operator (see Dynamics) is used by the FidelityComputer

uses_onto_evo [boolean]

- **flag to specify whether the onto_evo evolution operator** (see Dynamics) is used by the FidelityComputer
- fid_err [float] Last computed value of the fidelity error
- fidelity [float] Last computed value of the normalised fidelity
- **fidelity_current** [boolean] flag to specify whether the fidelity / fid_err are based on the current amplitude values. Set False when amplitudes change
- fid_err_grad: array[num_tslot, num_ctrls] of float Last computed values for the fidelity
 error gradients wrt the control in the timeslot
- grad_norm [float] Last computed value for the norm of the fidelity error gradients (sqrt of the sum of the squares)
- fid_err_grad_current [boolean] flag to specify whether the fidelity / fid_err are based on the current amplitude values. Set False when amplitudes change

apply_params (self, params=None)

Set object attributes based on the dictionary (if any) passed in the instantiation, or passed as a parameter This is called during the instantiation automatically. The key value pairs are the attribute name and value Note: attributes are created if they do not exist already, and are overwritten if they do.

clear(self)

clear any temporarily held status data

flag_system_changed(self)

Flag fidelity and gradients as needing recalculation

get_fid_err(self)

returns the absolute distance from the maximum achievable fidelity

get_fid_err_gradient (self)

Returns the normalised gradient of the fidelity error in a (nTimeslots x n_ctrls) array wrt the timeslot control amplitude

initialises the computer based on the configuration of the Dynamics

init_comp (self)

reset (self)

reset any configuration data and clear any temporarily held status data

class FidCompUnitary(dynamics, params=None)

Computes fidelity error and gradient assuming unitary dynamics, e.g. closed qubit systems Note fidelity and gradient calculations were taken from DYNAMO (see file header)

Attributes

phase_option [string]

determines how global phase is treated in fidelity calculations: PSU - global phase ignored SU - global phase included

fidelity_prenorm [complex] Last computed value of the fidelity before it is normalised It is stored to use in the gradient normalisation calculation

fidelity_prenorm_current [boolean] flag to specify whether fidelity_prenorm are based on the current amplitude values. Set False when amplitudes change

clear (self)

clear any temporarily held status data

compute_fid_grad(self)

Calculates exact gradient of function wrt to each timeslot control amplitudes. Note these gradients are not normalised These are returned as a (nTimeslots x n_ctrls) array

flag_system_changed(self)

Flag fidelity and gradients as needing recalculation

get_fid_err(self)

Gets the absolute error in the fidelity

get_fid_err_gradient (self)

Returns the normalised gradient of the fidelity error in a (nTimeslots x n_ctrls) array The gradients are cached in case they are requested multiple times between control updates (although this is not typically found to happen)

get_fidelity(self)

Gets the appropriately normalised fidelity value The normalisation is determined by the fid_norm_func pointer which should be set in the config

get_fidelity_prenorm(self)

Gets the current fidelity value prior to normalisation Note the gradient function uses this value The value is cached, because it is used in the gradient calculation

init_comp (self)

Check configuration and initialise the normalisation

init_normalization(self)

Calc norm of <Ufinal | Ufinal> to scale subsequent norms When considering unitary time evolution operators, this basically results in calculating the trace of the identity matrix and is hence equal to the

size of the target matrix There may be situations where this is not the case, and hence it is not assumed to be so. The normalisation function called should be set to either the PSU - global phase ignored SU - global phase respected

normalize_PSU(self, A)

normalize_SU(self, A)

normalize_gradient_PSU(*self*, *grad*)

Normalise the gradient matrix passed as grad This PSU version is independent of global phase

normalize_gradient_SU (self, grad)

Normalise the gradient matrix passed as grad This SU version respects global phase

reset (self)

reset any configuration data and clear any temporarily held status data

set_phase_option (self, phase_option=None)

Deprecated - use phase_option Phase options are SU - global phase important PSU - global phase is not important

class FidCompTraceDiff(dynamics, params=None)

Computes fidelity error and gradient for general system dynamics by calculating the the fidelity error as the trace of the overlap of the difference between the target and evolution resulting from the pulses with the transpose of the same. This should provide a distance measure for dynamics described by matrices Note the gradient calculation is taken from: 'Robust quantum gates for open systems via optimal control: Markovian versus non-Markovian dynamics' Frederik F Floether, Pierre de Fouquieres, and Sophie G Schirmer

Attributes

scale_factor [float] The fidelity error calculated is of some arbitary scale. This factor can be used to scale the fidelity error such that it may represent some physical measure If None is given then it is caculated as 1/2N, where N is the dimension of the drift, when the Dynamics are initialised.

compute_fid_err_grad(self)

Calculate exact gradient of the fidelity error function wrt to each timeslot control amplitudes. Uses the trace difference norm fidelity These are returned as a (nTimeslots x n_ctrls) array

get_fid_err(self)

Gets the absolute error in the fidelity

get_fid_err_gradient (self)

Returns the normalised gradient of the fidelity error in a (nTimeslots x n_ctrls) array The gradients are cached in case they are requested multiple times between control updates (although this is not typically found to happen)

init_comp (self)

initialises the computer based on the configuration of the Dynamics Calculates the scale_factor is not already set

reset (self)

reset any configuration data and clear any temporarily held status data

class FidCompTraceDiffApprox(dynamics, params=None)

As FidCompTraceDiff, except uses the finite difference method to compute approximate gradients

Attributes

epsilon [float] control amplitude offset to use when approximating the gradient wrt a timeslot control amplitude

compute_fid_err_grad(self)

Calculates gradient of function wrt to each timeslot control amplitudes. Note these gradients are not normalised They are calulated These are returned as a (nTimeslots x n_{ctrls}) array

reset (self)

reset any configuration data and clear any temporarily held status data

class TimeslotComputer (dynamics, params=None)

Base class for all Timeslot Computers Note: this must be instantiated with a Dynamics object, that is the container for the data that the methods operate on

Attributes

- **log_level** [integer] level of messaging output from the logger. Options are attributes of qutip.logging_utils, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN
- evo_comp_summary [EvoCompSummary] A summary of the most recent evolution computation Used in the stats and dump Will be set to None if neither stats or dump are set

apply_params (self, params=None)

Set object attributes based on the dictionary (if any) passed in the instantiation, or passed as a parameter This is called during the instantiation automatically. The key value pairs are the attribute name and value Note: attributes are created if they do not exist already, and are overwritten if they do.

dump_current (self)

Store a copy of the current time evolution

class TSlotCompUpdateAll(dynamics, params=None)

Timeslot Computer - Update All Updates all dynamics generators, propagators and evolutions when ctrl amplitudes are updated

compare_amps (self, new_amps)

Determine if any amplitudes have changed. If so, then mark the timeslots as needing recalculation Returns: True if amplitudes are the same, False if they have changed

get_timeslot_for_fidelity_calc(self)

Returns the timeslot index that will be used calculate current fidelity value. This (default) method simply returns the last timeslot

recompute_evolution(self)

Recalculates the evolution operators. Dynamics generators (e.g. Hamiltonian) and prop (propagators) are calculated as necessary

class PulseGen(dyn=None, params=None)

Pulse generator Base class for all Pulse generators The object can optionally be instantiated with a Dynamics object, in which case the timeslots and amplitude scaling and offset are copied from that. Otherwise the class can be used independently by setting: tau (array of timeslot durations) or num_tslots and pulse_time for equally spaced timeslots

Attributes

num_tslots [integer] Number of timeslots, aka timeslices (copied from Dynamics if given)

- pulse_time [float] total duration of the pulse (copied from Dynamics.evo_time if given)
- **offset** [float] linear offset applied to the pulse (copied from Dynamics.initial_ctrl_offset if given)
- tau [array[num_tslots] of float] Duration of each timeslot (copied from Dynamics if given)
- **lbound** [float] Lower boundary for the pulse amplitudes Note that the scaling and offset attributes can be used to fully bound the pulse for all generators except some of the random ones This bound (if set) may result in additional shifting / scaling Default is -Inf

- **ubound** [float] Upper boundary for the pulse amplitudes Note that the scaling and offset attributes can be used to fully bound the pulse for all generators except some of the random ones This bound (if set) may result in additional shifting / scaling Default is Inf
- periodic [boolean] True if the pulse generator produces periodic pulses
- **random** [boolean] True if the pulse generator produces random pulses
- **log_level** [integer] level of messaging output from the logger. Options are attributes of qutip.logging_utils, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN

apply_params (self, params=None)

Set object attributes based on the dictionary (if any) passed in the instantiation, or passed as a parameter This is called during the instantiation automatically. The key value pairs are the attribute name and value

gen_pulse (self)

returns the pulse as an array of vales for each timeslot Must be implemented by subclass

init_pulse(self)

Initialise the pulse parameters

reset (self)

reset attributes to default values

class PulseGenRandom(*dyn=None*, *params=None*)

Generates random pulses as simply random values for each timeslot

gen_pulse(self)

Generate a pulse of random values between 1 and -1 Values are scaled using the scaling property and shifted using the offset property Returns the pulse as an array of vales for each timeslot

reset (self)

reset attributes to default values

class PulseGenZero (dyn=None, params=None)

Generates a flat pulse

gen_pulse (self)

Generate a pulse with the same value in every timeslot. The value will be zero, unless the offset is not zero, in which case it will be the offset

class PulseGenLinear(dyn=None, params=None)

Generates linear pulses

Attributes

- **gradient** [float] Gradient of the line. Note this is calculated from the start_val and end_val if these are given
- start_val [float] Start point of the line. That is the starting amplitude

end_val [float] End point of the line. That is the amplitude at the start of the last timeslot

gen_pulse (*self*, *gradient=None*, *start_val=None*, *end_val=None*)

Generate a linear pulse using either the gradient and start value or using the end point to calulate the gradient Note that the scaling and offset parameters are still applied, so unless these values are the default 1.0 and 0.0, then the actual gradient etc will be different Returns the pulse as an array of vales for each timeslot

init_pulse (self, gradient=None, start_val=None, end_val=None)

Calculate the gradient if pulse is defined by start and end point values

reset (self)

reset attributes to default values

class PulseGenPeriodic (*dyn=None*, *params=None*)

Intermediate class for all periodic pulse generators All of the periodic pulses range from -1 to 1 All have a start phase that can be set between 0 and 2pi

Attributes

- num_waves [float] Number of complete waves (cycles) that occur in the pulse. wavelen and freq calculated from this if it is given
- wavelen [float] Wavelength of the pulse (assuming the speed is 1) freq is calculated from this if it is given

freq [float] Frequency of the pulse

start_phase [float] Phase of the pulse signal when t=0

init_pulse (self, num_waves=None, wavelen=None, freq=None, start_phase=None)

Calculate the wavelength, frequency, number of waves etc from the each other and the other parameters If num_waves is given then the other parameters are worked from this Otherwise if the wavelength is given then it is the driver Otherwise the frequency is used to calculate wavelength and num_waves

reset (self)

reset attributes to default values

class PulseGenSine (*dyn=None*, *params=None*)

Generates sine wave pulses

gen_pulse (*self*, *num_waves=None*, *wavelen=None*, *freq=None*, *start_phase=None*)

Generate a sine wave pulse If no params are provided then the class object attributes are used. If they are provided, then these will reinitialise the object attribs. returns the pulse as an array of vales for each timeslot

class PulseGenSquare (*dyn=None*, *params=None*)

Generates square wave pulses

- **gen_pulse** (*self*, *num_waves=None*, *wavelen=None*, *freq=None*, *start_phase=None*) Generate a square wave pulse If no parameters are pavided then the class object attributes are used. If they are provided, then these will reinitialise the object attribs
- class PulseGenSaw(dyn=None, params=None)

Generates saw tooth wave pulses

gen_pulse (*self*, *num_waves=None*, *wavelen=None*, *freq=None*, *start_phase=None*)

Generate a saw tooth wave pulse If no parameters are pavided then the class object attributes are used. If they are provided, then these will reinitialise the object attribs

class PulseGenTriangle(dyn=None, params=None) Generates triangular wave pulses

```
gen_pulse (self, num_waves=None, wavelen=None, freq=None, start_phase=None)
```

Generate a sine wave pulse If no parameters are pavided then the class object attributes are used. If they are provided, then these will reinitialise the object attribs

class PulseGenGaussian (*dyn=None*, *params=None*)

Generates pulses with a Gaussian profile

gen_pulse (self, mean=None, variance=None)

Generate a pulse with Gaussian shape. The peak is centre around the mean and the variance determines the breadth The scaling and offset attributes are applied as an amplitude and fixed linear offset. Note that the maximum amplitude will be scaling + offset.

reset (self)

reset attributes to default values

class PulseGenGaussianEdge(dyn=None, params=None)

Generate pulses with inverted Gaussian ramping in and out It's intended use for a ramping modulation, which is often required in experimental setups.

Attributes

decay_time [float] Determines the ramping rate. It is approximately the time required to bring the pulse to full amplitude It is set to 1/10 of the pulse time by default

gen_pulse (self, decay_time=None)

Generate a pulse that starts and ends at zero and 1.0 in between then apply scaling and offset The tailing in and out is an inverted Gaussian shape

reset (self)

reset attributes to default values

class PulseGenCrab (*dyn=None*, *num_coeffs=None*, *params=None*)

Base class for all CRAB pulse generators Note these are more involved in the optimisation process as they are used to produce piecewise control amplitudes each time new optimisation parameters are tried

Attributes

num_coeffs [integer] Number of coefficients used for each basis function

num_basis_funcs [integer] Number of basis functions In this case set at 2 and should not be changed

coeffs [float array[num_coeffs, num_basis_funcs]] The basis coefficient values

randomize_coeffs [bool] If True (default) then the coefficients are set to some random values when initialised, otherwise they will all be equal to self.scaling

estimate_num_coeffs (self, dim)

Estimate the number coefficients based on the dimensionality of the system. :returns: **num_coeffs** – estimated number of coefficients :rtype: int

get_optim_var_vals (self)

Get the parameter values to be optimised :returns: :rtype: list (or 1d array) of floats

init_coeffs (self, num_coeffs=None)

Generate the initial ceofficent values.

Parameters

num_coeffs [integer] Number of coefficients used for each basis function If given this overides the default and sets the attribute of the same name.

init_pulse(self, num_coeffs=None)

Set the initial freq and coefficient values

reset (self)

reset attributes to default values

set_optim_var_vals (self, param_vals)

Set the values of the any of the pulse generation parameters based on new values from the optimisation method Typically this will be the basis coefficients

class PulseGenCrabFourier (*dyn=None*, *num_coeffs=None*, *params=None*)

Generates a pulse using the Fourier basis functions, i.e. sin and cos

Attributes

freqs [float array[num_coeffs]] Frequencies for the basis functions

randomize_freqs [bool] If True (default) the some random offset is applied to the frequencies

gen_pulse (self, coeffs=None)

Generate a pulse using the Fourier basis with the freqs and coeffs attributes.

Parameters

coeffs [float array[num_coeffs, num_basis_funcs]] The basis coefficient values If given this overides the default and sets the attribute of the same name.

init_freqs(self)

Generate the frequencies These are the Fourier harmonics with a uniformly distributed random offset

init_pulse (self, num_coeffs=None)
Set the initial freq and coefficient values

reset (self)

reset attributes to default values

class Stats

Base class for all optimisation statistics Used for configurations where all timeslots are updated each iteration e.g. exact gradients Note that all times are generated using timeit.default_timer() and are in seconds

Attributes

dyn_gen_name [string] Text used in some report functions. Makes sense to set it to 'Hamiltonian' when using unitary dynamics Default is simply 'dynamics generator'

num_iter [integer] Number of iterations of the optimisation algorithm

wall_time_optim_start [float] Start time for the optimisation

wall_time_optim_end [float] End time for the optimisation

wall_time_optim [float] Time elasped during the optimisation

- **wall_time_dyn_gen_compute** [float] Total wall (elasped) time computing combined dynamics generator (for example combining drift and control Hamiltonians)
- wall_time_prop_compute [float] Total wall (elasped) time computing propagators, that is the time evolution from one timeslot to the next Includes calculating the propagator gradient for exact gradients
- wall_time_fwd_prop_compute [float] Total wall (elasped) time computing combined forward propagation, that is the time evolution from the start to a specific timeslot. Excludes calculating the propagators themselves
- wall_time_onwd_prop_compute [float] Total wall (elasped) time computing combined onward propagation, that is the time evolution from a specific timeslot to the end time. Excludes calculating the propagators themselves
- **wall_time_gradient_compute** [float] Total wall (elasped) time computing the fidelity error gradient. Excludes calculating the propagator gradients (in exact gradient methods)

- **num_fidelity_computes** [integer] Number of time the fidelity is computed (It is only computed if any amplitudes changed since the last call)
- **num_grad_computes** [integer] Number of time the gradient is computed (It is only computed if any amplitudes changed since the last call)
- num_ctrl_amp_updates [integer] Number of times the control amplitudes are updated
- mean_num_ctrl_amp_updates_per_iter [float] Mean number of control amplitude updates per iteration

- num_timeslot_changes [integer] Number of times the amplitudes of a any control in a
 timeslot changes
- **mean_num_timeslot_changes_per_update** [float] Mean average number of timeslot amplitudes that are changed per update
- num_ctrl_amp_changes [integer] Number of times individual control amplitudes that are changed
- **mean_num_ctrl_amp_changes_per_update** [float] Mean average number of control amplitudes that are changed per update

calculate (self)

Perform the calculations (e.g. averages) that are required on the stats Should be called before calling report

report (self)

Print a report of the stats to the console

class Dump

A container for dump items. The lists for dump items is depends on the type Note: abstract class

Attributes

- **parent** [some control object (Dynamics or Optimizer)] aka the host. Object that generates the data that is dumped and is host to this dump object.
- **dump_dir** [str] directory where files (if any) will be written out the path and be relative or absolute use ~/ to specify user home directory Note: files are only written when write_to_file is True of writeout is called explicitly Defaults to ~/.qtrl_dump
- *level* [string] The level of data dumping that will occur SUMMARY : A summary will be recorded FULL : All possible dumping CUSTOM : Some customised level of dumping When first set to CUSTOM this is equivalent to SUMMARY.
- write_to_file [bool] When set True data and summaries (as configured) will be written interactively to file during the processing Set during instantiation by the host based on its dump_to_file attrib
- dump_file_ext [str] Default file extension for any file names that are auto generated
- **fname_base** [str] First part of any auto generated file names. This is usually overridden in the subclass
- **dump_summary** [bool] If True a summary is recorded each time a new item is added to the the dump. Default is True
- summary_sep [str] delimiter for the summary file. default is a space
- data_sep [str] delimiter for the data files (arrays saved to file). default is a space
- summary_file [str] File path for summary file. Automatically generated. Can be set specifically

create_dump_dir(self)

Checks dump directory exists, creates it if not

property level

The level of data dumping that will occur

- SUMMARY : A summary will be recorded
- FULL : All possible dumping
- CUSTOM : Some customised level of dumping

When first set to CUSTOM this is equivalent to SUMMARY. It is then up to the user to specify what specifically is dumped

class OptimDump (optim, level='SUMMARY')

A container for dumps of optimisation data generated during the pulse optimisation.

Attributes

dump_summary [bool] When True summary items are appended to the iter_summary

iter_summary [list of optimizer.OptimIterSummary] Summary at each iteration

dump_fid_err [bool] When True values are appended to the fid_err_log

fid_err_log [list of float] Fidelity error at each call of the fid_err_func

dump_grad_norm [bool] When True values are appended to the fid_err_log

grad_norm_log [list of float] Gradient norm at each call of the grad_norm_log

dump_grad [bool] When True values are appended to the grad_log

grad_log [list of ndarray] Gradients at each call of the fid_grad_func

add_iter_summary(self)

add copy of current optimizer iteration summary

property dump_all

True if everything (ignoring the summary) is to be dumped

property dump_any

True if anything other than the summary is to be dumped

update_fid_err_log (*self*, *fid_err*) add an entry to the fid_err log

update_grad_log (*self*, *grad*) add an entry to the grad log

update_grad_norm_log (self, grad_norm)
 add an entry to the grad_norm log

writeout (self, f=None)
 write all the logs and the summary out to file(s)

Parameters

f [filename or filehandle] If specified then all summary and object data will go in one file. If None is specified then type specific files will be generated in the dump_dir If a filehandle is specified then it must be a byte mode file as numpy.savetxt is used, and requires this.

class DynamicsDump(dynamics, level='SUMMARY')

A container for dumps of dynamics data. Mainly time evolution calculations

Attributes

dump_summary [bool] If True a summary is recorded

evo_summary [list of :class:'tslotcomp.EvoCompSummary'] Summary items are appended if dump_summary is True at each recomputation of the evolution.

dump_amps [bool] If True control amplitudes are dumped

dump_dyn_gen [bool] If True the dynamics generators (Hamiltonians) are dumped

dump_prop [bool] If True propagators are dumped

dump_prop_grad [bool] If True propagator gradients are dumped

dump_fwd_evo [bool] If True forward evolution operators are dumped

dump_onwd_evo [bool] If True onward evolution operators are dumped

dump_onto_evo [bool] If True onto (or backward) evolution operators are dumped

evo_dumps [list of *EvoCompDumpItem*] A new dump item is appended at each recomputation of the evolution. That is if any of the calculation objects are to be dumped.

add_evo_comp_summary (self, dump_item_idx=None)
 add copy of current evo comp summary

add_evo_dump(self)

Add dump of current time evolution generating objects

property dump_all

True if all of the calculation objects are to be dumped

property dump_any

True if any of the calculation objects are to be dumped

writeout (self, f=None)

write all the dump items and the summary out to file(s) :param f: If specified then all summary and object data will go in one file.

If None is specified then type specific files will be generated in the dump_dir If a filehandle is specified then it must be a byte mode file as numpy.savetxt is used, and requires this.

class DumpItem

An item in a dump list

class EvoCompDumpItem(dump)

A copy of all objects generated to calculate one time evolution Note the attributes are only set if the corresponding *DynamicsDump* dump_ attribute is set.

writeout (self, f=None)

write all the objects out to files

Parameters

f [filename or filehandle] If specified then all object data will go in one file. If None is specified then type specific files will be generated in the dump_dir If a filehandle is specified then it must be a byte mode file as numpy.savetxt is used, and requires this.

class DumpSummaryItem

A summary of the most recent iteration Abstract class only

Attributes: idx : int

Index in the summary list in which this is stored

4.2 Functions

4.2.1 Manipulation and Creation of States and Operators

Quantum States

basis (N, n=0, offset=0)

Generates the vector representation of a Fock state.

Parameters

N [int] Number of Fock states in Hilbert space.

- n [int] Integer corresponding to desired number state, defaults to 0 if omitted.
- **offset** [int (default 0)] The lowest number state that is included in the finite number state representation of the state.

Returns

state [qutip.Qobj] Qobj representing the requested number state |n>.

Notes

A subtle incompatibility with the quantum optics toolbox: In QuTiP:

basis(N, 0) = ground state

but in the qotoolbox:

basis(N, 1) = ground state

Examples

```
>>> basis(5,2)
Quantum object: dims = [[5], [1]], shape = [5, 1], type = ket
Qobj data =
[[ 0.+0.j]
[ 0.+0.j]
[ 1.+0.j]
[ 0.+0.j]
[ 0.+0.j]
[ 0.+0.j]]
```

bell_state(state='00')

Returns the Bell state:

 $\begin{aligned} |B00\rangle &= 1 / sqrt(2)*[|0\rangle|0\rangle+|1\rangle|1\rangle| |B01\rangle &= 1 / sqrt(2)*[|0\rangle|0\rangle-|1\rangle|1\rangle| |B10\rangle &= 1 / sqrt(2)*[|0\rangle|1\rangle+|1\rangle|0\rangle| |B11\rangle &= 1 / sqrt(2)*[|0\rangle|1\rangle-|1\rangle|0\rangle| \end{aligned}$

Returns

Bell_state [qobj] Bell state

bra(seq, dim=2)

Produces a multiparticle bra state for a list or string, where each element stands for state of the respective particle.

Parameters

- seq [str / list of ints or characters] Each element defines state of the respective particle. (e.g. [1,1,0,1] or a string "1101"). For qubits it is also possible to use the following conventions: - 'g'/'e' (ground and excited state) - 'u'/'d' (spin up and down) - 'H'/'V' (horizontal and vertical polarization) Note: for dimension > 9 you need to use a list.
- **dim** [int (default: 2) / list of ints] Space dimension for each particle: int if there are the same, list if they are different.

Returns

bra [qobj]

Examples

```
>>> bra("10")
Quantum object: dims = [[1, 1], [2, 2]], shape = [1, 4], type = bra
Qobj data =
[[ 0. 0. 1. 0.]]
```

```
>>> bra("Hue")
Quantum object: dims = [[1, 1, 1], [2, 2, 2]], shape = [1, 8], type = bra
Qobj data =
[[ 0. 1. 0. 0. 0. 0. 0. 0.]]
>>> bra("12", 3)
Quantum object: dims = [[1, 1], [3, 3]], shape = [1, 9], type = bra
Qobj data =
[[ 0. 0. 0. 0. 0. 1. 0. 0. 0.]]
>>> bra("31", [5, 2])
Quantum object: dims = [[1, 1], [5, 2]], shape = [1, 10], type = bra
Qobj data =
```

0. 0.]]

coherent (*N*, *alpha*, *offset*=0, *method*='operator')

Generates a coherent state with eigenvalue alpha.

0. 0.

Constructed using displacement operator on vacuum state.

0.

0. 1.

Parameters

[[0. 0. 0.

N [int] Number of Fock states in Hilbert space.

alpha [float/complex] Eigenvalue of coherent state.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the state. Using a non-zero offset will make the default method 'analytic'.

method [string { 'operator', 'analytic' }] Method for generating coherent state.

Returns

state [qobj] Qobj quantum object for coherent state

Notes

Select method 'operator' (default) or 'analytic'. With the 'operator' method, the coherent state is generated by displacing the vacuum state using the displacement operator defined in the truncated Hilbert space of size 'N'. This method guarantees that the resulting state is normalized. With 'analytic' method the coherent state is generated using the analytical formula for the coherent state coefficients in the Fock basis. This method does not guarantee that the state is normalized if truncated to a small number of Fock states, but would in that case give more accurate coefficients.

Examples

```
>>> coherent(5,0.25j)
Quantum object: dims = [[5], [1]], shape = [5, 1], type = ket
Qobj data =
[[ 9.69233235e-01+0.j ]
[ 0.0000000e+00+0.24230831j]
[ -4.28344935e-02+0.j ]
[ 0.0000000e+00-0.00618204j]
[ 7.80904967e-04+0.j ]]
```

coherent_dm(N, alpha, offset=0, method='operator')

Density matrix representation of a coherent state.

Constructed via outer product of qutip.states.coherent

Parameters

- N [int] Number of Fock states in Hilbert space.
- alpha [float/complex] Eigenvalue for coherent state.
- **offset** [int (default 0)] The lowest number state that is included in the finite number state representation of the state.
- **method** [string {'operator', 'analytic'}] Method for generating coherent density matrix.

Returns

dm [qobj] Density matrix representation of coherent state.

Notes

Select method 'operator' (default) or 'analytic'. With the 'operator' method, the coherent density matrix is generated by displacing the vacuum state using the displacement operator defined in the truncated Hilbert space of size 'N'. This method guarantees that the resulting density matrix is normalized. With 'analytic' method the coherent density matrix is generated using the analytical formula for the coherent state coefficients in the Fock basis. This method does not guarantee that the state is normalized if truncated to a small number of Fock states, but would in that case give more accurate coefficients.

Examples

```
>>> coherent_dm(3,0.25j)
Quantum object: dims = [[3], [3]], shape = [3, 3], type = oper, isHerm = True
Qobj data =
[[ 0.93941695+0.j 0.0000000-0.23480733j -0.04216943+0.j ]
[ 0.00000000+0.23480733j 0.05869011+0.j 0.00000000-0.01054025j]
[-0.04216943+0.j 0.0000000+0.01054025j 0.00189294+0.j ]]
```

enr_state_dictionaries (dims, excitations)

Return the number of states, and lookup-dictionaries for translating a state tuple to a state index, and vice versa, for a system with a given number of components and maximum number of excitations.

Parameters

dims: list A list with the number of states in each sub-system.

excitations [integer] The maximum numbers of dimension

Returns

nstates, state2idx, idx2state: integer, dict, dict The number of states *nstates*, a dictionary for looking up state indices from a state tuple, and a dictionary for looking up state state tuples from state indices.

enr_thermal_dm(dims, excitations, n)

Generate the density operator for a thermal state in the excitation-number- restricted state space defined by the *dims* and *excitations* arguments. See the documentation for enr_fock for a more detailed description of these arguments. The temperature of each mode in dims is specified by the average number of excitations *n*.

Parameters

dims [list] A list of the dimensions of each subsystem of a composite quantum system.

- excitations [integer] The maximum number of excitations that are to be included in the state space.
- **n** [integer] The average number of excitations in the thermal state. *n* can be a float (which then applies to each mode), or a list/array of the same length as dims, in which each element corresponds specifies the temperature of the corresponding mode.

Returns

dm [Qobj] Thermal state density matrix.

enr_fock (dims, excitations, state)

Generate the Fock state representation in a excitation-number restricted state space. The *dims* argument is a list of integers that define the number of quantums states of each component of a composite quantum system, and the *excitations* specifies the maximum number of excitations for the basis states that are to be included in the state space. The *state* argument is a tuple of integers that specifies the state (in the number basis representation) for which to generate the Fock state representation.

Parameters

dims [list] A list of the dimensions of each subsystem of a composite quantum system.

excitations [integer] The maximum number of excitations that are to be included in the state space.

state [list of integers] The state in the number basis representation.

Returns

ket [Qobj] A Qobj instance that represent a Fock state in the exication-number- restricted state space defined by *dims* and *excitations*.

fock (*N*, *n*=0, *offset*=0)

Bosonic Fock (number) state.

Same as qutip.states.basis.

Parameters

N [int] Number of states in the Hilbert space.

n [int] int for desired number state, defaults to 0 if omitted.

Returns

Requested number state $|n\rangle$ **.**

Examples

```
>>> fock(4,3)
Quantum object: dims = [[4], [1]], shape = [4, 1], type = ket
Qobj data =
[[ 0.+0.j]
[ 0.+0.j]
[ 0.+0.j]
[ 1.+0.j]]
```

 $fock_dm(N, n=0, offset=0)$

Density matrix representation of a Fock state

Constructed via outer product of *qutip.states.fock*.

Parameters

N [int] Number of Fock states in Hilbert space.

n [int] int for desired number state, defaults to 0 if omitted.

Returns

dm [qobj] Density matrix representation of Fock state.

Examples

```
>>> fock_dm(3,1)
Quantum object: dims = [[3], [3]], shape = [3, 3], type = oper, isHerm = True
Qobj data =
[[ 0.+0.j 0.+0.j 0.+0.j]
[ 0.+0.j 1.+0.j 0.+0.j]
[ 0.+0.j 0.+0.j 0.+0.j]]
```

$ghz_state(N=3)$

Returns the N-qubit GHZ-state.

Parameters

N [int (default=3)] Number of qubits in state

Returns

G [qobj] N-qubit GHZ-state

$\texttt{maximally_mixed_dm}\left(N\right)$

Returns the maximally mixed density matrix for a Hilbert space of dimension N.

Parameters

N [int] Number of basis states in Hilbert space.

Returns

dm [qobj] Thermal state density matrix.

ket (seq, dim=2)

Produces a multiparticle ket state for a list or string, where each element stands for state of the respective particle.

Parameters

- seq [str / list of ints or characters] Each element defines state of the respective particle. (e.g. [1,1,0,1] or a string "1101"). For qubits it is also possible to use the following conventions: - 'g'/'e' (ground and excited state) - 'u'/'d' (spin up and down) - 'H'/'V' (horizontal and vertical polarization) Note: for dimension > 9 you need to use a list.
- **dim** [int (default: 2) / list of ints] Space dimension for each particle: int if there are the same, list if they are different.

Returns

ket [qobj]

Examples

```
>>> ket("10")
Quantum object: dims = [[2, 2], [1, 1]], shape = [4, 1], type = ket
Qobj data =
[[ 0.]
[ 0.]
[ 1.]
[ 0.]]
```

```
>>> ket("Hue")
Quantum object: dims = [[2, 2, 2], [1, 1, 1]], shape = [8, 1], type = ket
Qobj data =
[[ 0.]
[ 1.]
[ 0.]
[ 0.]
[ 0.]
[ 0.]
```

(continues on next page)

(continued from previous page)

```
[ 0.]
 [ 0.]
 [ 0.]]
>>> ket("12", 3)
Quantum object: dims = [[3, 3], [1, 1]], shape = [9, 1], type = ket
Qobj data =
[[ 0.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 0.]
 [ 1.]
 [ 0.]
 [ 0.]
 [ 0.]]
>>> ket("31", [5, 2])
```

```
Quantum object: dims = [[5, 2], [1, 1]], shape = [10, 1], type = ket
Qobj data =
[[ 0.]
[ 0.]
[ 0.]
[ 0.]
[ 0.]
[ 0.]
[ 0.]
[ 0.]
[ 0.]
[ 0.]
[ 0.]
[ 0.]
[ 0.]
[ 0.]
```

$\texttt{ket2dm}\left(Q\right)$

Takes input ket or bra vector and returns density matrix formed by outer product.

Parameters

Q [qobj] Ket or bra type quantum object.

Returns

dm [qobj] Density matrix formed by outer product of Q.

Examples

```
>>> x=basis(3,2)
>>> ket2dm(x)
Quantum object: dims = [[3], [3]], shape = [3, 3], type = oper, isHerm = True
Qobj data =
[[ 0.+0.j 0.+0.j 0.+0.j]
[ 0.+0.j 0.+0.j 0.+0.j]
[ 0.+0.j 0.+0.j 1.+0.j]]
```

phase_basis (N, m, phi0=0)

Basis vector for the mth phase of the Pegg-Barnett phase operator.

Parameters

N [int] Number of basis vectors in Hilbert space.

m [int] Integer corresponding to the mth discrete phase phi_m=phi0+2*pi*m/N

phi0 [float (default=0)] Reference phase angle.

Returns

state [qobj] Ket vector for mth Pegg-Barnett phase operator basis state.

Notes

The Pegg-Barnett basis states form a complete set over the truncated Hilbert space.

projection (N, n, m, offset=0)

The projection operator that projects state |m> on state |n>.

Parameters

N [int] Number of basis states in Hilbert space.

n, **m** [float] The number states in the projection.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the projector.

Returns

oper [qobj] Requested projection operator.

qutrit_basis()

Basis states for a three level system (qutrit)

Returns

qstates [array] Array of qutrit basis vectors

singlet_state()

Returns the two particle singlet-state:

S>=1/sqrt(2)*[|0>|1>-|1>|0>]

that is identical to the fourth bell state.

Returns

Bell_state [qobj] |B11> Bell state

spin_state (j, m, type='ket')
Generates the spin state |j, m>, i.e. the eigenstate of the spin-j Sz operator with eigenvalue m.

Parameters

j [float] The spin of the state ().

m [int] Eigenvalue of the spin-j Sz operator.

type [string {'ket', 'bra', 'dm'}] Type of state to generate.

Returns

state [qobj] Qobj quantum object for spin state

spin_coherent (j, theta, phi, type='ket')
Generate the coherent spin state theta, phi>.

Parameters

j [float] The spin of the state.

theta [float] Angle from z axis.

phi [float] Angle from x axis.

type [string { 'ket', 'bra', 'dm' }] Type of state to generate.

Returns

state [qobj] Qobj quantum object for spin coherent state

state_number_enumerate (dims, excitations=None, state=None, idx=0)

An iterator that enumerate all the state number arrays (quantum numbers on the form [n1, n2, n3, ...]) for a system with dimensions given by dims.

Example

```
>>> for state in state_number_enumerate([2,2]):
>>> print(state)
[ 0     0 ]
[ 0     1 ]
[ 1     0 ]
[ 1     1 ]
```

Parameters

dims [list or array] The quantum state dimensions array, as it would appear in a Qobj.

state [list] Current state in the iteration. Used internally.

excitations [integer (None)] Restrict state space to states with excitation numbers below or equal to this value.

idx [integer] Current index in the iteration. Used internally.

Returns

state_number [list] Successive state number arrays that can be used in loops and other iterations, using standard state enumeration *by definition*.

state_number_index(dims, state)

Return the index of a quantum state corresponding to state, given a system with dimensions given by dims.

Example

```
>>> state_number_index([2, 2, 2], [1, 1, 0])
6
```

Parameters

dims [list or array] The quantum state dimensions array, as it would appear in a Qobj.

state [list] State number array.

Returns

idx [int] The index of the state given by *state* in standard enumeration ordering.

state_index_number (dims, index)

Return a quantum number representation given a state index, for a system of composite structure defined by dims.

Example

```
>>> state_index_number([2, 2, 2], 6)
[1, 1, 0]
```

Parameters

dims [list or array] The quantum state dimensions array, as it would appear in a Qobj.

index [integer] The index of the state in standard enumeration ordering.

Returns

state [list] The state number array corresponding to index *index* in standard enumeration ordering.

state_number_qobj(dims, state)

Return a Qobj representation of a quantum state specified by the state array state.

Example

```
>>> state_number_qobj([2, 2, 2], [1, 0, 1])
Quantum object: dims = [[2, 2, 2], [1, 1, 1]], shape = [8, 1], type = ket
Qobj data =
[[ 0.]
[ 0.]
[ 0.]
[ 0.]
[ 0.]
[ 1.]
[ 0.]
[ 0.]
[ 0.]
```

Parameters

dims [list or array] The quantum state dimensions array, as it would appear in a Qobj.

state [list] State number array.

Returns

state [qutip.Qobj.qobj] The state as a qutip.Qobj.qobj instance.

thermal_dm (*N*, *n*, *method='operator'*) Density matrix for a thermal state of n particles

Parameters

N [int] Number of basis states in Hilbert space.

n [float] Expectation value for number of particles in thermal state.

method [string {'operator', 'analytic'}] string that sets the method used to generate the thermal state probabilities

Returns

dm [qobj] Thermal state density matrix.

Notes

The 'operator' method (default) generates the thermal state using the truncated number operator num(N). This is the method that should be used in computations. The 'analytic' method uses the analytic coefficients derived in an infinite Hilbert space. The analytic form is not necessarily normalized, if truncated too aggressively.

Examples

```
>>> thermal_dm(5, 1)
Quantum object: dims = [[5], [5]], shape = [5, 5], type = oper, isHerm = True
Qobj data =
[[ 0.51612903 0.
                           0.
                                       0.
                                                   Ο.
                                                             1
              0.25806452 0.
 [ 0.
                                       Ο.
                                                   0.
                                                             ]
 [ 0.
                          0.12903226 0.
                                                   Ο.
              0.
                                                             1
              Ο.
                                       0.06451613 0.
 [ 0.
                           0.
                                                             1
 [ 0.
               0.
                           0.
                                       0.
                                                   0.0322580611
>>> thermal_dm(5, 1, 'analytic')
Quantum object: dims = [[5], [5]], shape = [5, 5], type = oper, isHerm = True
Qobj data =
                              0.
          Ο.
                    0.
                                       0.
[[ 0.5
                              0.
                                       0.
 [ 0.
           0.25
                   Ο.
           0.
 [ 0.
                    0.125
                             0.
                                       0.
                                              1
           0.
                    Ο.
 [ 0.
                              0.0625
                                       0.
                                              1
                                       0.03125]]
 [ 0.
           0.
                    0.
                             0.
```

zero_ket (N, dims=None)

Creates the zero ket vector with shape Nx1 and dimensions dims.

Parameters

N [int] Hilbert space dimensionality

dims [list] Optional dimensions if ket corresponds to a composite Hilbert space.

Returns

zero_ket [qobj] Zero ket on given Hilbert space.

Quantum Operators

This module contains functions for generating Qobj representation of a variety of commonly occuring quantum operators.

```
charge (Nmax, Nmin=None, frac=1)
```

Generate the diagonal charge operator over charge states from Nmin to Nmax.

Parameters

Nmax [int] Maximum charge state to consider.

Nmin [int (default = -Nmax)] Lowest charge state to consider.

frac [float (default = 1)] Specify fractional charge if needed.

Returns

C [Qobj] Charge operator over [Nmin,Nmax].

Notes

New in version 3.2.

```
commutator (A, B, kind='normal')
```

Return the commutator of kind kind (normal, anti) of the two operators A and B.

```
create(N, offset=0)
```

Creation (raising) operator.

Parameters

N [int] Dimension of Hilbert space.

Returns

oper [qobj] Qobj for raising operator.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

Examples

```
>>> create(4)
Quantum object: dims = [[4], [4]], shape = [4, 4], type = oper, isHerm = False
Qobj data =
[[ 0.00000000+0.j 0.00000000+0.j 0.0000000+0.j 0.00000000+0.j]
[ 1.00000000+0.j 0.0000000+0.j 0.0000000+0.j]
[ 0.00000000+0.j 1.41421356+0.j 0.00000000+0.j 0.0000000+0.j]
[ 0.00000000+0.j 0.0000000+0.j 1.73205081+0.j 0.0000000+0.j]]
```

destroy (N, offset=0)

Destruction (lowering) operator.

Parameters

N [int] Dimension of Hilbert space.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

Returns

oper [qobj] Qobj for lowering operator.

Examples

```
>>> destroy(4)
Quantum object: dims = [[4], [4]], shape = [4, 4], type = oper, isHerm = False
Qobj data =
[[ 0.00000000+0.j 1.00000000+0.j 0.00000000+0.j 0.00000000+0.j]
[ 0.00000000+0.j 0.00000000+0.j 1.41421356+0.j 0.00000000+0.j]
[ 0.00000000+0.j 0.00000000+0.j 1.73205081+0.j]
[ 0.00000000+0.j 0.00000000+0.j 0.0000000+0.j ]]
```

displace (N, alpha, offset=0)

Single-mode displacement operator.

Parameters

N [int] Dimension of Hilbert space.

alpha [float/complex] Displacement amplitude.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

Returns

oper [qobj] Displacement operator.

Examples

```
>>> displace(4,0.25)
Quantum object: dims = [[4], [4]], shape = [4, 4], type = oper, isHerm = False
Qobj data =
[[ 0.96923323+0.j -0.24230859+0.j 0.04282883+0.j -0.00626025+0.j]
[ 0.24230859+0.j 0.90866411+0.j -0.33183303+0.j 0.07418172+0.j]
```

(continues on next page)

(continued from previous page)

```
[ 0.04282883+0.j 0.33183303+0.j 0.84809499+0.j -0.41083747+0.j]
[ 0.00626025+0.j 0.07418172+0.j 0.41083747+0.j 0.90866411+0.j]]
```

enr_destroy (dims, excitations)

Generate annihilation operators for modes in a excitation-number-restricted state space. For example, consider a system consisting of 4 modes, each with 5 states. The total hilbert space size is $5^{**4} = 625$. If we are only interested in states that contain up to 2 excitations, we only need to include states such as

(0, 0, 0, 0) (0, 0, 0, 1) (0, 0, 0, 2) (0, 0, 1, 0) (0, 0, 1, 1) (0, 0, 2, 0) ...

This function creates annihilation operators for the 4 modes that act within this state space:

a1, a2, a3, a4 = enr_destroy([5, 5, 5, 5], excitations=2)

From this point onwards, the annihiltion operators a1, ..., a4 can be used to setup a Hamiltonian, collapse operators and expectation-value operators, etc., following the usual pattern.

Parameters

dims [list] A list of the dimensions of each subsystem of a composite quantum system.

excitations [integer] The maximum number of excitations that are to be included in the state space.

Returns

a_ops [list of qobj] A list of annihilation operators for each mode in the composite quantum system described by dims.

enr_identity (dims, excitations)

Generate the identity operator for the excitation-number restricted state space defined by the *dims* and *excitations* arguments. See the docstring for enr_fock for a more detailed description of these arguments.

Parameters

dims [list] A list of the dimensions of each subsystem of a composite quantum system.

- excitations [integer] The maximum number of excitations that are to be included in the state space.
- state [list of integers] The state in the number basis representation.

Returns

op [Qobj] A Qobj instance that represent the identity operator in the exication-numberrestricted state space defined by *dims* and *excitations*.

jmat (j, *args)

Higher-order spin operators:

Parameters

j [float] Spin of operator

args [str] Which operator to return 'x','y','z','+','-'. If no args given, then output is ['x','y','z']

Returns

jmat [qobj / ndarray] qobj for requested spin operator(s).

Notes

If no 'args' input, then returns array of ['x','y','z'] operators.

Examples

```
>>> jmat(1)
[Quantum object: dims = [[3], [3]], shape = [3, 3], type = oper, isHerm = True
Qobj data =
[[ 0.
             0.70710678 0.
                                   1
                         0.70710678]
[ 0.70710678 0.
             0.70710678 0.
[ 0.
                                  11
Quantum object: dims = [[3], [3]], shape = [3, 3], type = oper, isHerm = True
Qobj data =
                 0.-0.70710678j 0.+0.j
[[ 0.+0.j
                                              1
                                 0.-0.70710678j]
[ 0.+0.70710678j 0.+0.j
                 0.+0.70710678j 0.+0.j
[ 0.+0.j
                                              ]]
Quantum object: dims = [[3], [3]], shape = [3, 3], type = oper, isHerm = True
Qobj data =
[[ 1. 0. 0.]
[ 0. 0. 0.]
[0. 0. -1.]]]
```

num(N, offset=0)

Quantum object for number operator.

Parameters

N [int] The dimension of the Hilbert space.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

Returns

oper: qobj Qobj for number operator.

Examples

```
>>> num(4)
Quantum object: dims = [[4], [4]], shape = [4, 4], type = oper, isHerm = True
Qobj data =
[[0 0 0 0]
[0 1 0 0]
[0 0 2 0]
[0 0 2 0]
[0 0 0 3]]
```

qeye(N)

Identity operator

Parameters

N [int or list of ints] Dimension of Hilbert space. If provided as a list of ints, then the dimension is the product over this list, but the dims property of the new Qobj are set to this list.

Returns

oper [qobj] Identity operator Qobj.

Examples

```
>>> qeye(3)
Quantum object: dims = [[3], [3]], shape = [3, 3], type = oper, isHerm = True
Qobj data =
[[ 1. 0. 0.]
```

(continues on next page)

(continued from previous page)

[0. 1	1. 0.]
[0. (0. 1.]]

identity(N)

Identity operator. Alternative name to qeye.

Parameters

N [int or list of ints] Dimension of Hilbert space. If provided as a list of ints, then the dimension is the product over this list, but the dims property of the new Qobj are set to this list.

Returns

oper [qobj] Identity operator Qobj.

momentum(N, offset=0)

Momentum operator p=-1j/sqrt(2)*(a-a.dag())

Parameters

N [int] Number of Fock states in Hilbert space.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

Returns

oper [qobj] Momentum operator as Qobj.

phase (N, phi0=0)

Single-mode Pegg-Barnett phase operator.

Parameters

N [int] Number of basis states in Hilbert space.

phi0 [float] Reference phase.

Returns

oper [qobj] Phase operator with respect to reference phase.

Notes

The Pegg-Barnett phase operator is Hermitian on a truncated Hilbert space.

position (N, offset=0)

Position operator x=1/sqrt(2)*(a+a.dag())

Parameters

N [int] Number of Fock states in Hilbert space.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

Returns

oper [qobj] Position operator as Qobj.

qdiags (*diagonals*, *offsets*, *dims=None*, *shape=None*) Constructs an operator from an array of diagonals.

Parameters

diagonals [sequence of array_like] Array of elements to place along the selected diagonals.

offsets [sequence of ints]

Sequence for diagonals to be set:

- k=0 main diagonal
- k>0 kth upper diagonal
- k<0 kth lower diagonal
- dims [list, optional] Dimensions for operator
- **shape** [list, tuple, optional] Shape of operator. If omitted, a square operator large enough to contain the diagonals is generated.

See also:

scipy.sparse.diags for usage information.

Notes

This function requires SciPy 0.11+.

Examples

```
>>> qdiags(sqrt(range(1, 4)), 1)
Quantum object: dims = [[4], [4]], shape = [4, 4], type = oper, isherm = False
Qobj data =
.0 ]]
               1.
                           0.
                                        0.
                                                  ]
                           1.41421356 0.
 ΓΟ.
               0.
                                                  1
                                       1.73205081]
 [ 0.
               Ο.
                           0.
               Ο.
[ 0.
                           0.
                                        0.
                                                  11
```

qutrit_ops()

Operators for a three level system (qutrit).

Returns

opers: array array of qutrit operators.

qzero(N)

Zero operator

Parameters

N [int or list of ints] Dimension of Hilbert space. If provided as a list of ints, then the dimension is the product over this list, but the dims property of the new Qobj are set to this list.

Returns

qzero [qobj] Zero operator Qobj.

sigmam()

Annihilation operator for Pauli spins.

Examples

```
>>> sigmam()
Quantum object: dims = [[2], [2]], shape = [2, 2], type = oper, isHerm = False
Qobj data =
[[ 0. 0.]
[ 1. 0.]]
```

sigmap()

Creation operator for Pauli spins.

Examples

```
>>> sigmap()
Quantum object: dims = [[2], [2]], shape = [2, 2], type = oper, isHerm = False
Qobj data =
[[ 0. 1.]
[ 0. 0.]]
```

sigmax()

Pauli spin 1/2 sigma-x operator

Examples

```
>>> sigmax()
Quantum object: dims = [[2], [2]], shape = [2, 2], type = oper, isHerm = False
Qobj data =
[[ 0. 1.]
[ 1. 0.]]
```

sigmay()

Pauli spin 1/2 sigma-y operator.

Examples

```
>>> sigmay()
Quantum object: dims = [[2], [2]], shape = [2, 2], type = oper, isHerm = True
Qobj data =
[[ 0.+0.j 0.-1.j]
[ 0.+1.j 0.+0.j]]
```

sigmaz()

Pauli spin 1/2 sigma-z operator.

Examples

```
>>> sigmaz()
Quantum object: dims = [[2], [2]], shape = [2, 2], type = oper, isHerm = True
Qobj data =
[[ 1. 0.]
[ 0. -1.]]
```

$spin_Jx(j)$

Spin-j x operator

Parameters

j [float] Spin of operator

Returns

op [Qobj] qobj representation of the operator.

 $spin_Jy(j)$

Spin-j y operator

Parameters

j [float] Spin of operator

Returns

op [Qobj] qobj representation of the operator.

$spin_Jz(j)$

Spin-j z operator

Parameters

j [float] Spin of operator

Returns

op [Qobj] qobj representation of the operator.

$spin_Jm(j)$

Spin-j annihilation operator

Parameters

j [float] Spin of operator

Returns

op [Qobj] qobj representation of the operator.

$spin_Jp(j)$

Spin-j creation operator

Parameters

j [float] Spin of operator

Returns

op [Qobj] qobj representation of the operator.

squeeze(N, z, offset=0)

Single-mode Squeezing operator.

Parameters

N [int] Dimension of hilbert space.

z [float/complex] Squeezing parameter.

offset [int (default 0)] The lowest number state that is included in the finite number state representation of the operator.

Returns

oper [qutip.qobj.Qobj] Squeezing operator.

Examples

```
>>> squeeze(4, 0.25)
Quantum object: dims = [[4], [4]], shape = [4, 4], type = oper, isHerm = False
Qobj data =
[[ 0.98441565+0.j 0.00000000+0.j 0.17585742+0.j 0.00000000+0.j]
[ 0.00000000+0.j 0.95349007+0.j 0.00000000+0.j 0.30142443+0.j]
[-0.17585742+0.j 0.00000000+0.j 0.98441565+0.j 0.00000000+0.j]
[ 0.00000000+0.j -0.30142443+0.j 0.0000000+0.j 0.95349007+0.j]]
```

```
squeezing (a1, a2, z)
```

Generalized squeezing operator.

$$S(z) = \exp\left(\frac{1}{2}\left(z^*a_1a_2 - za_1^{\dagger}a_2^{\dagger}\right)\right)$$

Parameters

al [qutip.qobj.Qobj] Operator 1.

a2 [qutip.qobj.Qobj] Operator 2.

z [float/complex] Squeezing parameter.

Returns

oper [qutip.qobj.Qobj] Squeezing operator.

tunneling (N, m=1)

Tunneling operator with elements of the form $\sum |N| > \langle N + m| + |N + m| > \langle N|$.

Parameters

N [int] Number of basis states in Hilbert space.

m [int (default = 1)] Number of excitations in tunneling event.

Returns

T [Qobj] Tunneling operator.

Notes

New in version 3.2.

Random Operators and States

This module is a collection of random state and operator generators. The sparsity of the ouput Qobj's is controlled by varing the *density* parameter.

rand_dm (N, density=0.75, pure=False, dims=None, seed=None)

Creates a random NxN density matrix.

Parameters

- N [int, ndarray, list] If int, then shape of output operator. If list/ndarray then eigenvalues of generated density matrix.
- **density** [float] Density between [0,1] of output density matrix.
- **dims** [list] Dimensions of quantum object. Used for specifying tensor structure. Default is dims=[[N],[N]].

Returns

oper [qobj] NxN density matrix quantum operator.

Notes

For small density matrices., choosing a low density will result in an error as no diagonal elements will be generated such that $Tr(\rho) = 1$.

rand_dm_ginibre (N=2, rank=None, dims=None, seed=None)

Returns a Ginibre random density operator of dimension dim and rank rank by using the algorithm of [BCSZ08]. If rank is *None*, a full-rank (Hilbert-Schmidt ensemble) random density operator will be returned.

Parameters

N [int] Dimension of the density operator to be returned.

- **dims** [list] Dimensions of quantum object. Used for specifying tensor structure. Default is dims=[[N],[N]].
- **rank** [int or None] Rank of the sampled density operator. If None, a full-rank density operator is generated.

Returns

rho [Qobj] An N × N density operator sampled from the Ginibre or Hilbert-Schmidt distribution.

rand_dm_hs (N=2, dims=None, seed=None)

Returns a Hilbert-Schmidt random density operator of dimension dim and rank rank by using the algorithm of [BCSZ08].

Parameters

N [int] Dimension of the density operator to be returned.

dims [list] Dimensions of quantum object. Used for specifying tensor structure. Default is dims=[[N],[N]].

Returns

rho [Qobj] A dim × dim density operator sampled from the Ginibre or Hilbert-Schmidt distribution.

rand_herm (*N*, *density=0.75*, *dims=None*, *pos_def=False*, *seed=None*) Creates a random NxN sparse Hermitian quantum object.

If 'N' is an integer, uses $H = 0.5 * (X + X^+)$ where X is a randomly generated quantum operator with a given *density*. Else uses complex Jacobi rotations when 'N' is given by an array.

Parameters

N [int, list/ndarray] If int, then shape of output operator. If list/ndarray then eigenvalues of generated operator.

density [float] Density between [0,1] of output Hermitian operator.

dims [list] Dimensions of quantum object. Used for specifying tensor structure. Default is dims=[[N],[N]].

pos_def [bool (default=False)] Return a positive semi-definite matrix (by diagonal dominance).

Returns

oper [qobj] NxN Hermitian quantum operator.

rand_ket (N, density=1, dims=None, seed=None)
Creates a random Nx1 sparse ket vector.

Parameters

N [int] Number of rows for output quantum operator.

density [float] Density between [0,1] of output ket state.

dims [list] Left-dimensions of quantum object. Used for specifying tensor structure. Default is dims=[[N]].

Returns

oper [qobj] Nx1 ket state quantum operator.

```
rand_ket_haar(N=2, dims=None, seed=None)
```

Returns a Haar random pure state of dimension dim by applying a Haar random unitary to a fixed pure state.

Parameters

N [int] Dimension of the state vector to be returned.

dims [list of ints, or None] Left-dimensions of the resultant quantum object. If None, [N] is used.

Returns

psi [Qobj] A random state vector drawn from the Haar measure.

rand_unitary (N, density=0.75, dims=None, seed=None)

Creates a random NxN sparse unitary quantum object.

Uses $\exp(-iH)$ where H is a randomly generated Hermitian operator.

Parameters

N [int] Shape of output quantum operator.

density [float] Density between [0,1] of output Unitary operator.

dims [list] Dimensions of quantum object. Used for specifying tensor structure. Default is dims=[[N],[N]].

Returns

oper [qobj] NxN Unitary quantum operator.

rand_unitary_haar(N=2, dims=None, seed=None)

Returns a Haar random unitary matrix of dimension dim, using the algorithm of [Mez07].

Parameters

N [int] Dimension of the unitary to be returned.

dims [list of lists of int, or None] Dimensions of quantum object. Used for specifying tensor structure. Default is dims=[[N],[N]].

Returns

U [Qobj] Unitary of dims [[dim], [dim]] drawn from the Haar measure.

rand_super(N=5, dims=None, seed=None)

Returns a randomly drawn superoperator acting on operators acting on N dimensions.

Parameters

N [int] Square root of the dimension of the superoperator to be returned.

dims [list] Dimensions of quantum object. Used for specifying tensor structure. Default is dims=[[[N],[N]], [[N],[N]]].

rand_super_bcsz (N=2, enforce_tp=True, rank=None, dims=None, seed=None)

Returns a random superoperator drawn from the Bruzda et al ensemble for CPTP maps [BCSZ08]. Note that due to finite numerical precision, for ranks less than full-rank, zero eigenvalues may become slightly negative, such that the returned operator is not actually completely positive.

Parameters

N [int] Square root of the dimension of the superoperator to be returned.


- **enforce_tp** [bool] If True, the trace-preserving condition of [BCSZ08] is enforced; otherwise only complete positivity is enforced.
- **rank** [int or None] Rank of the sampled superoperator. If None, a full-rank superoperator is generated.
- **dims** [list] Dimensions of quantum object. Used for specifying tensor structure. Default is dims=[[[N],[N]], [[N],[N]]].

Returns

rho [Qobj] A superoperator acting on vectorized dim × dim density operators, sampled from the BCSZ distribution.

Three-Level Atoms

This module provides functions that are useful for simulating the three level atom with QuTiP. A three level atom (qutrit) has three states, which are linked by dipole transitions so that 1 <-> 2 <-> 3. Depending on there relative energies they are in the ladder, lambda or vee configuration. The structure of the relevant operators is the same for any of the three configurations:



References

The naming of qutip operators follows the convention in [R0be8dcf25d86-1].

Notes

Contributed by Markus Baden, Oct. 07, 2011

three_level_basis()

Basis states for a three level atom.

Returns

states [array] array of three level atom basis vectors.

three_level_ops()

Operators for a three level system (qutrit)

Returns

ops [array] array of three level operators.

Superoperators and Liouvillians

operator_to_vector(op)

Create a vector representation of a quantum operator given the matrix representation.

vector_to_operator(op)

Create a matrix representation given a quantum operator in vector form.

liouvillian (*H*, *c_ops=[]*, *data_only=False*, *chi=None*)

Assembles the Liouvillian superoperator from a Hamiltonian and a list of collapse operators. Like liouvillian, but with an experimental implementation which avoids creating extra Qobj instances, which can be advantageous for large systems.

Parameters

H [Qobj or QobjEvo] System Hamiltonian.

c_ops [array_like of Qobj or QobjEvo] A list or array of collapse operators.

Returns

L [Qobj or QobjEvo] Liouvillian superoperator.

spost(A)

Superoperator formed from post-multiplication by operator A

Parameters

A [Qobj or QobjEvo] Quantum operator for post multiplication.

Returns

super [Qobj or QobjEvo] Superoperator formed from input qauntum object.

spre(A)

Superoperator formed from pre-multiplication by operator A.

Parameters

A [Qobj or QobjEvo] Quantum operator for pre-multiplication.

Returns

super : Qobj or QobjEvo Superoperator formed from input quantum object.

sprepost(A, B)

Superoperator formed from pre-multiplication by operator A and post- multiplication of operator B.

Parameters

A [Qobj or QobjEvo] Quantum operator for pre-multiplication.

B [Qobj or QobjEvo] Quantum operator for post-multiplication.

Returns

super [Qobj or QobjEvo] Superoperator formed from input quantum objects.

lindblad_dissipator (*a*, *b*=None, data_only=False, chi=None)

Lindblad dissipator (generalized) for a single pair of collapse operators (a, b), or for a single collapse operator (a) when b is not specified:

$$\mathcal{D}[a,b]
ho = a
ho b^{\dagger} - rac{1}{2}a^{\dagger}b
ho - rac{1}{2}
ho a^{\dagger}b$$

Parameters

- a [Qobj or QobjEvo] Left part of collapse operator.
- **b** [Qobj or QobjEvo (optional)] Right part of collapse operator. If not specified, b defaults to a.

Returns

D [qobj, QobjEvo] Lindblad dissipator superoperator.

Superoperator Representations

This module implements transformations between superoperator representations, including supermatrix, Kraus, Choi and Chi (process) matrix formalisms.

$to_choi(q_oper)$

Converts a Qobj representing a quantum map to the Choi representation, such that the trace of the returned operator is equal to the dimension of the system.

Parameters

q_oper [Qobj] Superoperator to be converted to Choi representation. If q_oper is
type="oper", then it is taken to act by conjugation, such that to_choi(A) ==
to_choi(sprepost(A, A.dag())).

Returns

choi [Qobj] A quantum object representing the same map as q_oper, such that choi.
 superrep == "choi".

Raises

TypeError: if the given quantum object is not a map, or cannot be converted to Choi representation.

to_super(q_oper)

Converts a Qobj representing a quantum map to the supermatrix (Liouville) representation.

Parameters

q_oper [Qobj] Superoperator to be converted to supermatrix representation. If q_oper is type="oper", then it is taken to act by conjugation, such that to_super(A) == sprepost(A, A.dag()).

Returns

superop [Qobj] A quantum object representing the same map as q_oper, such that superop.superrep == "super".

Raises

TypeError If the given quantum object is not a map, or cannot be converted to supermatrix representation.

$\texttt{to_kraus}\left(q_oper\right)$

Converts a Qobj representing a quantum map to a list of quantum objects, each representing an operator in the Kraus decomposition of the given map.

Parameters

q_oper [Qobj] Superoperator to be converted to Kraus representation. If q_oper is
type="oper", then it is taken to act by conjugation, such that to_kraus(A) ==
to_kraus(sprepost(A, A.dag())) == [A].

Returns

kraus_ops [list of Qobj] A list of quantum objects, each representing a Kraus operator in the decomposition of q_oper.

Raises

TypeError: if the given quantum object is not a map, or cannot be decomposed into Kraus operators.

4.2.2 Functions acting on states and operators

Expectation Values

expect (oper, state)

Calculates the expectation value for operator(s) and state(s).

Parameters

oper [qobj/array-like] A single or a *list* or operators for expectation value.

state [qobj/array-like] A single or a *list* of quantum states or density matrices.

Returns

expt [float/complex/array-like] Expectation value. real if *oper* is Hermitian, complex otherwise. A (nested) array of expectaction values of state or operator are arrays.

Examples

```
>>> expect(num(4), basis(4, 3))
3
```

variance(oper, state)

Variance of an operator for the given state vector or density matrix.

Parameters

oper [qobj] Operator for expectation value.

state [qobj/list] A single or *list* of quantum states or density matrices..

Returns

var [float] Variance of operator 'oper' for given state.

Tensor

Module for the creation of composite quantum objects via the tensor product.

tensor(*args)

Calculates the tensor product of input operators.

Parameters

args [array_like] list or array of quantum objects for tensor product.

Returns

obj [qobj] A composite quantum object.

Examples

super_tensor(*args)

Calculates the tensor product of input superoperators, by tensoring together the underlying Hilbert spaces on which each vectorized operator acts.

Parameters

args [array_like] list or array of quantum objects with type="super".

Returns

obj [qobj] A composite quantum object.

composite (*args)

Given two or more operators, kets or bras, returns the Qobj corresponding to a composite system over each argument. For ordinary operators and vectors, this is the tensor product, while for superoperators and vectorized operators, this is the column-reshuffled tensor product.

If a mix of Qobjs supported on Hilbert and Liouville spaces are passed in, the former are promoted. Ordinary operators are assumed to be unitaries, and are promoted using to_super, while kets and bras are promoted by taking their projectors and using operator_to_vector(ket2dm(arg)).

tensor_contract (qobj, *pairs)

Contracts a qobj along one or more index pairs. Note that this uses dense representations and thus should *not* be used for very large Qobjs.

Parameters

pairs [tuple] One or more tuples (i, j) indicating that the i and j dimensions of the original qobj should be contracted.

Returns

cqobj [Qobj] The original Qobj with all named index pairs contracted away.

Partial Transpose

partial_transpose (rho, mask, method='dense')

Return the partial transpose of a Qobj instance *rho*, where *mask* is an array/list with length that equals the number of components of *rho* (that is, the length of *rho.dims[0]*), and the values in *mask* indicates whether or not the corresponding subsystem is to be transposed. The elements in *mask* can be boolean or integers 0 or 1, where *True*/1 indicates that the corresponding subsystem should be transposed.

Parameters

rho [qutip.qobj] A density matrix.

mask [list / array] A mask that selects which subsystems should be transposed.

method [str] choice of method, *dense* or *sparse*. The default method is *dense*. The *sparse* implementation can be faster for large and sparse systems (hundreds of quantum states).

Returns

rho_pr: qutip.qobj A density matrix with the selected subsystems transposed.

Entropy Functions

concurrence (rho)

Calculate the concurrence entanglement measure for a two-qubit state.

Parameters

state [qobj] Ket, bra, or density matrix for a two-qubit state.

Returns

concur [float] Concurrence

References

[1]

entropy_conditional (rho, selB, base=2.718281828459045, sparse=False)

Calculates the conditional entropy S(A|B) = S(A, B) - S(B) of a selected density matrix component.

Parameters

rho [qobj] Density matrix of composite object

selB [int/list] Selected components for density matrix B

base [{e,2}] Base of logarithm.

sparse [{False,True}] Use sparse eigensolver.

Returns

ent_cond [float] Value of conditional entropy

entropy_linear(rho)

Linear entropy of a density matrix.

Parameters

rho [qobj] sensity matrix or ket/bra vector.

Returns

entropy [float] Linear entropy of rho.

Examples

```
>>> rho=0.5*fock_dm(2,0)+0.5*fock_dm(2,1)
>>> entropy_linear(rho)
0.5
```

entropy_mutual (rho, selA, selB, base=2.718281828459045, sparse=False)

Calculates the mutual information S(A:B) between selection components of a system density matrix.

Parameters

rho [qobj] Density matrix for composite quantum systems

selA [int/list] int or list of first selected density matrix components.

selB [int/list] int or list of second selected density matrix components.

base [{e,2}] Base of logarithm.

sparse [{False,True}] Use sparse eigensolver.

Returns

ent_mut [float] Mutual information between selected components.

entropy_vn (*rho*, *base*=2.718281828459045, *sparse*=False) Von-Neumann entropy of density matrix

Parameters

rho [qobj] Density matrix.

base [{e,2}] Base of logarithm.

sparse [{False,True}] Use sparse eigensolver.

Returns

entropy [float] Von-Neumann entropy of rho.

Examples

```
>>> rho=0.5*fock_dm(2,0)+0.5*fock_dm(2,1)
>>> entropy_vn(rho,2)
1.0
```

Density Matrix Metrics

This module contains a collection of functions for calculating metrics (distance measures) between states and operators.

fidelity (A, B)

Calculates the fidelity (pseudo-metric) between two density matrices. See: Nielsen & Chuang, "Quantum Computation and Quantum Information"

Parameters

A [qobj] Density matrix or state vector.

B [qobj] Density matrix or state vector with same dimensions as A.

Returns

fid [float] Fidelity pseudo-metric between A and B.

Examples

```
>>> x = fock_dm(5,3)
>>> y = coherent_dm(5,1)
>>> fidelity(x,y)
0.24104350624628332
```

tracedist (A, B, sparse=False, tol=0)

Calculates the trace distance between two density matrices.. See: Nielsen & Chuang, "Quantum Computation and Quantum Information"

Parameters

A [qobj] Density matrix or state vector.

B [qobj] Density matrix or state vector with same dimensions as A.

tol [float] Tolerance used by sparse eigensolver, if used. (0=Machine precision)

sparse [{False, True}] Use sparse eigensolver.

Returns

tracedist [float] Trace distance between A and B.

Examples

```
>>> x=fock_dm(5,3)
>>> y=coherent_dm(5,1)
>>> tracedist(x,y)
0.9705143161472971
```

$bures_dist(A, B)$

Returns the Bures distance between two density matrices A & B.

The Bures distance ranges from 0, for states with unit fidelity, to sqrt(2).

Parameters

A [qobj] Density matrix or state vector.

B [qobj] Density matrix or state vector with same dimensions as A.

Returns

dist [float] Bures distance between density matrices.

$bures_angle(A, B)$

Returns the Bures Angle between two density matrices A & B.

The Bures angle ranges from 0, for states with unit fidelity, to pi/2.

Parameters

A [qobj] Density matrix or state vector.

B [qobj] Density matrix or state vector with same dimensions as A.

Returns

angle [float] Bures angle between density matrices.

$hilbert_dist(A, B)$

Returns the Hilbert-Schmidt distance between two density matrices A & B.

Parameters

A [qobj] Density matrix or state vector.

B [qobj] Density matrix or state vector with same dimensions as A.

Returns

dist [float] Hilbert-Schmidt distance between density matrices.

Notes

See V. Vedral and M. B. Plenio, Phys. Rev. A 57, 1619 (1998).

average_gate_fidelity (oper, target=None)

Given a Qobj representing the supermatrix form of a map, returns the average gate fidelity (pseudo-metric) of that map.

Parameters

A [Qobj] Quantum object representing a superoperator.

target [Qobj] Quantum object representing the target unitary; the inverse is applied before evaluating the fidelity.

Returns

fid [float] Fidelity pseudo-metric between A and the identity superoperator, or between A and the target superunitary.

process_fidelity(U1, U2, normalize=True)

Calculate the process fidelity given two process operators.

Continuous Variables

This module contains a collection functions for calculating continuous variable quantities from fock-basis representation of the state of multi-mode fields.

correlation_matrix(basis, rho=None)

Given a basis set of operators $\{a\}_n$, calculate the correlation matrix:

$$C_{mn} = \langle a_m a_n \rangle$$

Parameters

basis [list] List of operators that defines the basis for the correlation matrix.

rho [Qobj] Density matrix for which to calculate the correlation matrix. If *rho* is *None*, then a matrix of correlation matrix operators is returned instead of expectation values of those operators.

Returns

corr_mat [ndarray] A 2-dimensional array of correlation values or operators.

covariance_matrix (*basis*, *rho*, *symmetrized=True*)

Given a basis set of operators $\{a\}_n$, calculate the covariance matrix:

$$V_{mn} = \frac{1}{2} \langle a_m a_n + a_n a_m \rangle - \langle a_m \rangle \langle a_n \rangle$$

or, if of the optional argument symmetrized=False,

$$V_{mn} = \langle a_m a_n \rangle - \langle a_m \rangle \langle a_n \rangle$$

Parameters

basis [list] List of operators that defines the basis for the covariance matrix.

rho [Qobj] Density matrix for which to calculate the covariance matrix.

symmetrized [bool {True, False}] Flag indicating whether the symmetrized (default) or non-symmetrized correlation matrix is to be calculated.

Returns

corr_mat [ndarray] A 2-dimensional array of covariance values.

correlation_matrix_field(a1, a2, rho=None)

Calculates the correlation matrix for given field operators a_1 and a_2 . If a density matrix is given the expectation values are calculated, otherwise a matrix with operators is returned.

Parameters

a1 [Qobj] Field operator for mode 1.

a2 [Qobj] Field operator for mode 2.

rho [Qobj] Density matrix for which to calculate the covariance matrix.

Returns

cov_mat [ndarray] Array of complex numbers or Qobj's A 2-dimensional *array* of covariance values, or, if rho=0, a matrix of operators.

correlation_matrix_quadrature(*a1*, *a2*, *rho=None*)

Calculate the quadrature correlation matrix with given field operators a_1 and a_2 . If a density matrix is given the expectation values are calculated, otherwise a matrix with operators is returned.

Parameters

a1 [Qobj] Field operator for mode 1.

a2 [Qobj] Field operator for mode 2.

rho [Qobj] Density matrix for which to calculate the covariance matrix.

Returns

corr_mat [ndarray] Array of complex numbers or Qobj's A 2-dimensional *array* of covariance values for the field quadratures, or, if rho=0, a matrix of operators.

wigner_covariance_matrix (a1=None, a2=None, R=None, rho=None)

Calculates the Wigner covariance matrix $V_{ij} = \frac{1}{2}(R_{ij} + R_{ji})$, given the quadrature correlation matrix $R_{ij} = \langle R_i R_j \rangle - \langle R_i \rangle \langle R_j \rangle$, where $R = (q_1, p_1, q_2, p_2)^T$ is the vector with quadrature operators for the two modes.

Alternatively, if R = None, and if annihilation operators a1 and a2 for the two modes are supplied instead, the quadrature correlation matrix is constructed from the annihilation operators before then the covariance matrix is calculated.

Parameters

a1 [Qobj] Field operator for mode 1.

a2 [Qobj] Field operator for mode 2.

R [ndarray] The quadrature correlation matrix.

rho [Qobj] Density matrix for which to calculate the covariance matrix.

Returns

cov_mat [ndarray] A 2-dimensional array of covariance values.

$logarithmic_negativity(V)$

Calculates the logarithmic negativity given a symmetrized covariance matrix, see qutip. continous_variables.covariance_matrix. Note that the two-mode field state that is described by *V* must be Gaussian for this function to applicable.

Parameters

V [2d array] The covariance matrix.

Returns

N [float] The logarithmic negativity for the two-mode Gaussian state that is described by the the Wigner covariance matrix V.

4.2.3 Dynamics and Time-Evolution

Schrödinger Equation

This module provides solvers for the unitary Schrodinger equation.

Schrodinger equation evolution of a state vector or unitary matrix for a given Hamiltonian.

Evolve the state vector (psi0) using a given Hamiltonian (H), by integrating the set of ordinary differential equations that define the system. Alternatively evolve a unitary matrix in solving the Schrödinger operator equation.

The output is either the state vector or unitary matrix at arbitrary points in time (*tlist*), or the expectation values of the supplied operators (e_ops). If e_ops is a callback function, it is invoked for each time in *tlist* with time and the state as arguments, and the function does not use any return values. e_ops cannot be used in conjunction with solving the Schrödinger operator equation

Parameters

- **H** [qutip.qobj,qutip.qobjevo, *list*, *callable*] system Hamiltonian as a Qobj, list of Qobj and coefficient, QobjEvo, or a callback function for time-dependent Hamiltonians. list format and options can be found in QobjEvo's description.
- **psi0** [qutip.qobj] initial state vector (ket) or initial unitary operator psi0 = U
- **tlist** [*list / array*] list of times for *t*.
- e_ops [list of qutip.qobj / callback function] single operator or list of operators for which to evaluate expectation values. For list operator evolution, the overlapse is computed:

tr(e_ops[i].dag()*op(t))

- args [dictionary] dictionary of parameters for time-dependent Hamiltonians
- options [qutip.Qdeoptions] with options for the ODE solver.
- **progress_bar** [BaseProgressBar] Optional instance of BaseProgressBar, or a subclass thereof, for showing the progress of the simulation.

Returns

output: qutip.solver An instance of the class qutip.solver, which contains either an *array* of expectation values for the times specified by *tlist*, or an *array* or state vectors corresponding to the times in *tlist* [if *e_ops* is an empty list], or nothing if a callback function was given inplace of operators for which to calculate the expectation values.

Master Equation

This module provides solvers for the Lindblad master equation and von Neumann equation.

mesolve (H, rho0, tlist, c_ops=[], e_ops=[], args={}, options=<qutip.solver.Options object
 at 0x2acc48230860>, progress_bar=<qutip.ui.progressbar.BaseProgressBar object at
 0x2acc45b78a90>, _safe_mode=True)

Master equation evolution of a density matrix for a given Hamiltonian and set of collapse operators, or a Liouvillian.

Evolve the state vector or density matrix (*rho0*) using a given Hamiltonian (*H*) and an [optional] set of collapse operators (c_{ops}), by integrating the set of ordinary differential equations that define the system. In the absence of collapse operators the system is evolved according to the unitary evolution of the Hamiltonian.

The output is either the state vector at arbitrary points in time (*tlist*), or the expectation values of the supplied operators (e_ops). If e_ops is a callback function, it is invoked for each time in *tlist* with time and the state as arguments, and the function does not use any return values.

If either H or the Qobj elements in c_{ops} are superoperators, they will be treated as direct contributions to the total system Liouvillian. This allows to solve master equations that are not on standard Lindblad form by passing a custom Liouvillian in place of either the H or c_{ops} elements.

Time-dependent operators

For time-dependent problems, H and c_{ops} can be callback functions that takes two arguments, time and *args*, and returns the Hamiltonian or Liouvillian for the system at that point in time (*callback format*).

Alternatively, H and c_{ops} can be a specified in a nested-list format where each element in the list is a list of length 2, containing an operator (qutip.qobj) at the first element and where the second element is either a string *(list string format)*, a callback function *(list callback format)* that evaluates to the time-dependent coefficient for the corresponding operator, or a NumPy array *(list array format)* which specifies the value of the coefficient to the corresponding operator for each value of t in tlist.

Examples

 $H = [[H0, 'sin(w^*t)'], [H1, 'sin(2^*w^*t)']]$

 $H = [[H0, f0_t], [H1, f1_t]]$

where f0_t and f1_t are python functions with signature f_t(t, args).

H = [[H0, np.sin(w*tlist)], [H1, np.sin(2*w*tlist)]]

In the *list string format* and *list callback format*, the string expression and the callback function must evaluate to a real or complex number (coefficient for the corresponding operator).

In all cases of time-dependent operators, *args* is a dictionary of parameters that is used when evaluating operators. It is passed to the callback functions as second argument.

Additional options

Additional options to mesolve can be set via the *options* argument, which should be an instance of *qutip.solver.Options*. Many ODE integration options can be set this way, and the *store_states* and *store_final_state* options can be used to store states even though expectation values are requested via the *e_ops* argument.

Note: If an element in the list-specification of the Hamiltonian or the list of collapse operators are in superoperator form it will be added to the total Liouvillian of the problem with out further transformation. This allows for using mesolve for solving master equations that are not on standard Lindblad form.

Note: On using callback function: mesolve transforms all qutip.qobj objects to sparse matrices before handing the problem to the integrator function. In order for your callback function to work correctly, pass all qutip.qobj objects that are used in constructing the Hamiltonian via args. mesolve will check for qutip.qobj in *args* and handle the conversion to sparse matrices. All other qutip.qobj objects that

are not passed via *args* will be passed on to the integrator in scipy which will raise an NotImplemented exception.

Parameters

- **H** [*qutip.Qobj*] System Hamiltonian, or a callback function for time-dependent Hamiltonians, or alternatively a system Liouvillian.
- **rho0** [qutip.Qobj] initial density matrix or state vector (ket).
- **tlist** [*list / array*] list of times for *t*.
- **c_ops** [list of *qutip.Qobj*] single collapse operator, or list of collapse operators, or a list of Liouvillian superoperators.
- **e_ops** [list of *qutip.Qobj* / callback function single] single operator or list of operators for which to evaluate expectation values.
- **args** [*dictionary*] dictionary of parameters for time-dependent Hamiltonians and collapse operators.
- options [qutip.Options] with options for the solver.
- **progress_bar** [BaseProgressBar] Optional instance of BaseProgressBar, or a subclass thereof, for showing the progress of the simulation.

Returns

result: qutip.Result An instance of the class **qutip.Result**, which contains either an *array result.expect* of expectation values for the times specified by *tlist*, or an *array result.states* of state vectors or density matrices corresponding to the times in *tlist* [if *e_ops* is an empty list], or nothing if a callback function was given in place of operators for which to calculate the expectation values.

Monte Carlo Evolution

Monte Carlo evolution of a state vector $|\psi\rangle$ for a given Hamiltonian and sets of collapse operators, and possibly, operators for calculating expectation values. Options for the underlying ODE solver are given by the Options class.

mcsolve supports time-dependent Hamiltonians and collapse operators using either Python functions of strings to represent time-dependent coefficients. Note that, the system Hamiltonian MUST have at least one constant term.

As an example of a time-dependent problem, consider a Hamiltonian with two terms H0 and H1, where H1 is time-dependent with coefficient sin(w*t), and collapse operators C0 and C1, where C1 is time-dependent with coefficient exp(-a*t). Here, w and a are constant arguments with values W and A.

Using the Python function time-dependent format requires two Python functions, one for each collapse coefficient. Therefore, this problem could be expressed as:

```
def H1_coeff(t,args):
    return sin(args['w']*t)

def C1_coeff(t,args):
    return exp(-args['a']*t)

H = [H0, [H1, H1_coeff]]

c_ops = [C0, [C1, C1_coeff]]
```

(continues on next page)

(continued from previous page)

args={'a': A, 'w': W}

or in String (Cython) format we could write:

H = [H0, [H1, 'sin(w*t)']]
c_ops = [C0, [C1, 'exp(-a*t)']]
args={'a': A, 'w': W}

Constant terms are preferably placed first in the Hamiltonian and collapse operator lists.

Parameters

H [qutip.Qobj, list] System Hamiltonian.

psi0 [qutip.Qobj] Initial state vector

tlist [array_like] Times at which results are recorded.

ntraj [int] Number of trajectories to run.

- **c_ops** [qutip.Qobj, list] single collapse operator or a list of collapse operators.
- **e_ops** [*qutip.Qobj*, list] single operator as Qobj or list or equivalent of Qobj operators for calculating expectation values.

args [dict] Arguments for time-dependent Hamiltonian and collapse operator terms.

options [Options] Instance of ODE solver options.

progress_bar: BaseProgressBar Optional instance of BaseProgressBar, or a subclass thereof, for showing the progress of the simulation. Set to None to disable the progress bar.

map_func: function A map function for managing the calls to the single-trajactory solver.

map_kwargs: dictionary Optional keyword arguments to the map_func function.

Returns

results [qutip.solver.Result] Object storing all results from the simulation.

Note: It is possible to reuse the random number seeds from a previous run of the mcsolver by passing the output Result object seeds via the Options class, i.e. Options(seeds=prev_result.seeds).

Exponential Series

essolve (*H*, *rho0*, *tlist*, *c_op_list*, *e_ops*)

Evolution of a state vector or density matrix (*rho0*) for a given Hamiltonian (*H*) and set of collapse operators (c_op_list), by expressing the ODE as an exponential series. The output is either the state vector at arbitrary points in time (*tlist*), or the expectation values of the supplied operators (e_ops).

Parameters

H [qobj/function_type] System Hamiltonian.

rho0 [qutip.qobj] Initial state density matrix.

tlist [list/array] list of times for t.

c_op_list [list of qutip.qobj] list of qutip.qobj collapse operators.

e_ops [list of qutip.qobj] list of qutip.qobj operators for which to evaluate expectation values.

Returns

expt_array [array] Expectation values of wavefunctions/density matrices for the times
 specified in tlist.

Note: This solver does not support time-dependent Hamiltonians. ..

ode2es (L, rho0)

Creates an exponential series that describes the time evolution for the initial density matrix (or state vector) *rho0*, given the Liouvillian (or Hamiltonian) *L*.

Parameters

L [qobj] Liouvillian of the system.

rho0 [qobj] Initial state vector or density matrix.

Returns

eseries [qutip.eseries] eseries represention of the system dynamics.

Bloch-Redfield Master Equation

bose=False)

Solves for the dynamics of a system using the Bloch-Redfield master equation, given an input Hamiltonian, Hermitian bath-coupling terms and their associated spectrum functions, as well as possible Lindblad collapse operators.

For time-independent systems, the Hamiltonian must be given as a Qobj, whereas the bath-coupling terms (a_ops), must be written as a nested list of operator - spectrum function pairs, where the frequency is specified by the w variable.

Example

 $a_{ops} = [[a+a.dag(), lambda w: 0.2*(w>=0)]]$

For time-dependent systems, the Hamiltonian, a_ops, and Lindblad collapse operators (c_ops), can be specified in the QuTiP string-based time-dependent format. For the a_op spectra, the frequency variable must be w, and the string cannot contain any other variables other than the possibility of having a time-dependence through the time variable t:

Example

```
a_{ops} = [[a+a.dag(), `0.2*exp(-t)*(w>=0)']]
```

It is also possible to use Cubic_Spline objects for time-dependence. In the case of a_ops, Cubic_Splines must be passed as a tuple:

Example

 $a_{ops} = [[a+a.dag(), (f(w), g(t)]]$

where f(w) and g(t) are strings or Cubic_spline objects for the bath spectrum and time-dependence, respectively.

Finally, if one has bath-coupling terms of the form $H = f(t)^*a + conj[f(t)]^*a.dag()$, then the correct input format is

Example

```
a_{ops} = [ [(a,a.dag()), (f(w), g1(t), g2(t))],... ]
```

where f(w) is the spectrum of the operators while g1(t) and g2(t) are the time-dependence of the operators *a* and *a.dag()*, respectively

Parameters

H [Qobj / list] System Hamiltonian given as a Qobj or nested list in string-based format.

psi0: Qobj Initial density matrix or state vector (ket).

tlist [array_like] List of times for evaluating evolution

- **a_ops** [list] Nested list of Hermitian system operators that couple to the bath degrees of freedom, along with their associated spectra.
- e_ops [list] List of operators for which to evaluate expectation values.
- c_ops [list] List of system collapse operators, or nested list in string-based format.
- args [dict] Placeholder for future implementation, kept for API consistency.
- **use_secular** [bool {True}] Use secular approximation when evaluating bath-coupling terms.
- **sec_cutoff** [float {0.1}] Cutoff for secular approximation.
- **tol** [float {qutip.setttings.atol}] Tolerance used for removing small values after basis transformation.
- **spectra_cb** [list] DEPRECIATED. Do not use.
- options [qutip.solver.Options] Options for the solver.
- **progress_bar** [BaseProgressBar] Optional instance of BaseProgressBar, or a subclass thereof, for showing the progress of the simulation.

Returns

result: *qutip.solver.Result* An instance of the class *qutip.solver.Result*, which contains either an array of expectation values, for operators given in e_ops, or a list of states for the times specified by *tlist*.

bloch_redfield_tensor()

Calculates the time-independent Bloch-Redfield tensor for a system given a set of operators and corresponding spectral functions that describes the system's coupling its environment.

Parameters

H [qutip.qobj]

System Hamiltonian.

- **a_ops** [list] Nested list of system operators that couple to the environment, and the corresponding bath spectra represented as Python functions.
- spectra_cb [list] Depreciated.
- c_ops [list] List of system collapse operators.
- **use_secular** [bool {True, False}] Flag that indicates if the secular approximation should be used.
- **sec_cutoff** [float {0.1}] Threshold for secular approximation.
- atol [float {qutip.settings.atol}] Threshold for removing small parameters.

Returns

R, kets: *qutip*. *Qobj*, list of *qutip*. *Qobj* R is the Bloch-Redfield tensor and kets is a list eigenstates of the Hamiltonian.

bloch_redfield_solve (R, ekets, rho0, tlist, e_ops=[], options=None, progress_bar=None)
Evolve the ODEs defined by Bloch-Redfield master equation. The Bloch-Redfield tensor can be calculated
by the function bloch_redfield_tensor.

Parameters

R [qutip.qobj] Bloch-Redfield tensor.

ekets [array of qutip.qobj] Array of kets that make up a basis tranformation for the eigenbasis.

rho0 [qutip.qobj] Initial density matrix.

- tlist [list / array] List of times for t.
- e_ops [list of qutip.qobj / callback function] List of operators for which to evaluate expectation values.

options [qutip.Qdeoptions] Options for the ODE solver.

Returns

output: qutip.solver An instance of the class **qutip.solver**, which contains either an *array* of expectation values for the times specified by *tlist*.

Floquet States and Floquet-Markov Master Equation

fmmesolve (H, rho0, tlist, c_ops=[], e_ops=[], spectra_cb=[], T=None, args={}, options=<qutip.solver.Options object at 0x2acc489df048>, floquet_basis=True, kmax=5, _safe_mode=True)

Solve the dynamics for the system using the Floquet-Markov master equation.

Note: This solver currently does not support multiple collapse operators.

Parameters

H [qutip.qobj] system Hamiltonian.

rho0/psi0 [qutip.qobj] initial density matrix or state vector (ket).

tlist [list / array] list of times for t.

- **c_ops** [list of qutip.qobj] list of collapse operators.
- e_ops [list of qutip.qobj / callback function] list of operators for which to evaluate expectation values.
- **spectra_cb** [list callback functions] List of callback functions that compute the noise power spectrum as a function of frequency for the collapse operators in *c_ops*.
- **T** [float] The period of the time-dependence of the hamiltonian. The default value 'None' indicates that the 'tlist' spans a single period of the driving.
- **args** [*dictionary*] dictionary of parameters for time-dependent Hamiltonians and collapse operators.

This dictionary should also contain an entry 'w_th', which is the temperature of the environment (if finite) in the energy/frequency units of the Hamiltonian. For example, if the Hamiltonian written in units of 2pi GHz, and the temperature is given in K, use the following conversion

```
>>> temperature = 25e-3 # unit K
>>> h = 6.626e-34
>>> kB = 1.38e-23
>>> args['w_th'] = temperature * (kB / h) * 2 * pi * 1e-9
```

options [qutip.solver] options for the ODE solver.

k_max [int] The truncation of the number of sidebands (default 5).

Returns

output [qutip.solver] An instance of the class qutip.solver, which contains either an *array* of expectation values for the times specified by *tlist*.

floquet_modes (H, T, args=None, sort=False, U=None)

Calculate the initial Floquet modes Phi_alpha(0) for a driven system with period T.

Returns a list of qutip.qobj instances representing the Floquet modes and a list of corresponding quasienergies, sorted by increasing quasienergy in the interval [-pi/T, pi/T]. The optional parameter *sort* decides if the output is to be sorted in increasing quasienergies or not.

Parameters

H [qutip.qobj] system Hamiltonian, time-dependent with period T

args [dictionary] dictionary with variables required to evaluate H

- **T** [float] The period of the time-dependence of the hamiltonian. The default value 'None' indicates that the 'tlist' spans a single period of the driving.
- U [qutip.qobj] The propagator for the time-dependent Hamiltonian with period *T*. If U is *None* (default), it will be calculated from the Hamiltonian *H* using *qutip*. propagator.propagator.

Returns

output [list of kets, list of quasi energies] Two lists: the Floquet modes as kets and the quasi energies.

floquet_modes_t (f_modes_0, f_energies, t, H, T, args=None)

Calculate the Floquet modes at times tlist Phi_alpha(tlist) propagting the initial Floquet modes Phi_alpha(0)

Parameters

f_modes_0 [list of qutip.qobj (kets)] Floquet modes at t

f_energies [list] Floquet energies.

t [float] The time at which to evaluate the floquet modes.

H [qutip.qobj] system Hamiltonian, time-dependent with period T

args [dictionary] dictionary with variables required to evaluate H

T [float] The period of the time-dependence of the hamiltonian.

Returns

output [list of kets] The Floquet modes as kets at time t

floquet_modes_table (f_modes_0, f_energies, tlist, H, T, args=None)

Pre-calculate the Floquet modes for a range of times spanning the floquet period. Can later be used as a table to look up the floquet modes for any time.

Parameters

f_modes_0 [list of qutip.qobj (kets)] Floquet modes at t

f_energies [list] Floquet energies.

tlist [array] The list of times at which to evaluate the floquet modes.

H [qutip.qobj] system Hamiltonian, time-dependent with period T

T [float] The period of the time-dependence of the hamiltonian.

args [dictionary] dictionary with variables required to evaluate H

Returns

output [nested list] A nested list of Floquet modes as kets for each time in tlist

floquet_modes_t_lookup (f_modes_table_t, t, T)

Lookup the floquet mode at time t in the pre-calculated table of floquet modes in the first period of the time-dependence.

Parameters

f_modes_table_t [nested list of qutip.qobj (kets)] A lookup-table of Floquet modes at times precalculated by qutip.floquet.floquet_modes_table.

t [float] The time for which to evaluate the Floquet modes.

T [float] The period of the time-dependence of the hamiltonian.

Returns

output [nested list] A list of Floquet modes as kets for the time that most closely matching the time *t* in the supplied table of Floquet modes.

floquet_states (f_modes_t, f_energies, t)

Evaluate the floquet states at time t given the Floquet modes at that time.

Parameters

f_modes_t [list of qutip.qobj (kets)] A list of Floquet modes for time t.

f_energies [array] The Floquet energies.

t [float] The time for which to evaluate the Floquet states.

Returns

output [list] A list of Floquet states for the time t.

floquet_states_t (f_modes_0, f_energies, t, H, T, args=None)

Evaluate the floquet states at time t given the initial Floquet modes.

Parameters

f_modes_t [list of qutip.qobj (kets)] A list of initial Floquet modes (for time t = 0).

f_energies [array] The Floquet energies.

t [float] The time for which to evaluate the Floquet states.

H [qutip.qobj] System Hamiltonian, time-dependent with period *T*.

T [float] The period of the time-dependence of the hamiltonian.

args [dictionary] Dictionary with variables required to evaluate H.

Returns

output [list] A list of Floquet states for the time t.

floquet_wavefunction (f_modes_t, f_energies, f_coeff, t)

Evaluate the wavefunction for a time t using the Floquet state decompositon, given the Floquet modes at time *t*.

Parameters

f_modes_t [list of qutip.qobj (kets)] A list of initial Floquet modes (for time t = 0).

f_energies [array] The Floquet energies.

f_coeff [array] The coefficients for Floquet decomposition of the initial wavefunction.

t [float] The time for which to evaluate the Floquet states.

Returns

output [qutip.qobj] The wavefunction for the time t.

floquet_wavefunction_t (f_modes_0, f_energies, f_coeff, t, H, T, args=None)

Evaluate the wavefunction for a time t using the Floquet state decompositon, given the initial Floquet modes.

Parameters

f_modes_t [list of qutip.qobj (kets)] A list of initial Floquet modes (for time t = 0).

f_energies [array] The Floquet energies.

f_coeff [array] The coefficients for Floquet decomposition of the initial wavefunction.

t [float] The time for which to evaluate the Floquet states.

H [qutip.qobj] System Hamiltonian, time-dependent with period *T*.

 ${\bf T}$ [float] The period of the time-dependence of the hamiltonian.

args [dictionary] Dictionary with variables required to evaluate H.

Returns

output [qutip.qobj] The wavefunction for the time t.

floquet_state_decomposition (f_states, f_energies, psi)

Decompose the wavefunction *psi* (typically an initial state) in terms of the Floquet states, $\psi = \sum_{\alpha} c_{\alpha} \psi_{\alpha}(0)$.

Parameters

f_states [list of qutip.qobj (kets)] A list of Floquet modes.

f_energies [array] The Floquet energies.

psi [qutip.qobj] The wavefunction to decompose in the Floquet state basis.

Returns

output [array] The coefficients c_{α} in the Floquet state decomposition.

fsesolve (*H*, *psi0*, *tlist*, *e_ops=[]*, *T=None*, *args={}*, *Tsteps=100*) Solve the Schrodinger equation using the Floquet formalism.

Parameters

H [qutip.qobj.Qobj] System Hamiltonian, time-dependent with period T.

psi0 [qutip.qobj] Initial state vector (ket).

tlist [*list / array*] list of times for *t*.

- **e_ops** [list of qutip.qobj / callback function] list of operators for which to evaluate expectation values. If this list is empty, the state vectors for each time in *tlist* will be returned instead of expectation values.
- T [float] The period of the time-dependence of the hamiltonian.

args [dictionary] Dictionary with variables required to evaluate H.

Tsteps [integer] The number of time steps in one driving period for which to precalculate the Floquet modes. *Tsteps* should be an even number.

Returns

output [qutip.solver.Result] An instance of the class qutip.solver. Result, which contains either an *array* of expectation values or an array of state vectors, for the times specified by *tlist*.

Calculate the rates and matrix elements for the Floquet-Markov master equation.

Parameters

f_modes_0 [list of qutip.qobj (kets)] A list of initial Floquet modes.

f_energies [array] The Floquet energies.

- **c_op** [qutip.qobj] The collapse operators describing the dissipation.
- **H** [qutip.qobj] System Hamiltonian, time-dependent with period *T*.
- T [float] The period of the time-dependence of the hamiltonian.
- args [dictionary] Dictionary with variables required to evaluate H.
- **J_cb** [callback functions] A callback function that computes the noise power spectrum, as a function of frequency, associated with the collapse operator c_op .
- **w_th** [float] The temperature in units of frequency.
- **k_max** [int] The truncation of the number of sidebands (default 5).
- f_modes_table_t [nested list of qutip.qobj(kets)] A lookup-table of Floquet modes at times precalculated by qutip.floquet.floquet_modes_table (optional).

Returns

output [list] A list (Delta, X, Gamma, A) containing the matrices Delta, X, Gamma and A used in the construction of the Floquet-Markov master equation.

- $\begin{array}{l} \texttt{floquet_master_equation_steadystate} (H, A) \\ \text{Returns the steadystate density matrix (in the floquet basis!) for the Floquet-Markov master equation.} \end{array}$
- **floquet_basis_transform** (*f_modes*, *f_energies*, *rho0*) Make a basis transform that takes rho0 from the floquet basis to the computational basis.
- floquet_markov_mesolve(R, ekets, rho0, tlist, e_ops, f_modes_table=None, options=None, floquet_basis=True)

Solve the dynamics for the system using the Floquet-Markov master equation.

Stochastic Schrödinger Equation and Master Equation

smesolve (H, rho0, times, c_ops=[], sc_ops=[], e_ops=[], _safe_mode=True, args={}, **kwargs)
Solve stochastic master equation. Dispatch to specific solvers depending on the value of the solver keyword
argument.

Parameters

- **H** [*qutip.Qobj*, or time dependent system.] System Hamiltonian. Can depend on time, see StochasticSolverOptions help for format.
- **rho0** [qutip.Qobj] Initial density matrix or state vector (ket).
- times [*list / array*] List of times for t. Must be uniformly spaced.
- **c_ops** [list of *qutip.Qobj*, or time dependent Qobjs.] Deterministic collapse operator which will contribute with a standard Lindblad type of dissipation. Can depend on time, see StochasticSolverOptions help for format.
- **sc_ops** [list of *qutip.Qobj*, or time dependent Qobjs.] List of stochastic collapse operators. Each stochastic collapse operator will give a deterministic and stochastic contribution to the equation of motion according to how the d1 and d2 functions are defined. Can depend on time, see StochasticSolverOptions help for format.
- **e_ops** [list of *qutip.Qobj*] single operator or list of operators for which to evaluate expectation values.
- kwargs [dictionary] Optional keyword arguments. See qutip.stochastic. StochasticSolverOptions.

Returns

output: qutip.solver.Result An instance of the class qutip.solver.Result.

ssesolve (*H*, *psi0*, *times*, *sc_ops=[]*, *e_ops=[]*, *_safe_mode=True*, *args={}*, **kwargs)

Solve stochastic schrodinger equation. Dispatch to specific solvers depending on the value of the *solver* keyword argument.

Parameters

H [*qutip.Qobj*, or time dependent system.] System Hamiltonian. Can depend on time, see StochasticSolverOptions help for format.

psi0 [qutip.Qobj] State vector (ket).

times [list / array] List of times for t. Must be uniformly spaced.

- sc_ops [list of qutip.Qobj, or time dependent Qobjs.] List of stochastic collapse operators. Each stochastic collapse operator will give a deterministic and stochastic contribution to the equation of motion according to how the d1 and d2 functions are defined. Can depend on time, see StochasticSolverOptions help for format.
- **e_ops** [list of *qutip.Qobj*] single operator or list of operators for which to evaluate expectation values.
- **kwargs** [*dictionary*] Optional keyword arguments. See *qutip.stochastic. StochasticSolverOptions*.

Returns

output: qutip.solver.Result An instance of the class gutip.solver.Result.

smepdpsolve (H, rho0, times, c_ops, e_ops, **kwargs)

A stochastic (piecewse deterministic process) PDP solver for density matrix evolution.

Parameters

H [qutip.Qobj] System Hamiltonian.

rho0 [qutip.Qobj] Initial density matrix.

- times [list / array] List of times for t. Must be uniformly spaced.
- **c_ops** [list of *qutip.Qobj*] Deterministic collapse operator which will contribute with a standard Lindblad type of dissipation.
- **sc_ops** [list of *qutip.Qobj*] List of stochastic collapse operators. Each stochastic collapse operator will give a deterministic and stochastic contribution to the eqaution of motion according to how the d1 and d2 functions are defined.
- **e_ops** [list of *qutip.Qobj* / callback function single] single operator or list of operators for which to evaluate expectation values.
- kwargs [dictionary] Optional keyword arguments. See qutip.stochastic. StochasticSolverOptions.

Returns

output: qutip.solver.Result An instance of the class qutip.solver.Result.

ssepdpsolve (*H*, *psi0*, *times*, *c_ops*, *e_ops*, ***kwargs*)

A stochastic (piecewse deterministic process) PDP solver for wavefunction evolution. For most purposes, use *qutip.mcsolve* instead for quantum trajectory simulations.

Parameters

H [qutip.Qobj] System Hamiltonian.

psi0 [qutip.Qobj] Initial state vector (ket).

times [list / array] List of times for t. Must be uniformly spaced.

c_ops [list of *qutip.Qobj*] Deterministic collapse operator which will contribute with a standard Lindblad type of dissipation.

- **e_ops** [list of *qutip.Qobj* / callback function single] single operator or list of operators for which to evaluate expectation values.
- kwargs [dictionary] Optional keyword arguments. See qutip.stochastic. StochasticSolverOptions.

Returns

output: qutip.solver.Result An instance of the class qutip.solver.Result.

Correlation Functions

correlation (*H*, state0, tlist, taulist, c_ops, a_op, b_op, solver='me', reverse=False, args={}, options=<qutip.solver.Options object at 0x2acc48c86f60>)

Calculate the two-operator two-time correlation function: $\langle A(t + \tau)B(t) \rangle$ along two time axes using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Parameters

- **H** [Qobj] system Hamiltonian, may be time-dependent for solver choice of *me* or *mc*.
- **state0** [Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$. If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented for the *me* and *es* solvers.
- **tlist** [array_like] list of times for t. tlist must be positive and contain the element 0. When taking steady-steady correlations only one tlist value is necessary, i.e. when $t \to \infty$; here tlist is automatically set, ignoring user input.
- **taulist** [array_like] list of times for τ . taulist must be positive and contain the element θ .
- **c_ops** [list] list of collapse operators, may be time-dependent for solver choice of *me* or *mc*.
- a_op [Qobj] operator A.
- **b_op** [Qobj] operator B.
- **reverse** [bool] If True, calculate $\langle A(t)B(t+\tau)\rangle$ instead of $\langle A(t+\tau)B(t)\rangle$.
- **solver** [str] choice of solver (*me* for master-equation, *mc* for Monte Carlo, and *es* for exponential series).
- **options** [Options] solver options class. *ntraj* is taken as a two-element list because the *mc* correlator calls *mcsolve()* recursively; by default, *ntraj=[20, 100]*. *mc_corr_eps* prevents divide-by-zero errors in the *mc* correlator; by default, *mc_corr_eps=1e-10*.

Returns

corr_mat [array] An 2-dimensional array (matrix) of correlation values for the times specified by *tlist* (first index) and *taulist* (second index). If *tlist* is *None*, then a 1-dimensional array of correlation values is returned instead.

References

See, Gardiner, Quantum Noise, Section 5.2.

correlation_ss(H, taulist, c_ops, a_op, b_op, solver='me', reverse=False, args={}, options=<qutip.solver.Options object at 0x2acc48c86f28>) Calculate the two-operator two-time correlation function:

$$\lim_{t \to \infty} \left\langle A(t+\tau) B(t) \right\rangle$$

along one time axis (given steady-state initial conditions) using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Parameters

H [Qobj] system Hamiltonian.

taulist [array_like] list of times for τ . taulist must be positive and contain the element θ .

c_ops [list] list of collapse operators.

a_op [Qobj] operator A.

b_op [Qobj] operator B.

reverse [bool] If True, calculate $\lim_{t\to\infty} \langle A(t)B(t+\tau) \rangle$ instead of $\lim_{t\to\infty} \langle A(t+\tau)B(t) \rangle$.

solver [str] choice of solver (me for master-equation and es for exponential series).

options [Options] solver options class. *ntraj* is taken as a two-element list because the *mc* correlator calls *mcsolve()* recursively; by default, *ntraj=[20, 100]*. *mc_corr_eps* prevents divide-by-zero errors in the *mc* correlator; by default, *mc_corr_eps=1e-10*.

Returns

corr_vec [array] An array of correlation values for the times specified by *tlist*.

References

See, Gardiner, Quantum Noise, Section 5.2.

correlation_2op_1t (*H*, state0, taulist, c_ops, a_op, b_op, solver='me', reverse=False, args={}, options=<qutip.solver.Options object at 0x2acc48c86dd8>)

Calculate the two-operator two-time correlation function: $\langle A(t + \tau)B(t) \rangle$ along one time axis using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Parameters

H [Qobj] system Hamiltonian, may be time-dependent for solver choice of me or mc.

- **state0** [Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$. If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented for the *me* and *es* solvers.
- **taulist** [array_like] list of times for τ . taulist must be positive and contain the element θ .
- **c_ops** [list] list of collapse operators, may be time-dependent for solver choice of *me* or *mc*.
- **a_op** [Qobj] operator A.

b_op [Qobj] operator B.

- **reverse** [bool {False, True}] If *True*, calculate $\langle A(t)B(t+\tau)\rangle$ instead of $\langle A(t+\tau)B(t)\rangle$.
- **solver** [str {'me', 'mc', 'es'}] choice of solver (*me* for master-equation, *mc* for Monte Carlo, and *es* for exponential series).
- **options** [Options] Solver options class. *ntraj* is taken as a two-element list because the *mc* correlator calls *mcsolve()* recursively; by default, *ntraj=[20, 100]*. *mc_corr_eps* prevents divide-by-zero errors in the *mc* correlator; by default, *mc_corr_eps=1e-10*.

Returns

corr_vec [ndarray] An array of correlation values for the times specified by *tlist*.

References

See, Gardiner, Quantum Noise, Section 5.2.

correlation_2op_2t (*H*, state0, tlist, taulist, c_ops, a_op, b_op, solver='me', reverse=False, args={}, options=<qutip.solver.Options object at 0x2acc48c86e10>)

Calculate the two-operator two-time correlation function: $\langle A(t + \tau)B(t) \rangle$ along two time axes using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Parameters

- H [Qobj] system Hamiltonian, may be time-dependent for solver choice of me or mc.
- **state0** [Qobj] Initial state density matrix ρ_0 or state vector ψ_0 . If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented for the *me* and *es* solvers.
- **tlist** [array_like] list of times for t. tlist must be positive and contain the element 0. When taking steady-steady correlations only one tlist value is necessary, i.e. when $t \to \infty$; here tlist is automatically set, ignoring user input.
- **taulist** [array_like] list of times for τ . taulist must be positive and contain the element θ .
- **c_ops** [list] list of collapse operators, may be time-dependent for solver choice of *me* or *mc*.
- **a_op** [Qobj] operator A.
- **b_op** [Qobj] operator B.
- **reverse** [bool {False, True}] If *True*, calculate $\langle A(t)B(t+\tau)\rangle$ instead of $\langle A(t+\tau)B(t)\rangle$.
- **solver** [str] choice of solver (*me* for master-equation, *mc* for Monte Carlo, and *es* for exponential series).
- **options** [Options] solver options class. *ntraj* is taken as a two-element list because the *mc* correlator calls *mcsolve()* recursively; by default, *ntraj=[20, 100]*. *mc_corr_eps* prevents divide-by-zero errors in the *mc* correlator; by default, *mc_corr_eps=1e-10*.

Returns

corr_mat [ndarray] An 2-dimensional array (matrix) of correlation values for the times specified by *tlist* (first index) and *taulist* (second index). If *tlist* is *None*, then a 1-dimensional array of correlation values is returned instead.

References

See, Gardiner, Quantum Noise, Section 5.2.

correlation_3op_1t (H, state0, taulist, c_ops, a_op, b_op, c_op, solver='me', args={}, options=<qutip.solver.Options object at 0x2acc48c86e48>)

Calculate the three-operator two-time correlation function: $\langle A(t)B(t+\tau)C(t)\rangle$ along one time axis using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Note: it is not possibly to calculate a physically meaningful correlation of this form where $\tau < 0$.

Parameters

- H [Qobj] system Hamiltonian, may be time-dependent for solver choice of me or mc.
- **rho0** [Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$. If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented for the *me* and *es* solvers.
- **taulist** [array_like] list of times for τ . taulist must be positive and contain the element θ .
- **c_ops** [list] list of collapse operators, may be time-dependent for solver choice of *me* or *mc*.
- **a_op** [Qobj] operator A.
- **b_op** [Qobj] operator B.
- **c_op** [Qobj] operator C.

- **solver** [str] choice of solver (*me* for master-equation, *mc* for Monte Carlo, and *es* for exponential series).
- **options** [Options] solver options class. *ntraj* is taken as a two-element list because the *mc* correlator calls *mcsolve()* recursively; by default, *ntraj=[20, 100]*. *mc_corr_eps* prevents divide-by-zero errors in the *mc* correlator; by default, *mc_corr_eps=1e-10*.

Returns

corr_vec [array] An array of correlation values for the times specified by taulist

References

See, Gardiner, Quantum Noise, Section 5.2.

correlation_3op_2t (H, state0, tlist, taulist, c_ops, a_op, b_op, c_op, solver='me', args={}, options=<qutip.solver.Options object at 0x2acc48c86e80>)

Calculate the three-operator two-time correlation function: $\langle A(t)B(t+\tau)C(t)\rangle$ along two time axes using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Note: it is not possibly to calculate a physically meaningful correlation of this form where $\tau < 0$.

Parameters

H [Qobj] system Hamiltonian, may be time-dependent for solver choice of *me* or *mc*.

- **rho0** [Qobj] Initial state density matrix ρ_0 or state vector ψ_0 . If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented for the *me* and *es* solvers.
- **tlist** [array_like] list of times for t. tlist must be positive and contain the element 0. When taking steady-steady correlations only one tlist value is necessary, i.e. when $t \to \infty$; here tlist is automatically set, ignoring user input.
- **taulist** [array_like] list of times for τ . taulist must be positive and contain the element θ .
- **c_ops** [list] list of collapse operators, may be time-dependent for solver choice of *me* or *mc*.
- **a_op** [Qobj] operator A.
- **b_op** [Qobj] operator B.
- **c_op** [Qobj] operator C.
- **solver** [str] choice of solver (*me* for master-equation, *mc* for Monte Carlo, and *es* for exponential series).
- **options** [Options] solver options class. *ntraj* is taken as a two-element list because the *mc* correlator calls *mcsolve()* recursively; by default, *ntraj=[20, 100]*. *mc_corr_eps* prevents divide-by-zero errors in the *mc* correlator; by default, *mc_corr_eps=1e-10*.

Returns

corr_mat [array] An 2-dimensional array (matrix) of correlation values for the times specified by *tlist* (first index) and *taulist* (second index). If *tlist* is *None*, then a 1-dimensional array of correlation values is returned instead.

References

See, Gardiner, Quantum Noise, Section 5.2.

correlation_4op_1t (H, state0, taulist, c_ops, a_op, b_op, c_op, d_op, solver='me', args={}, options=<qutip.solver.Options object at 0x2acc48c86f98>)

Calculate the four-operator two-time correlation function: $\langle A(t)B(t+\tau)C(t+\tau)D(t)\rangle$ along one time axis using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Note: it is not possibly to calculate a physically meaningful correlation of this form where $\tau < 0$.

Parameters

- H [Qobj] system Hamiltonian, may be time-dependent for solver choice of me or mc.
- **rho0** [Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$. If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented for the *me* and *es* solvers.
- taulist [array_like] list of times for τ . taulist must be positive and contain the element θ .
- **c_ops** [list] list of collapse operators, may be time-dependent for solver choice of *me* or *mc*.
- **a_op** [Qobj] operator A.
- **b_op** [Qobj] operator B.
- **c_op** [Qobj] operator C.
- **d_op** [Qobj] operator D.
- **solver** [str] choice of solver (*me* for master-equation, *mc* for Monte Carlo, and *es* for exponential series).
- **options** [Options] solver options class. *ntraj* is taken as a two-element list because the *mc* correlator calls *mcsolve()* recursively; by default, *ntraj=[20, 100]*. *mc_corr_eps* prevents divide-by-zero errors in the *mc* correlator; by default, *mc_corr_eps=1e-10*.

Returns

corr_vec [array] An array of correlation values for the times specified by taulist.

References

See, Gardiner, Quantum Noise, Section 5.2.

Note: Deprecated in QuTiP 3.1 Use correlation_3op_1t() instead.

- - Calculate the four-operator two-time correlation function: $\langle A(t)B(t+\tau)C(t+\tau)D(t)\rangle$ along two time axes using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Note: it is not possibly to calculate a physically meaningful correlation of this form where $\tau < 0$.

Parameters

- **H** [Qobj] system Hamiltonian, may be time-dependent for solver choice of *me* or *mc*.
- **rho0** [Qobj] Initial state density matrix ρ_0 or state vector ψ_0 . If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented for the *me* and *es* solvers.
- **tlist** [array_like] list of times for t. tlist must be positive and contain the element 0. When taking steady-steady correlations only one tlist value is necessary, i.e. when $t \to \infty$; here tlist is automatically set, ignoring user input.
- **taulist** [array_like] list of times for τ . taulist must be positive and contain the element θ .
- **c_ops** [list] list of collapse operators, may be time-dependent for solver choice of *me* or *mc*.
- **a_op** [Qobj] operator A.
- **b_op** [Qobj] operator B.
- **c_op** [Qobj] operator C.
- **d_op** [Qobj] operator D.

- **solver** [str] choice of solver (*me* for master-equation, *mc* for Monte Carlo, and *es* for exponential series).
- **options** [Options] solver options class. *ntraj* is taken as a two-element list because the *mc* correlator calls *mcsolve()* recursively; by default, *ntraj=[20, 100]*. *mc_corr_eps* prevents divide-by-zero errors in the *mc* correlator; by default, *mc_corr_eps=1e-10*.

Returns

corr_mat [array] An 2-dimensional array (matrix) of correlation values for the times specified by *tlist* (first index) and *taulist* (second index). If *tlist* is *None*, then a 1-dimensional array of correlation values is returned instead.

References

See, Gardiner, Quantum Noise, Section 5.2.

spectrum(H, wlist, c_ops, a_op, b_op, solver='es', use_pinv=False)

Calculate the spectrum of the correlation function $\lim_{t\to\infty} \langle A(t+\tau)B(t)\rangle$, i.e., the Fourier transform of the correlation function:

$$S(\omega) = \int_{-\infty}^{\infty} \lim_{t \to \infty} \left\langle A(t+\tau)B(t) \right\rangle e^{-i\omega\tau} d\tau.$$

using the solver indicated by the *solver* parameter. Note: this spectrum is only defined for stationary statistics (uses steady state rho0)

Parameters

H [qutip.qobj] system Hamiltonian.

wlist [array_like] list of frequencies for ω .

c_ops [list] list of collapse operators.

a_op [Qobj] operator A.

b_op [Qobj] operator B.

solver [str] choice of solver (es for exponential series and pi for psuedo-inverse).

use_pinv [bool] For use with the *pi* solver: if *True* use numpy's pinv method, otherwise use a generic solver.

Returns

spectrum [array] An array with spectrum $S(\omega)$ for the frequencies specified in *wlist*.

spectrum_ss(H, wlist, c_ops, a_op, b_op)

Calculate the spectrum of the correlation function $\lim_{t\to\infty} \langle A(t+\tau)B(t)\rangle$, i.e., the Fourier transform of the correlation function:

$$S(\omega) = \int_{-\infty}^{\infty} \lim_{t \to \infty} \left\langle A(t+\tau)B(t) \right\rangle e^{-i\omega\tau} d\tau$$

using an eseries based solver Note: this spectrum is only defined for stationary statistics (uses steady state rho0).

Parameters

H [qutip.qobj] system Hamiltonian.

wlist [array_like] list of frequencies for ω .

c_ops [*list* of qutip.qobj] list of collapse operators.

a_op [qutip.qobj] operator A.

b_op [qutip.qobj] operator B.

use_pinv [bool] If True use numpy's pinv method, otherwise use a generic solver.

Returns

spectrum [array] An array with spectrum $S(\omega)$ for the frequencies specified in *wlist*.

spectrum_pi(H, wlist, c_ops, a_op, b_op, use_pinv=False)

Calculate the spectrum of the correlation function $\lim_{t\to\infty} \langle A(t+\tau)B(t)\rangle$, i.e., the Fourier transform of the correlation function:

$$S(\omega) = \int_{-\infty}^{\infty} \lim_{t \to \infty} \left\langle A(t+\tau)B(t) \right\rangle e^{-i\omega\tau} d\tau.$$

using a psuedo-inverse method. Note: this spectrum is only defined for stationary statistics (uses steady state rho0)

Parameters

H [qutip.qobj] system Hamiltonian.

wlist [array_like] list of frequencies for ω .

c_ops [*list* of qutip.qobj] list of collapse operators.

a_op [qutip.qobj] operator A.

b_op [qutip.qobj] operator B.

use_pinv [bool] If True use numpy's pinv method, otherwise use a generic solver.

Returns

spectrum [array] An array with spectrum $S(\omega)$ for the frequencies specified in *wlist*.

spectrum_correlation_fft(tlist, y, inverse=False)

Calculate the power spectrum corresponding to a two-time correlation function using FFT.

Parameters

tlist [array_like] list/array of times t which the correlation function is given.

y [array_like] list/array of correlations corresponding to time delays t.

inverse: boolean boolean parameter for using a positive exponent in the Fourier Transform instead. Default is False.

Returns

- **w**, **S** [tuple] Returns an array of angular frequencies 'w' and the corresponding two-sided power spectrum 'S(w)'.
- coherence_function_g1(H, state0, taulist, c_ops, a_op, solver='me', args={}, options=<qutip.solver.Options object at 0x2acc48c86eb8>)

Calculate the normalized first-order quantum coherence function:

$$g^{(1)}(\tau) = \frac{\langle A^{\dagger}(\tau)A(0)\rangle}{\sqrt{\langle A^{\dagger}(\tau)A(\tau)\rangle\langle A^{\dagger}(0)A(0)\rangle}}$$

using the quantum regression theorem and the evolution solver indicated by the *solver* parameter.

Parameters

H [Qobj] system Hamiltonian, may be time-dependent for solver choice of me or mc.

state0 [Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$. If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented for the *me* and *es* solvers.

taulist [array_like] list of times for τ . taulist must be positive and contain the element θ .

c_ops [list] list of collapse operators, may be time-dependent for solver choice of *me* or *mc*.

a_op [Qobj] operator A.

solver [str] choice of solver (me for master-equation and es for exponential series).

options [Options] solver options class. *ntraj* is taken as a two-element list because the *mc* correlator calls *mcsolve()* recursively; by default, *ntraj=[20, 100]*. *mc_corr_eps* prevents divide-by-zero errors in the *mc* correlator; by default, *mc corr eps=1e-10*.

Returns

g1, G1 [tuple] The normalized and unnormalized second-order coherence function.

coherence_function_g2 (H, state0, taulist, c_ops, a_op, solver='me', args={}, options=<qutip.solver.Options object at 0x2acc48c86ef0>) Calculate the normalized second-order quantum coherence function:

$$g^{(2)}(\tau) = \frac{\langle A^{\dagger}(0)A^{\dagger}(\tau)A(\tau)A(0)\rangle}{\langle A^{\dagger}(\tau)A(\tau)\rangle\langle A^{\dagger}(0)A(0)\rangle}$$

using the quantum regression theorem and the evolution solver indicated by the solver parameter.

Parameters

- **H** [Qobj] system Hamiltonian, may be time-dependent for solver choice of *me* or *mc*.
- **state0** [Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$. If 'state0' is 'None', then the steady state will be used as the initial state. The 'steady-state' is only implemented for the *me* and *es* solvers.
- **taulist** [array_like] list of times for τ . taulist must be positive and contain the element θ .
- **c_ops** [list] list of collapse operators, may be time-dependent for solver choice of *me* or *mc*.
- **a_op** [Qobj] operator A.
- args [dict] Dictionary of arguments to be passed to solver.
- solver [str] choice of solver (me for master-equation and es for exponential series).
- **options** [Options] solver options class. *ntraj* is taken as a two-element list because the *mc* correlator calls *mcsolve()* recursively; by default, *ntraj=[20, 100]*. *mc_corr_eps* prevents divide-by-zero errors in the *mc* correlator; by default, *mc_corr_eps=1e-10*.

Returns

g2, G2 [tuple] The normalized and unnormalized second-order coherence function.

Steady-state Solvers

Module contains functions for solving for the steady state density matrix of open quantum systems defined by a Liouvillian or Hamiltonian and a list of collapse operators.

steadystate(A, c_op_list=[], method='direct', solver=None, **kwargs)

Calculates the steady state for quantum evolution subject to the supplied Hamiltonian or Liouvillian operator and (if given a Hamiltonian) a list of collapse operators.

If the user passes a Hamiltonian then it, along with the list of collapse operators, will be converted into a Liouvillian operator in Lindblad form.

Parameters

A [qobj] A Hamiltonian or Liouvillian operator.

c_op_list [list] A list of collapse operators.

solver [str {None, 'scipy', 'mkl'}] Selects the sparse solver to use. Default is auto-select based on the availability of the MKL library.

method [str {'direct', 'eigen', 'iterative-gmres',]

'iterative-lgmres', 'iterative-bicgstab', 'svd', 'power', 'power-gmres', 'power-lgmres', 'power-bicgstab'}

Method for solving the underlying linear equation. Direct LU solver 'direct' (default), sparse eigenvalue problem 'eigen', iterative GMRES method 'iterative-gmres', iterative LGMRES method 'iterative-lgmres', iterative BICGSTAB method 'iterative-bicgstab', SVD 'svd' (dense), or inverse-power method 'power'. The iterative power methods 'power-gmres', 'power-lgmres', 'power-bicgstab' use the same solvers as their direct counterparts.

- **return_info** [bool, optional, default = False] Return a dictionary of solver-specific infomation about the solution and how it was obtained.
- sparse [bool, optional, default = True] Solve for the steady state using sparse algorithms. If set to False, the underlying Liouvillian operator will be converted into a dense matrix. Use only for 'smaller' systems.
- **use_rcm** [bool, optional, default = False] Use reverse Cuthill-Mckee reordering to minimize fill-in in the LU factorization of the Liouvillian.
- **use_wbm** [bool, optional, default = False] Use Weighted Bipartite Matching reordering to make the Liouvillian diagonally dominant. This is useful for iterative preconditioners only, and is set to True by default when finding a preconditioner.
- **weight** [float, optional] Sets the size of the elements used for adding the unity trace condition to the linear solvers. This is set to the average abs value of the Liouvillian elements if not specified by the user.
- max_iter_refine [int {10}] MKL ONLY. Max. number of iterative refinements to perform.
- scaling_vectors [bool {True, False}] MKL ONLY. Scale matrix to unit norm columns and rows.
- weighted_matching [bool {True, False}] MKL ONLY. Use weighted matching to better condition diagonal.
- x0 [ndarray, optional] ITERATIVE ONLY. Initial guess for solution vector.
- **maxiter** [int, optional, default=1000] ITERATIVE ONLY. Maximum number of iterations to perform.
- tol [float, optional, default=1e-12] ITERATIVE ONLY. Tolerance used for terminating solver.
- **mtol** [float, optional, default=None] ITERATIVE 'power' methods ONLY. Tolerance for lu solve method. If None given then *max*(0.1*tol, 1e-15) is used
- **matol** [float, optional, default=1e-15] ITERATIVE ONLY. Absolute tolerance for lu solve method.
- **permc_spec** [str, optional, default='COLAMD'] ITERATIVE ONLY. Column ordering used internally by superLU for the 'direct' LU decomposition method. Options include 'COLAMD' and 'NATURAL'. If using RCM then this is set to 'NATURAL' automatically unless explicitly specified.
- **use_precond** [bool optional, default = False] ITERATIVE ONLY. Use an incomplete sparse LU decomposition as a preconditioner for the 'iterative' GMRES and BICG solvers. Speeds up convergence time by orders of magnitude in many cases.
- M [{sparse matrix, dense matrix, LinearOperator}, optional] ITERATIVE ONLY. Preconditioner for A. The preconditioner should approximate the inverse of A. Effective preconditioning can dramatically improve the rate of convergence for iterative methods. If no preconditioner is given and use_precond = True, then one is generated automatically.

- **fill_factor** [float, optional, default = 100] ITERATIVE ONLY. Specifies the fill ratio upper bound (>=1) of the iLU preconditioner. Lower values save memory at the cost of longer execution times and a possible singular factorization.
- **drop_tol** [float, optional, default = 1e-4] ITERATIVE ONLY. Sets the threshold for the magnitude of preconditioner elements that should be dropped. Can be reduced for a courser factorization at the cost of an increased number of iterations, and a possible singular factorization.
- **diag_pivot_thresh** [float, optional, default = None] ITERATIVE ONLY. Sets the threshold between [0,1] for which diagonal elements are considered acceptable pivot points when using a preconditioner. A value of zero forces the pivot to be the diagonal element.
- **ILU_MILU** [str, optional, default = 'smilu_2'] ITERATIVE ONLY. Selects the incomplete LU decomposition method algoithm used in creating the preconditoner. Should only be used by advanced users.

Returns

dm [qobj] Steady state density matrix.

info [dict, optional] Dictionary containing solver-specific information about the solution.

Notes

The SVD method works only for dense operators (i.e. small systems).

build_preconditioner(A, c_op_list=[], **kwargs)

Constructs a iLU preconditioner necessary for solving for the steady state density matrix using the iterative linear solvers in the 'steadystate' function.

Parameters

A [qobj] A Hamiltonian or Liouvillian operator.

c_op_list [list] A list of collapse operators.

- **return_info** [bool, optional, default = False] Return a dictionary of solver-specific infomation about the solution and how it was obtained.
- **use_rcm** [bool, optional, default = False] Use reverse Cuthill-Mckee reordering to minimize fill-in in the LU factorization of the Liouvillian.
- **use_wbm** [bool, optional, default = False] Use Weighted Bipartite Matching reordering to make the Liouvillian diagonally dominant. This is useful for iterative preconditioners only, and is set to True by default when finding a preconditioner.
- **weight** [float, optional] Sets the size of the elements used for adding the unity trace condition to the linear solvers. This is set to the average abs value of the Liouvillian elements if not specified by the user.
- **method** [str, default = 'iterative'] Tells the preconditioner what type of Liouvillian to build for iLU factorization. For direct iterative methods use 'iterative'. For power iterative methods use 'power'.
- permc_spec [str, optional, default='COLAMD'] Column ordering used internally by superLU for the 'direct' LU decomposition method. Options include 'COLAMD' and 'NATURAL'. If using RCM then this is set to 'NATURAL' automatically unless explicitly specified.
- **fill_factor** [float, optional, default = 100] Specifies the fill ratio upper bound (>=1) of the iLU preconditioner. Lower values save memory at the cost of longer execution times and a possible singular factorization.

- **drop_tol** [float, optional, default = 1e-4] Sets the threshold for the magnitude of preconditioner elements that should be dropped. Can be reduced for a courser factorization at the cost of an increased number of iterations, and a possible singular factorization.
- **diag_pivot_thresh** [float, optional, default = None] Sets the threshold between [0,1] for which diagonal elements are considered acceptable pivot points when using a preconditioner. A value of zero forces the pivot to be the diagonal element.
- **ILU_MILU** [str, optional, default = 'smilu_2'] Selects the incomplete LU decomposition method algoithm used in creating the preconditoner. Should only be used by advanced users.

lu [object] Returns a SuperLU object representing iLU preconditioner.

info [dict, optional] Dictionary containing solver-specific information.

Propagators

Calculate the propagator U(t) for the density matrix or wave function such that $\psi(t) = U(t)\psi(0)$ or $\rho_{vec}(t) = U(t)\rho_{vec}(0)$ where ρ_{vec} is the vector representation of the density matrix.

Parameters

- **H** [qobj or list] Hamiltonian as a Qobj instance of a nested list of Qobjs and coefficients in the list-string or list-function format for time-dependent Hamiltonians (see description in *qutip.mesolve*).
- t [float or array-like] Time or list of times for which to evaluate the propagator.
- c_op_list [list] List of qobj collapse operators.
- **args** [list/array/dictionary] Parameters to callback functions for time-dependent Hamiltonians and collapse operators.
- options [qutip.Options] with options for the ODE solver.
- unitary_mode = str ('batch', 'single') Solve all basis vectors simulaneously ('batch') or individually ('single').
- **parallel** [bool {False, True}] Run the propagator in parallel mode. This will override the unitary_mode settings if set to True.
- **progress_bar: BaseProgressBar** Optional instance of BaseProgressBar, or a subclass thereof, for showing the progress of the simulation. By default no progress bar is used, and if set to True a TextProgressBar will be used.

Returns

a [qobj] Instance representing the propagator U(t).

$\verb|propagator_steadystate(U)|$

Find the steady state for successive applications of the propagator U.

Parameters

U [qobj] Operator representing the propagator.

Returns

a [qobj] Instance representing the steady-state density matrix.

Time-dependent problems

rhs_generate(*H*, *c_ops*, *args={}*, *options=<qutip.solver.Options object at* 0x2acc45b676d8>, *name=None*, *cleanup=True*)

Generates the Cython functions needed for solving the dynamics of a given system using the mesolve function inside a parfor loop.

Parameters

H [qobj] System Hamiltonian.

c_ops [list] list of collapse operators.

args [dict] Arguments for time-dependent Hamiltonian and collapse operator terms.

options [Options] Instance of ODE solver options.

name: str Name of generated RHS

cleanup: bool Whether the generated cython file should be automatically removed or not.

Notes

Using this function with any solver other than the mesolve function will result in an error.

rhs_clear()

Resets the string-format time-dependent Hamiltonian parameters.

Returns

Nothing, just clears data from internal config module.

Scattering in Quantum Optical Systems

Photon scattering in quantum optical systems

This module includes a collection of functions for numerically computing photon scattering in driven arbitrary systems coupled to some configuration of output waveguides. The implementation of these functions closely follows the mathematical treatment given in K.A. Fischer, et. al., Scattering of Coherent Pulses from Quantum Optical Systems (2017, arXiv:1710.02875).

temporal_basis_vector(waveguide_emission_indices, n_time_bins)

Generate a temporal basis vector for emissions at specified time bins into specified waveguides.

Parameters

waveguide_emission_indices [list or tuple] List of indices where photon emission occurs for each waveguide, e.g. [[t1_wg1], [t1_wg2, t2_wg2], [], [t1_wg4, t2_wg4, t3_wg4]].

n_time_bins [int] Number of time bins; the range over which each index can vary.

Returns

temporal_basis_vector [:class: qutip.Qobj] A basis vector representing photon scattering at the specified indices. If there are W waveguides, T times, and N photon emissions, then the basis vector has dimensionality (W*T)^N.

temporal_scattered_state (*H*, *psi0*, *n_emissions*, *c_ops*, *tlist*, *system_zero_state=None*, *con-struct_effective_hamiltonian=True*)

Compute the scattered n-photon state projected onto the temporal basis.

Parameters

- **H** [:class: qutip.Qobj or list] System-waveguide(s) Hamiltonian or effective Hamiltonian in Qobj or list-callback format. If construct_effective_hamiltonian is not specified, an effective Hamiltonian is constructed from *H* and *c_ops*.
- **psi0** [:class: qutip.Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$.

n_emissions [int] Number of photon emissions to calculate.

- **c_ops** [list] List of collapse operators for each waveguide; these are assumed to include spontaneous decay rates, e.g. $\sigma = \sqrt{\gamma} \cdot a$
- tlist [array_like] List of times for τ_i . tlist should contain 0 and exceed the pulse duration / temporal region of interest.
- system_zero_state [:class: qutip.Qobj] State representing zero excitations in the system. Defaults to $\psi(t_0)$
- **construct_effective_hamiltonian** [bool] Whether an effective Hamiltonian should be constructed from H and c_ops: $H_{eff} = H \frac{i}{2} \sum_n \sigma_n^{\dagger} \sigma_n$ Default: True.

Returns

phi_n [:class: qutip.Qobj] The scattered bath state projected onto the temporal basis given by tlist. If there are W waveguides, T times, and N photon emissions, then the state is a tensor product state with dimensionality T^(W*N).

scattering_probability (H, psi0, n_emissions, c_ops, tlist, system_zero_state=None, construct_effective_hamiltonian=True)

Compute the integrated probability of scattering n photons in an arbitrary system. This function accepts a nonlinearly spaced array of times.

Parameters

- **H** [:class: qutip.Qobj or list] System-waveguide(s) Hamiltonian or effective Hamiltonian in Qobj or list-callback format. If construct_effective_hamiltonian is not specified, an effective Hamiltonian is constructed from H and *c_ops*.
- **psi0** [:class: qutip.Qobj] Initial state density matrix $\rho(t_0)$ or state vector $\psi(t_0)$.
- **n_emissions** [int] Number of photons emitted by the system (into any combination of waveguides).
- **c_ops** [list] List of collapse operators for each waveguide; these are assumed to include spontaneous decay rates, e.g. $\sigma = \sqrt{\gamma} \cdot a$.
- tlist [array_like] List of times for τ_i . tlist should contain 0 and exceed the pulse duration / temporal region of interest; tlist need not be linearly spaced.
- **system_zero_state** [:class: qutip.Qobj] State representing zero excitations in the system. Defaults to *basis(systemDims, 0)*.
- **construct_effective_hamiltonian** [bool] Whether an effective Hamiltonian should be constructed from H and c_ops: $H_{eff} = H \frac{i}{2} \sum_n \sigma_n^{\dagger} \sigma_n$ Default: True.

Returns

scattering_prob [float] The probability of scattering n photons from the system over the time range specified.

Permutational Invariance

Permutational Invariant Quantum Solver (PIQS)

This module calculates the Liouvillian for the dynamics of ensembles of identical two-level systems (TLS) in the presence of local and collective processes by exploiting permutational symmetry and using the Dicke basis.

```
jspin (N, op=None, basis='dicke')
```

Calculate the list of collective operators of the total algebra.

The Dicke basis $|j, m\rangle\langle j, m'|$ is used by default. Otherwise with "uncoupled" the operators are in a 2^N space.

Parameters

N: int Number of two-level systems.

op: str The operator to return 'x','y','z','+','-'. If no operator given, then output is the list of operators for ['x','y','z'].

basis: str The basis of the operators - "dicke" or "uncoupled" default: "dicke".

Returns

j_alg: list or :class: qutip.Qobj A list of *qutip.Qobj* representing all the operators in the "dicke" or "uncoupled" basis or a single operator requested.

dicke(N, j, m)

Generate a Dicke state as a pure density matrix in the Dicke basis.

For instance, the superradiant state given by $|j,m\rangle = |1,0\rangle$ for N = 2, and the state is represented as a density matrix of size (nds, nds) or (4, 4), with the (1, 1) element set to 1.

Parameters

N: int The number of two-level systems.

j: float The eigenvalue j of the Dicke state (j, m).

m: float The eigenvalue m of the Dicke state (j, m).

Returns

rho: :class: qutip.Qobj The density matrix.

superradiant (N, basis='dicke')

Generate the density matrix of the superradiant state.

This state is given by (N/2, 0) or (N/2, 0.5) in the Dicke basis. If the argument *basis* is "uncoupled" then it generates the state in a 2**N dim Hilbert space.

Parameters

N: int The number of two-level systems.

basis: str The basis to use. Either "dicke" or "uncoupled".

Returns

state: :class: qutip.Qobj The superradiant state density matrix in the requested basis.

```
ghz (N, basis='dicke')
```

Generate the density matrix of the GHZ state.

If the argument *basis* is "uncoupled" then it generates the state in a 2^N -dimensional Hilbert space.

Parameters

N: int The number of two-level systems.

basis: str The basis to use. Either "dicke" or "uncoupled".

Returns

state: :class: qutip.Qobj The GHZ state density matrix in the requested basis.

css (N, x=0.7071067811865475, y=0.7071067811865475, basis='dicke', coordinates='cartesian') Generate the density matrix of the Coherent Spin State (CSS).

It can be defined as, $|CSS\rangle = \prod_{i}^{N} (a|1\rangle_{i} + b|0\rangle_{i})$ with $a = sin(\frac{\theta}{2})$, $b = e^{i\phi} \cos(\frac{\theta}{2})$. The default basis is that of Dicke space $|j, m\rangle\langle j, m'|$. The default state is the symmetric CSS, $|CSS\rangle = |+\rangle$.

Parameters

N: int The number of two-level systems.

x, y: float The coefficients of the CSS state.

basis: str The basis to use. Either "dicke" or "uncoupled".

coordinates: str Either "cartesian" or "polar". If polar then the coefficients are constructed as sin(x/2), $cos(x/2)e^{(iy)}$.

Returns

rho: :class: qutip.Qobj The CSS state density matrix.

excited (N, basis='dicke')

Generate the density matrix for the excited state.

This state is given by (N/2, N/2) in the default Dicke basis. If the argument *basis* is "uncoupled" then it generates the state in a 2**N dim Hilbert space.

Parameters

N: int The number of two-level systems.

basis: str The basis to use. Either "dicke" or "uncoupled".

Returns

state: :class: qutip.Qobj The excited state density matrix in the requested basis.

ground (N, basis='dicke')

Generate the density matrix of the ground state.

This state is given by (N/2, -N/2) in the Dicke basis. If the argument *basis* is "uncoupled" then it generates the state in a 2^N -dimensional Hilbert space.

Parameters

N: int The number of two-level systems.

basis: str The basis to use. Either "dicke" or "uncoupled"

Returns

state: :class: qutip.Qobj The ground state density matrix in the requested basis.

num_dicke_states(N)

Calculate the number of Dicke states.

Parameters

N: int The number of two-level systems.

Returns

nds: int The number of Dicke states.

num_dicke_ladders(N)

Calculate the total number of ladders in the Dicke space.

For a collection of N two-level systems it counts how many different "j" exist or the number of blocks in the block-diagonal matrix.

Parameters

N: int The number of two-level systems.

Returns

Nj: int The number of Dicke ladders.

num_tls(nds)

Calculate the number of two-level systems.

Parameters

nds: int The number of Dicke states.

Returns

N: int The number of two-level systems.

isdiagonal(mat)

Check if the input matrix is diagonal.

Parameters

mat: ndarray/Qobj A 2D numpy array

Returns

diag: bool True/False depending on whether the input matrix is diagonal.

state_degeneracy (N, j)

Calculate the degeneracy of the Dicke state.

Each state $|j, m\rangle$ includes D(N,j) irreducible representations $|j, m, \alpha\rangle$.

Uses Decimals to calculate higher numerator and denominators numbers.

Parameters

N: int The number of two-level systems.

j: float Total spin eigenvalue (cooperativity).

Returns

degeneracy: int The state degeneracy.

$m_degeneracy(N, m)$

Calculate the number of Dicke states $|j, m\rangle$ with same energy.

Parameters

N: int The number of two-level systems.

m: float Total spin z-axis projection eigenvalue (proportional to the total energy).

Returns

degeneracy: int The m-degeneracy.

$\mathbf{ap}(j,m)$

Calculate the coefficient *ap* by applying J_+ |j, m>.

The action of ap is given by: $J_+|j,m\rangle = A_+(j,m)|j,m+1\rangle$

Parameters

j, **m: float** The value for j and m in the dicke basis |j,m>.

Returns

a_plus: float The value of a_+ .

$\mathbf{am}(j,m)$

Calculate the operator am used later.

The action of ap is given by: $J_{-}|j, m\rangle = A_{-}(jm)|j, m-1\rangle$

Parameters

j: float The value for j.

m: float The value for m.

Returns

a_minus: float The value of a_- .

spin_algebra (N, op=None)

Create the list [sx, sy, sz] with the spin operators.

The operators are constructed for a collection of N two-level systems (TLSs). Each element of the list, i.e., sx, is a vector of *qutip.Qobj* objects (spin matrices), as it cointains the list of the SU(2) Pauli matrices for the N TLSs. Each TLS operator sx[i], with i = 0, ..., (N-1), is placed in a 2^N -dimensional Hilbert space.

Parameters

N: int The number of two-level systems.

Returns

spin_operators: list or :class: qutip.Qobj A list of *qutip.Qobj* operators - [sx, sy, sz] or the requested operator.

Notes

sx[i] is $\frac{\sigma_x}{2}$ in the composite Hilbert space.

collapse_uncoupled (*N*, *emission=0.0*, *dephasing=0.0*, *pumping=0.0*, *collective_emission=0.0*, *collective_dephasing=0.0*, *collective_pumping=0.0*)

Create the collapse operators (c_ops) of the Lindbladian in the uncoupled basis

These operators are in the uncoupled basis of the two-level system (TLS) SU(2) Pauli matrices.

Parameters

N: int The number of two-level systems.

emission: float Incoherent emission coefficient (also nonradiative emission). default: 0.0

dephasing: float Local dephasing coefficient. default: 0.0

pumping: float Incoherent pumping coefficient. default: 0.0

collective_emission: float Collective (superradiant) emmission coefficient. default: 0.0

collective_pumping: float Collective pumping coefficient. default: 0.0

collective_dephasing: float Collective dephasing coefficient. default: 0.0

Returns

c_ops: list The list of collapse operators as *qutip.Qobj* for the system.

Notes

The collapse operator list can be given to *qutip.mesolve*. Notice that the operators are placed in a Hilbert space of dimension 2^N . Thus the method is suitable only for small N (of the order of 10).

dicke_basis (N, jmm1=None)

Initialize the density matrix of a Dicke state for several (j, m, m1).

This function can be used to build arbitrary states in the Dicke basis $|j,m\rangle\langle j,m'|$. We create coefficients for each (j, m, m1) value in the dictionary jmm1. The mapping for the (i, k) index of the density matrix to the lj, m> values is given by the cythonized function *jmm1_dictionary*. A density matrix is created from the given dictionary of coefficients for each (j, m, m1).

Parameters

N: int The number of two-level systems.

jmm1: dict A dictionary of {(j, m, m1): p} that gives a density p for the (j, m, m1) matrix element.

Returns

rho: :class: qutip.Qobj The density matrix in the Dicke basis.

4.2.4 Visualization

Pseudoprobability Functions

qfunc (*state*, *xvec*, *yvec*, *g*=1.4142135623730951)

Q-function of a given state vector or density matrix at points xvec + i * yvec.

Parameters

state [qobj] A state vector or density matrix.

xvec [array_like] x-coordinates at which to calculate the Wigner function.

yvec [array_like] y-coordinates at which to calculate the Wigner function.

g [float] Scaling factor for a = 0.5 * g * (x + iy), default g = sqrt(2).

Returns

Q [array] Values representing the Q-function calculated over the specified range [xvec,yvec].

spin_q_function (rho, theta, phi)

Husimi Q-function for spins.

Parameters

state [qobj] A state vector or density matrix for a spin-j quantum system.

theta [array_like] theta-coordinates at which to calculate the Q function.

phi [array_like] phi-coordinates at which to calculate the Q function.

Returns

Q, **THETA**, **PHI** [2d-array] Values representing the spin Q function at the values specified by THETA and PHI.

spin_wigner(rho, theta, phi)

Wigner function for spins on the Bloch sphere.

Parameters

state [qobj] A state vector or density matrix for a spin-j quantum system.

theta [array_like] theta-coordinates at which to calculate the Q function.

phi [array_like] phi-coordinates at which to calculate the Q function.

Returns

W, THETA, PHI [2d-array] Values representing the spin Wigner function at the values specified by THETA and PHI.

Notes

Experimental.

wigner (*psi*, *xvec*, *yvec*, *method='clenshaw'*, g=1.4142135623730951, *sparse=False*, *parfor=False*) Wigner function for a state vector or density matrix at points xvec + i * yvec.

Parameters

state [qobj] A state vector or density matrix.

xvec [array_like] x-coordinates at which to calculate the Wigner function.

yvec [array_like] y-coordinates at which to calculate the Wigner function. Does not apply to the 'fft' method.

g [float] Scaling factor for a = 0.5 * g * (x + iy), default g = sqrt(2).

- **method** [string { 'clenshaw', 'iterative', 'laguerre', 'fft' }] Select method 'clenshaw' 'iterative', 'laguerre', or 'fft', where 'clenshaw' and 'iterative' use an iterative method to evaluate the Wigner functions for density matrices |m > < n|, while 'laguerre' uses the Laguerre polynomials in scipy for the same task. The 'fft' method evaluates the Fourier transform of the density matrix. The 'iterative' method is default, and in general recommended, but the 'laguerre' method is more efficient for very sparse density matrices (e.g., superpositions of Fock states in a large Hilbert space). The 'clenshaw' method is the preferred method for dealing with density matrices that have a large number of excitations (>~50). 'clenshaw' is a fast and numerically stable method.
- **sparse** [bool {False, True}] Tells the default solver whether or not to keep the input density matrix in sparse format. As the dimensions of the density matrix grow, setthing this flag can result in increased performance.
- **parfor** [bool {False, True}] Flag for calculating the Laguerre polynomial based Wigner function method='laguerre' in parallel using the parfor function.

- W [array] Values representing the Wigner function calculated over the specified range [xvec,yvec].
- **yvex** [array] FFT ONLY. Returns the y-coordinate values calculated via the Fourier transform.

Notes

The 'fft' method accepts only an xvec input for the x-coordinate. The y-coordinates are calculated internally.

References

Ulf Leonhardt, Measuring the Quantum State of Light, (Cambridge University Press, 1997)

Graphs and Visualization

Functions for visualizing results of quantum dynamics simulations, visualizations of quantum states and processes.

hinton (*rho*, *xlabels=None*, *ylabels=None*, *title=None*, *ax=None*, *cmap=None*, *label_top=True*) Draws a Hinton diagram for visualizing a density matrix or superoperator.

Parameters

rho [qobj] Input density matrix or superoperator.

xlabels [list of strings or False] list of x labels

ylabels [list of strings or False] list of y labels

title [string] title of the plot (optional)

ax [a matplotlib axes instance] The axes context in which the plot will be drawn.

cmap [a matplotlib colormap instance] Color map to use when plotting.

label_top [bool] If True, x-axis labels will be placed on top, otherwise they will appear below the plot.

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

Raises

ValueError Input argument is not a quantum object.

matrix_histogram(M, xlabels=None, ylabels=None, title=None, limits=None, colorbar=True, fig=None, ax=None)

Draw a histogram for the matrix M, with the given x and y labels and title.

Parameters

M [Matrix of Qobj] The matrix to visualize

xlabels [list of strings] list of x labels

ylabels [list of strings] list of y labels

title [string] title of the plot (optional)

limits [list/array with two float numbers] The z-axis limits [min, max] (optional)

ax [a matplotlib axes instance] The axes context in which the plot will be drawn.

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

Raises

ValueError Input argument is not valid.

old=None)

Draw a histogram for the amplitudes of matrix M, using the argument of each element for coloring the bars, with the given x and y labels and title.

Parameters

M [Matrix of Qobj] The matrix to visualize

xlabels [list of strings] list of x labels

ylabels [list of strings] list of y labels

title [string] title of the plot (optional)

limits [list/array with two float numbers] The z-axis limits [min, max] (optional)

- **phase_limits** [list/array with two float numbers] The phase-axis (colorbar) limits [min, max] (optional)
- **ax** [a matplotlib axes instance] The axes context in which the plot will be drawn.

threshold: float (None) Threshold for when bars of smaller height should be transparent. If not set, all bars are colored according to the color map.

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

Raises

ValueError Input argument is not valid.

plot_energy_levels (H_list, N=0, labels=None, show_ylabels=False, figsize=(8, 12), fig=None,

ax=None)

Plot the energy level diagrams for a list of Hamiltonians. Include up to N energy levels. For each element in H_list, the energy levels diagram for the cummulative Hamiltonian $sum(H_list[0:n])$ is plotted, where n is the index of an element in H_list.

Parameters

H_list [List of Qobj]

A list of Hamiltonians.

labels [List of string] A list of labels for each Hamiltonian

- **show_ylabels** [Bool (default False)] Show y labels to the left of energy levels of the initial Hamiltonian.
- N [int] The number of energy levels to plot
- figsize [tuple (int,int)] The size of the figure (width, height).
- fig [a matplotlib Figure instance] The Figure canvas in which the plot will be drawn.
- **ax** [a matplotlib axes instance] The axes context in which the plot will be drawn.

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

Raises

ValueError Input argument is not valid.

Plot the Fock distribution for a density matrix (or ket) that describes an oscillator mode.

Parameters

rho [qutip.qobj.Qobj] The density matrix (or ket) of the state to visualize.

fig [a matplotlib Figure instance] The Figure canvas in which the plot will be drawn.

ax [a matplotlib axes instance] The axes context in which the plot will be drawn.

title [string] An optional title for the figure.

figsize [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

plot_wigner_fock_distribution (rho, fig=None, axes=None, figsize=(8, 4), cmap=None, alpha_max=7.5, colorbar=False, method='iterative', projection='2d')

Plot the Fock distribution and the Wigner function for a density matrix (or ket) that describes an oscillator mode.

Parameters

rho [qutip.qobj.Qobj] The density matrix (or ket) of the state to visualize.

fig [a matplotlib Figure instance] The Figure canvas in which the plot will be drawn.

axes [a list of two matplotlib axes instances] The axes context in which the plot will be drawn.

figsize [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

cmap [a matplotlib cmap instance] The colormap.

alpha_max [float] The span of the x and y coordinates (both [-alpha_max, alpha_max]).

- **colorbar** [bool] Whether (True) or not (False) a colorbar should be attached to the Wigner function graph.
- **method** [string {'iterative', 'laguerre', 'fft'}] The method used for calculating the wigner function. See the documentation for qutip.wigner for details.
- **projection: string {'2d', '3d'}** Specify whether the Wigner function is to be plotted as a contour graph ('2d') or surface plot ('3d').

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

Plot the the Wigner function for a density matrix (or ket) that describes an oscillator mode.

Parameters

rho [qutip.qobj.Qobj] The density matrix (or ket) of the state to visualize.

- fig [a matplotlib Figure instance] The Figure canvas in which the plot will be drawn.
- ax [a matplotlib axes instance] The axes context in which the plot will be drawn.
- **figsize** [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).
- cmap [a matplotlib cmap instance] The colormap.
- alpha_max [float] The span of the x and y coordinates (both [-alpha_max, alpha_max]).
- **colorbar** [bool] Whether (True) or not (False) a colorbar should be attached to the Wigner function graph.
- **method** [string {'clenshaw', 'iterative', 'laguerre', 'fft'}] The method used for calculating the wigner function. See the documentation for qutip.wigner for details.
- **projection: string {'2d', '3d'}** Specify whether the Wigner function is to be plotted as a contour graph ('2d') or surface plot ('3d').

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

sphereplot (*theta*, *phi*, *values*, *fig=None*, *ax=None*, *save=False*) Plots a matrix of values on a sphere

Parameters

theta [float] Angle with respect to z-axis

phi [float] Angle in x-y plane

values [array] Data set to be plotted

fig [a matplotlib Figure instance] The Figure canvas in which the plot will be drawn.

ax [a matplotlib axes instance] The axes context in which the plot will be drawn.

save [bool {False, True}] Whether to save the figure or not

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

plot_schmidt (ket, splitting=None, labels_iteration=(3, 2), theme='light', fig=None, ax=None, fig-

size = (6, 6)

Plotting scheme related to Schmidt decomposition. Converts a state into a matrix $(A_ij \rightarrow A_i^{j})$, where rows are first particles and columns - last.

See also: plot_qubism with how='before_after' for a similar plot.

Parameters

ket [Qobj] Pure state for plotting.

- **splitting** [int] Plot for a number of first particles versus the rest. If not given, it is (number of particles + 1) // 2.
- **theme** ['light' (default) or 'dark'] Set coloring theme for mapping complex values into colors. See: complex_array_to_rgb.

- **labels_iteration** [int or pair of ints (default (3,2))] Number of particles to be shown as tick labels, for first (vertical) and last (horizontal) particles, respectively.
- fig [a matplotlib figure instance] The figure canvas on which the plot will be drawn.
- ax [a matplotlib axis instance] The axis context in which the plot will be drawn.
- **figsize** [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

- fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

Qubism plot for pure states of many qudits. Works best for spin chains, especially with even number of particles of the same dimension. Allows to see entanglement between first 2*k particles and the rest.

More information:

J. Rodriguez-Laguna, P. Migdal, M. Ibanez Berganza, M. Lewenstein, G. Sierra, "Qubism: self-similar visualization of many-body wavefunctions", New J. Phys. 14 053028 (2012), arXiv:1112.3560, http://dx.doi.org/10.1088/1367-2630/14/5/053028 (open access)

Parameters

ket [Qobj] Pure state for plotting.

- **theme** ['light' (default) or 'dark'] Set coloring theme for mapping complex values into colors. See: complex_array_to_rgb.
- how ['pairs' (default), 'pairs_skewed' or 'before_after'] Type of Qubism plotting. Options:

'pairs' - typical coordinates, 'pairs_skewed' - for ferromagnetic/antriferromagnetic plots, 'before_after' - related to Schmidt plot (see also: plot_schmidt).

- grid_iteration [int (default 1)] Helper lines to be drawn on plot. Show tiles for 2*grid_iteration particles vs all others.
- **legend_iteration** [int (default 0) or 'grid_iteration' or 'all'] Show labels for first 2*legend_iteration particles. Option 'grid_iteration' sets the same number of particles

as for grid_iteration.

- Option 'all' makes label for all particles. Typically it should be 0, 1, 2 or perhaps 3.
- fig [a matplotlib figure instance] The figure canvas on which the plot will be drawn.
- ax [a matplotlib axis instance] The axis context in which the plot will be drawn.
- **figsize** [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

Visualize the results (expectation values) for an evolution solver. *results* is assumed to be an instance of Result, or a list of Result instances.

Parameters

results [(list of) *qutip.solver.Result*] List of results objects returned by any of the QuTiP evolution solvers.

ylabels [list of strings] The y-axis labels. List should be of the same length as results.

title [string] The title of the figure.

show_legend [bool] Whether or not to show the legend.

fig [a matplotlib Figure instance] The Figure canvas in which the plot will be drawn.

axes [a matplotlib axes instance] The axes context in which the plot will be drawn.

figsize [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

plot_spin_distribution_2d (P, THETA, PHI, fig=None, ax=None, figsize=(8, 8))

Plot a spin distribution function (given as meshgrid data) with a 2D projection where the surface of the unit sphere is mapped on the unit disk.

Parameters

P [matrix] Distribution values as a meshgrid matrix.

THETA [matrix] Meshgrid matrix for the theta coordinate.

PHI [matrix] Meshgrid matrix for the phi coordinate.

fig [a matplotlib figure instance] The figure canvas on which the plot will be drawn.

ax [a matplotlib axis instance] The axis context in which the plot will be drawn.

figsize [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

plot_spin_distribution_3d(P, THETA, PHI, fig=None, ax=None, figsize=(8, 6))
Plots a matrix of values on a sphere

Parameters

P [matrix] Distribution values as a meshgrid matrix.

THETA [matrix] Meshgrid matrix for the theta coordinate.

PHI [matrix] Meshgrid matrix for the phi coordinate.

fig [a matplotlib figure instance] The figure canvas on which the plot will be drawn.

ax [a matplotlib axis instance] The axis context in which the plot will be drawn.

figsize [(width, height)] The size of the matplotlib figure (in inches) if it is to be created (that is, if no 'fig' and 'ax' arguments are passed).

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

orbital (theta, phi, *args)

Calculates an angular wave function on a sphere. psi = orbital (theta, phi, ket1, ket2, ...) calculates the angular wave function on a sphere at the mesh of points defined by theta and phi which is $\sum_{lm} c_{lm} Y_{lm}(theta, phi)$ where C_{lm} are the coefficients specified by the list of kets. Each ket has 2l+1 components for some integer l.

Parameters

theta [list/array] Polar angles

phi [list/array] Azimuthal angles

args [list/array] list of ket vectors.

Returns

array for angular wave function

Quantum Process Tomography

qpt (U, op_basis_list)

Calculate the quantum process tomography chi matrix for a given (possibly nonunitary) transformation matrix U, which transforms a density matrix in vector form according to:

vec(rho) = U * vec(rho0)

or

rho = vec2mat(U * mat2vec(rho0))

U can be calculated for an open quantum system using the QuTiP propagator function.

Parameters

U [Qobj] Transformation operator. Can be calculated using QuTiP propagator function.

op_basis_list [list] A list of Qobj's representing the basis states.

Returns

chi [array] QPT chi matrix

qpt_plot (chi, lbls_list, title=None, fig=None, axes=None)

Visualize the quantum process tomography chi matrix. Plot the real and imaginary parts separately.

Parameters

chi [array] Input QPT chi matrix.

lbls_list [list] List of labels for QPT plot axes.

title [string] Plot title.

fig [figure instance] User defined figure instance used for generating QPT plot.

axes [list of figure axis instance] User defined figure axis instance (list of two axes) used for generating QPT plot.

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

qpt_plot_combined (chi, lbls_list, title=None, fig=None, ax=None, figsize=(8, 6), threshold=None)
Visualize the quantum process tomography chi matrix. Plot bars with height and color corresponding to the
absolute value and phase, respectively.

Parameters

chi [array] Input QPT chi matrix.

lbls_list [list] List of labels for QPT plot axes.

title [string] Plot title.

- fig [figure instance] User defined figure instance used for generating QPT plot.
- **ax** [figure axis instance] User defined figure axis instance used for generating QPT plot (alternative to the fig argument).
- **threshold: float (None)** Threshold for when bars of smaller height should be transparent. If not set, all bars are colored according to the color map.

Returns

fig, ax [tuple] A tuple of the matplotlib figure and axes instances used to produce the figure.

4.2.5 Quantum Information Processing

Gates

rx (*phi*, *N*=None, *target*=0)

Single-qubit rotation for operator sigmax with angle phi.

Returns

result [qobj] Quantum object for operator describing the rotation.

ry (*phi*, *N*=*None*, *target*=0)

Single-qubit rotation for operator sigmay with angle phi.

Returns

result [qobj] Quantum object for operator describing the rotation.

rz (*phi*, *N*=*None*, *target*=0)

Single-qubit rotation for operator sigmaz with angle phi.

Returns

result [qobj] Quantum object for operator describing the rotation.

sqrtnot (N=None, target=0)

Single-qubit square root NOT gate.

Returns

result [qobj] Quantum object for operator describing the square root NOT gate.

snot (N=None, target=0)

Quantum object representing the SNOT (Hadamard) gate.

Returns

snot_gate [qobj] Quantum object representation of SNOT gate.

Examples

```
>>> snot()
Quantum object: dims = [[2], [2]], shape = [2, 2], type = oper, isHerm = True
Qobj data =
[[ 0.70710678+0.j 0.70710678+0.j]
[ 0.70710678+0.j -0.70710678+0.j]]
```

phasegate(theta, N=None, target=0)

Returns quantum object representing the phase shift gate.

Parameters

theta [float] Phase rotation angle.

Returns

phase_gate [qobj] Quantum object representation of phase shift gate.

Examples

```
>>> phasegate(pi/4)
Quantum object: dims = [[2], [2]], shape = [2, 2], type = oper, isHerm = False
Qobj data =
[[ 1.00000000+0.j 0.0000000+0.j ]
[ 0.00000000+0.j 0.70710678+0.70710678j]]
```

cphase (*theta*, *N*=2, *control*=0, *target*=1)

Returns quantum object representing the controlled phase shift gate.

Parameters

theta [float] Phase rotation angle.

N [integer] The number of qubits in the target space.

control [integer] The index of the control qubit.

target [integer] The index of the target qubit.

Returns

U [qobj] Quantum object representation of controlled phase gate.

```
cnot (N=None, control=0, target=1)
```

Quantum object representing the CNOT gate.

Returns

cnot_gate [qobj] Quantum object representation of CNOT gate

Examples

csign (N=None, control=0, target=1)

Quantum object representing the CSIGN gate.

Returns

csign_gate [qobj] Quantum object representation of CSIGN gate

Examples

berkeley (*N*=*None*, *targets*=[0, 1])

Quantum object representing the Berkeley gate.

Returns

berkeley_gate [qobj] Quantum object representation of Berkeley gate

Examples

swapalpha (alpha, N=None, targets=[0, 1])

Quantum object representing the SWAPalpha gate.

Returns

swapalpha_gate [qobj] Quantum object representation of SWAPalpha gate

Examples

```
>>> swapalpha(alpha)
Quantum object: dims = [[2, 2], [2, 2]], shape = [4, 4], type = oper, isHerm =_
⇔True
Qobj data =
                                     0.+0.j
[[ 1.+0.j 0.+0.j
                                                                0.+0.j]
[0.+0.j 0.5*(1 + exp(j*pi*alpha))]
                                     0.5*(1 - exp(j*pi*alpha)
                                                                0.+0.jl
[ 0.+0.j 0.5*(1 - exp(j*pi*alpha)
                                     0.5*(1 + \exp(j*pi*alpha))
                                                                0.+0.j]
[ 0.+0.j 0.+0.j
                                     0.+0.j
                                                                1.+0.j]]
```

swap (N=None, targets=[0, 1])

Quantum object representing the SWAP gate.

Returns

swap_gate [qobj] Quantum object representation of SWAP gate

Examples

iswap(N=None, targets=[0, 1])

Quantum object representing the iSWAP gate.

Returns

iswap_gate [qobj] Quantum object representation of iSWAP gate

Examples

```
>>> iswap()
Quantum object: dims = [[2, 2], [2, 2]], shape = [4, 4], type = oper, isHerm =_
→False
```

(continues on next page)

(continued from previous page)

```
Qobj data =
[[ 1.+0.j 0.+0.j 0.+0.j 0.+0.j]
[ 0.+0.j 0.+0.j 0.+1.j 0.+0.j]
[ 0.+0.j 0.+1.j 0.+0.j 0.+0.j]
[ 0.+0.j 0.+0.j 0.+0.j 1.+0.j]]
```

sqrtswap(N=None, targets=[0, 1])

Quantum object representing the square root SWAP gate.

Returns

sqrtswap_gate [qobj] Quantum object representation of square root SWAP gate

sqrtiswap(N=None, targets=[0, 1])

Quantum object representing the square root iSWAP gate.

Returns

sqrtiswap_gate [qobj] Quantum object representation of square root iSWAP gate

Examples

```
>>> sqrtiswap()
Quantum object: dims = [[2, 2], [2, 2]], shape = [4, 4], type = oper, isHerm =_
←False
Qobj data =
[[ 1.0000000+0.j 0.0000000+0.j
                                          0.00000000+0.j
                                                                  0.
↔0000000+0.j]
                                          0.0000000-0.70710678j 0.
[ 0.0000000+0.j
                  0.70710678+0.j
→00000000+0.j]
[ 0.0000000+0.j
                   0.00000000-0.70710678j
                                               0.70710678+0.j
                                                                       0.
→00000000+0.j]
[ 0.0000000+0.j
                   0.00000000+0.j
                                          0.00000000+0.j
                                                                  1.
→0000000+0.j]]
```

```
fredkin (N=None, control=0, targets=[1, 2])
Quantum object representing the Fredkin gate.
```

Returns

fredkin_gate [qobj] Quantum object representation of Fredkin gate.

Examples

```
>>> fredkin()
Quantum object: dims = [[2, 2, 2], [2, 2, 2]], shape = [8, 8], type = oper,
⊶isHerm = True
Qobj data =
   [[1.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j]
    [ 0.+0.j 1.+0.j 0.+0.j 0.+0.j 0.+0.j
                                          0.+0.j
                                                 0.+0.j
                                                        0.+0.j]
    [ 0.+0.j 0.+0.j 1.+0.j 0.+0.j 0.+0.j
                                          0.+0.j
                                                 0.+0.j
                                                         0.+0.j]
    [ 0.+0.j 0.+0.j 0.+0.j 1.+0.j 0.+0.j
                                          0.+0.j 0.+0.j
                                                        0.+0.j]
    [0.+0.j 0.+0.j 0.+0.j 0.+0.j 1.+0.j 0.+0.j 0.+0.j 0.+0.j]
    [0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 1.+0.j 0.+0.j]
    [0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 1.+0.j 0.+0.j]
    [0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 1.+0.j]]
```

```
toffoli (N=None, controls=[0, 1], target=2)
Quantum object representing the Toffoli gate.
```

Returns

toff_gate [qobj] Quantum object representation of Toffoli gate.

Examples

```
>>> toffoli()
Quantum object: dims = [[2, 2, 2], [2, 2, 2]], shape = [8, 8], type = oper,
⇔isHerm = True
Qobj data =
   [[ 1.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j]
    [0.+0.j 1.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j]
    [0.+0.j 0.+0.j 1.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j]
    [0.+0.j 0.+0.j 0.+0.j 1.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j]
    [ 0.+0.j 0.+0.j 0.+0.j 0.+0.j 1.+0.j 0.+0.j 0.+0.j 0.+0.j]
    [ 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j
                                          1.+0.j 0.+0.j 0.+0.j]
    [ 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j 0.+0.j
                                                 0.+0.j 1.+0.j]
    [ 0.+0.j 0.+0.j
                    0.+0.j 0.+0.j 0.+0.j 0.+0.j
                                                  1.+0.j 0.+0.j]]
```

rotation (op, phi, N=None, target=0)

Single-qubit rotation for operator op with angle phi.

Returns

result [qobj] Quantum object for operator describing the rotation.

controlled_gate (*U*, *N*=2, *control*=0, *target*=1, *control_value*=1)

Create an N-qubit controlled gate from a single-qubit gate U with the given control and target qubits.

Parameters

U [Qobj] Arbitrary single-qubit gate.

N [integer] The number of qubits in the target space.

control [integer] The index of the first control qubit.

target [integer] The index of the target qubit.

control_value [integer (1)] The state of the control qubit that activates the gate U.

Returns

result [qobj] Quantum object representing the controlled-U gate.

globalphase (*theta*, N=1)

Returns quantum object representing the global phase shift gate.

Parameters

theta [float] Phase rotation angle.

Returns

phase_gate [qobj] Quantum object representation of global phase shift gate.

Examples

$hadamard_transform(N=1)$

Quantum object representing the N-qubit Hadamard gate.

Returns

q [qobj] Quantum object representation of the N-qubit Hadamard gate.

gate_sequence_product (U_list, left_to_right=True)

Calculate the overall unitary matrix for a given list of unitary operations

Parameters

U_list [list] List of gates implementing the quantum circuit.

left_to_right [Boolean] Check if multiplication is to be done from left to right.

Returns

U_overall [qobj] Overall unitary matrix of a given quantum circuit.

gate_expand_ltoN(U, N, target)

Create a Qobj representing a one-qubit gate that act on a system with N qubits.

Parameters

U [Qobj] The one-qubit gate

N [integer] The number of qubits in the target space.

target [integer] The index of the target qubit.

Returns

gate [qobj] Quantum object representation of N-qubit gate.

gate_expand_2toN (U, N, control=None, target=None, targets=None)
Create a Qobj representing a two-qubit gate that act on a system with N qubits.

Parameters

U [Qobj] The two-qubit gate

N [integer] The number of qubits in the target space.

control [integer] The index of the control qubit.

target [integer] The index of the target qubit.

targets [list] List of target qubits.

Returns

gate [qobj] Quantum object representation of N-qubit gate.

gate_expand_3toN (U, N, controls=[0, 1], target=2)

Create a Qobj representing a three-qubit gate that act on a system with N qubits.

Parameters

U [Qobj] The three-qubit gate

N [integer] The number of qubits in the target space.

controls [list] The list of the control qubits.

target [integer] The index of the target qubit.

Returns

gate [qobj] Quantum object representation of N-qubit gate.

Qubits

qubit_states(N=1, states=[0])

Function to define initial state of the qubits.

Parameters

N [Integer] Number of qubits in the register.

states [List] Initial state of each qubit.

Returns

qstates [Qobj] List of qubits.

Algorithms

This module provides the circuit implementation for Quantum Fourier Transform.

qft (N=1)

Quantum Fourier Transform operator on N qubits.

Parameters

N [int] Number of qubits.

Returns

QFT: qobj Quantum Fourier transform operator.

qft_steps (N=1, swapping=True)

Quantum Fourier Transform operator on N qubits returning the individual steps as unitary matrices operating from left to right.

Parameters

N: int Number of qubits.

swap: boolean Flag indicating sequence of swap gates to be applied at the end or not.

Returns

U_step_list: list of qobj List of Hadamard and controlled rotation gates implementing QFT.

qft_gate_sequence(N=1, swapping=True)

Quantum Fourier Transform operator on N qubits returning the gate sequence.

Parameters

N: int Number of qubits.

swap: boolean Flag indicating sequence of swap gates to be applied at the end or not.

Returns

qc: instance of QubitCircuit Gate sequence of Hadamard and controlled rotation gates implementing QFT.

4.2.6 Non-Markovian Solvers

This module contains an implementation of the non-Markovian transfer tensor method (TTM), introduced in [1].

[1] Javier Cerrillo and Jianshu Cao, Phys. Rev. Lett 112, 110401 (2014)

ttmsolve (*dynmaps*, *rho0*, *times*, *e_ops=[]*, *learningtimes=None*, *tensors=None*, ***kwargs*) Solve time-evolution using the Transfer Tensor Method, based on a set of precomputed dynamical maps.

Parameters

dynmaps [list of *qutip.Qobj*] List of precomputed dynamical maps (superoperators), or a callback function that returns the superoperator at a given time.

rho0 [qutip.Qobj] Initial density matrix or state vector (ket).

times [array_like] list of times t_n at which to compute $\rho(t_n)$. Must be uniformily spaced.

- **e_ops** [list of *qutip.Qobj* / callback function] single operator or list of operators for which to evaluate expectation values.
- **learningtimes** [array_like] list of times t_k for which we have knowledge of the dynamical maps $E(t_k)$.
- **tensors** [array_like] optional list of precomputed tensors T_k
- kwargs [dictionary] Optional keyword arguments. See qutip.nonmarkov.ttm. TTMSolverOptions.

output: qutip.solver.Result An instance of the class qutip.solver.Result.

4.2.7 Optimal control

Wrapper functions that will manage the creation of the objects, build the configuration, and execute the algorithm required to optimise a set of ctrl pulses for a given (quantum) system. The fidelity error is some measure of distance of the system evolution from the given target evolution in the time allowed for the evolution. The functions minimise this fidelity error wrt the piecewise control amplitudes in the timeslots

There are currently two quantum control pulse optimisations algorithms implemented in this library. There are accessible through the methods in this module. Both the algorithms use the scipy.optimize methods to minimise the fidelity error with respect to to variables that define the pulse.

GRAPE

The default algorithm (as it was implemented here first) is GRAPE GRadient Ascent Pulse Engineering [1][2]. It uses a gradient based method such as BFGS to minimise the fidelity error. This makes convergence very quick when an exact gradient can be calculated, but this limits the factors that can taken into account in the fidelity.

CRAB

The CRAB [3][4] algorithm was developed at the University of Ulm. In full it is the Chopped RAndom Basis algorithm. The main difference is that it reduces the number of optimisation variables by defining the control pulses by expansions of basis functions, where the variables are the coefficients. Typically a Fourier series is chosen, i.e. the variables are the Fourier coefficients. Therefore it does not need to compute an explicit gradient. By default it uses the Nelder-Mead method for fidelity error minimisation.

References

- 1. N Khaneja et. al. Optimal control of coupled spin dynamics: Design of NMR pulse sequences by gradient ascent algorithms. J. Magn. Reson. 172, 296–305 (2005).
- 2. Shai Machnes et.al DYNAMO Dynamic Framework for Quantum Optimal Control arXiv.1011.4874
- 3. Doria, P., Calarco, T. & Montangero, S. Optimal Control Technique for Many-Body Quantum Dynamics. Phys. Rev. Lett. 106, 1–4 (2011).
- 4. Caneva, T., Calarco, T. & Montangero, S. Chopped random-basis quantum optimization. Phys. Rev. A At. Mol. Opt. Phys. 84, (2011).

optimize_pulse(drift, ctrls, initial, target, num_tslots=None, evo_time=None, tau=None, $amp_lbound=None, \quad amp_ubound=None, \quad fid_err_targ=1e-10, \quad min_grad=1e-10, \quad min_grad=10, \quad min_gra$ 10, max_iter=500, max_wall_time=180, alg='GRAPE', alg_params=None, optim_method='DEF', optim_params=None, method_params=None, optim_alg=None, max metric corr=None, accuracy factor=None, dyn type='GEN MAT', dyn params=None, prop_type='DEF', prop_params=None, fid_type='DEF', fid_params=None, phase_option=None, fid err scale factor=None, tslot_type='DEF', tslot params=None, *init_pulse_type='DEF'*, *amp update mode=None*, init pulse params=None, pulse scaling=1.0, *pulse_offset=0.0*, ramping_pulse_type=None, ramping_pulse_params=None, log_level=0, out_file_ext=None, gen_stats=False)

Optimise a control pulse to minimise the fidelity error. The dynamics of the system in any given timeslot are governed by the combined dynamics generator, i.e. the sum of the drift+ctrl_amp[j]*ctrls[j] The control pulse is an [n_ts, n_ctrls)] array of piecewise amplitudes Starting from an initial (typically random) pulse, a multivariable optimisation algorithm attempts to determines the optimal values for the control pulse to minimise the fidelity error is some measure of distance of the system evolution from the given target evolution in the time allowed for the evolution.

Parameters

- **drift** [Qobj or list of Qobj] the underlying dynamics generator of the system can provide list (of length num_tslots) for time dependent drift
- **ctrls** [List of Qobj or array like [num_tslots, evo_time]] a list of control dynamics generators. These are scaled by the amplitudes to alter the overall dynamics Array like imput can be provided for time dependent control generators
- initial [Qobj] starting point for the evolution. Typically the identity matrix
- target [Qobj] target transformation, e.g. gate or state, for the time evolution
- **num_tslots** [integer or None] number of timeslots. None implies that timeslots will be given in the tau array
- evo_time [float or None] total time for the evolution None implies that timeslots will be given in the tau array
- **tau** [array[num_tslots] of floats or None] durations for the timeslots. if this is given then num_tslots and evo_time are dervived from it None implies that timeslot durations will be equal and calculated as evo_time/num_tslots
- **amp_lbound** [float or list of floats] lower boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control
- **amp_ubound** [float or list of floats] upper boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control
- fid_err_targ [float] Fidelity error target. Pulse optimisation will terminate when the fidelity error falls below this value
- **mim_grad** [float] Minimum gradient. When the sum of the squares of the gradients wrt to the control amplitudes falls below this value, the optimisation terminates, assuming local minima
- max_iter [integer] Maximum number of iterations of the optimisation algorithm
- max_wall_time [float] Maximum allowed elapsed time for the optimisation algorithm
- alg [string] Algorithm to use in pulse optimisation. Options are:
 - 'GRAPE' (default) GRadient Ascent Pulse Engineering 'CRAB' Chopped RAndom Basis
- alg_params [Dictionary] options that are specific to the algorithm see above

- **optim_params** [Dictionary] The key value pairs are the attribute name and value used to set attribute values Note: attributes are created if they do not exist already, and are overwritten if they do. Note: method_params are applied afterwards and so may override these
- **optim_method** [string] a scipy.optimize.minimize method that will be used to optimise the pulse for minimum fidelity error Note that FMIN, FMIN_BFGS & FMIN_L_BFGS_B will all result in calling these specific scipy.optimize methods Note the LBFGSB is equivalent to FMIN_L_BFGS_B for backwards capatibility reasons. Supplying DEF will given alg dependent result:

<code>GRAPE</code> - <code>Default</code> <code>optim_method</code> is <code>FMIN_L_BFGS_B</code> <code>CRAB</code> - <code>Default</code> <code>optim_method</code> is <code>FMIN</code>

- **method_params** [dict] Parameters for the optim_method. Note that where there is an attribute of the Optimizer object or the termination_conditions matching the key that attribute. Otherwise, and in some case also, they are assumed to be method_options for the scipy.optimize.minimize method.
- optim_alg [string] Deprecated. Use optim_method.
- max_metric_corr [integer] Deprecated. Use method_params instead
- accuracy_factor [float] Deprecated. Use method_params instead
- **dyn_type** [string] Dynamics type, i.e. the type of matrix used to describe the dynamics. Options are UNIT, GEN_MAT, SYMPL (see Dynamics classes for details)
- **dyn_params** [dict] Parameters for the Dynamics object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- prop_type [string] Propagator type i.e. the method used to calculate the propagtors and propagtor gradient for each timeslot options are DEF, APPROX, DIAG, FRECHET, AUG_MAT DEF will use the default for the specific dyn_type (see PropagatorComputer classes for details)
- **prop_params** [dict] Parameters for the PropagatorComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- fid_type [string] Fidelity error (and fidelity error gradient) computation method Options are DEF, UNIT, TRACEDIFF, TD_APPROX DEF will use the default for the specific dyn_type (See FidelityComputer classes for details)
- **fid_params** [dict] Parameters for the FidelityComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- phase_option [string] Deprecated. Pass in fid_params instead.
- fid_err_scale_factor [float] Deprecated. Use scale_factor key in fid_params instead.
- **tslot_type** [string] Method for computing the dynamics generators, propagators and evolution in the timeslots. Options: DEF, UPDATE_ALL, DYNAMIC UPDATE_ALL is the only one that currently works (See TimeslotComputer classes for details)
- **tslot_params** [dict] Parameters for the TimeslotComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **amp_update_mode** [string] Deprecated. Use tslot_type instead.
- **init_pulse_type** [string] type / shape of pulse(s) used to initialise the the control amplitudes. Options (GRAPE) include:

RND, LIN, ZERO, SINE, SQUARE, TRIANGLE, SAW

DEF is RND (see PulseGen classes for details) For the CRAB the this the guess_pulse_type.

- **init_pulse_params** [dict] Parameters for the initial / guess pulse generator object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **pulse_scaling** [float] Linear scale factor for generated initial / guess pulses By default initial pulses are generated with amplitudes in the range (-1.0, 1.0). These will be scaled by this parameter
- **pulse_offset** [float] Linear offset for the pulse. That is this value will be added to any initial / guess pulses generated.
- **ramping_pulse_type** [string] Type of pulse used to modulate the control pulse. It's intended use for a ramping modulation, which is often required in experimental setups. This is only currently implemented in CRAB. GAUSSIAN_EDGE was added for this purpose.
- **ramping_pulse_params** [dict] Parameters for the ramping pulse generator object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **log_level** [integer] level of messaging output from the logger. Options are attributes of qutip.logging_utils, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN
- **out_file_ext** [string or None] files containing the initial and final control pulse amplitudes are saved to the current directory. The default name will be postfixed with this extension Setting this to None will suppress the output of files
- **gen_stats** [boolean] if set to True then statistics for the optimisation run will be generated accessible through attributes of the stats object

- **opt** [OptimResult] Returns instance of OptimResult, which has attributes giving the reason for termination, final fidelity error, final evolution final amplitudes, statistics etc
- optimize_pulse_unitary (H_d, H_c, U_0, U_targ, num_tslots=None, evo_time=None, tau=None, amp_lbound=None, amp_ubound=None, fid_err_targ=1e-10, min_grad=1e-10, max_iter=500, max_wall_time=180, alg='GRAPE', *alg_params=None*, optim_params=None, optim_method='DEF', *method params=None*, optim alg=None, max metric corr=None, accuracy_factor=None, phase_option='PSU', dyn_params=None, prop_params=None, fid_params=None, tslot_type='DEF', tslot_params=None, amp_update_mode=None, init_pulse_type='DEF', init pulse params=None, pulse scaling=1.0, pulse offset=0.0, ramping_pulse_type=None, ramping_pulse_params=None, log_level=0, out_file_ext=None, gen_stats=False)

Optimise a control pulse to minimise the fidelity error, assuming that the dynamics of the system are generated by unitary operators. This function is simply a wrapper for optimize_pulse, where the appropriate options for unitary dynamics are chosen and the parameter names are in the format familiar to unitary dynamics. The dynamics of the system in any given timeslot are governed by the combined Hamiltonian, i.e. the sum of the $H_d + ctrl_amp[j]*H_c[j]$ The control pulse is an $[n_ts, n_ctrls]$ array of piecewise amplitudes Starting from an initial (typically random) pulse, a multivariable optimisation algorithm attempts to determines the optimal values for the control pulse to minimise the fidelity error. The maximum fidelity for a unitary system is 1, i.e. when the time evolution resulting from the pulse is equivalent to the target. And therefore the fidelity error is 1 - fidelity

Parameters

H_d [Qobj or list of Qobj] Drift (aka system) the underlying Hamiltonian of the system can provide list (of length num_tslots) for time dependent drift

- **H_c** [List of Qobj or array like [num_tslots, evo_time]] a list of control Hamiltonians. These are scaled by the amplitudes to alter the overall dynamics Array like imput can be provided for time dependent control generators
- **U_0** [Qobj] starting point for the evolution. Typically the identity matrix
- U_targ [Qobj] target transformation, e.g. gate or state, for the time evolution
- num_tslots [integer or None] number of timeslots. None implies that timeslots will be given in the tau array
- evo_time [float or None] total time for the evolution None implies that timeslots will be given in the tau array
- **tau** [array[num_tslots] of floats or None] durations for the timeslots. if this is given then num_tslots and evo_time are dervived from it None implies that timeslot durations will be equal and calculated as evo_time/num_tslots
- **amp_lbound** [float or list of floats] lower boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control
- **amp_ubound** [float or list of floats] upper boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control
- fid_err_targ [float] Fidelity error target. Pulse optimisation will terminate when the fidelity error falls below this value
- mim_grad [float] Minimum gradient. When the sum of the squares of the gradients wrt to the control amplitudes falls below this value, the optimisation terminates, assuming local minima
- max_iter [integer] Maximum number of iterations of the optimisation algorithm
- max_wall_time [float] Maximum allowed elapsed time for the optimisation algorithm
- alg [string] Algorithm to use in pulse optimisation. Options are:

'GRAPE' (default) - GRadient Ascent Pulse Engineering 'CRAB' - Chopped RAndom Basis

- alg_params [Dictionary] options that are specific to the algorithm see above
- **optim_params** [Dictionary] The key value pairs are the attribute name and value used to set attribute values Note: attributes are created if they do not exist already, and are overwritten if they do. Note: method_params are applied afterwards and so may override these
- **optim_method** [string] a scipy.optimize.minimize method that will be used to optimise the pulse for minimum fidelity error Note that FMIN, FMIN_BFGS & FMIN_L_BFGS_B will all result in calling these specific scipy.optimize methods Note the LBFGSB is equivalent to FMIN_L_BFGS_B for backwards capatibility reasons. Supplying DEF will given alg dependent result:

<code>GRAPE</code> - <code>Default</code> <code>optim_method</code> is <code>FMIN_L_BFGS_B</code> <code>CRAB</code> - <code>Default</code> <code>optim_method</code> is <code>FMIN</code>

method_params [dict] Parameters for the optim_method. Note that where there is an attribute of the Optimizer object or the termination_conditions matching the key that attribute. Otherwise, and in some case also, they are assumed to be method_options for the scipy.optimize.minimize method.

optim_alg [string] Deprecated. Use optim_method.

max_metric_corr [integer] Deprecated. Use method_params instead

accuracy_factor [float] Deprecated. Use method_params instead

phase_option [string] determines how global phase is treated in fidelity calculations
 (fid_type='UNIT' only). Options:

PSU - global phase ignored SU - global phase included

- **dyn_params** [dict] Parameters for the Dynamics object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **prop_params** [dict] Parameters for the PropagatorComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **fid_params** [dict] Parameters for the FidelityComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **tslot_type** [string] Method for computing the dynamics generators, propagators and evolution in the timeslots. Options: DEF, UPDATE_ALL, DYNAMIC UPDATE_ALL is the only one that currently works (See TimeslotComputer classes for details)
- **tslot_params** [dict] Parameters for the TimeslotComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- amp_update_mode [string] Deprecated. Use tslot_type instead.
- **init_pulse_type** [string] type / shape of pulse(s) used to initialise the control amplitudes. Options (GRAPE) include:

RND, LIN, ZERO, SINE, SQUARE, TRIANGLE, SAW DEF is RND

(see PulseGen classes for details) For the CRAB the this the guess_pulse_type.

- **init_pulse_params** [dict] Parameters for the initial / guess pulse generator object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **pulse_scaling** [float] Linear scale factor for generated initial / guess pulses By default initial pulses are generated with amplitudes in the range (-1.0, 1.0). These will be scaled by this parameter
- pulse_offset [float] Linear offset for the pulse. That is this value will be added to any initial
 / guess pulses generated.
- **ramping_pulse_type** [string] Type of pulse used to modulate the control pulse. It's intended use for a ramping modulation, which is often required in experimental setups. This is only currently implemented in CRAB. GAUSSIAN_EDGE was added for this purpose.
- ramping_pulse_params [dict] Parameters for the ramping pulse generator object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **log_level** [integer] level of messaging output from the logger. Options are attributes of qutip.logging_utils, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN
- **out_file_ext** [string or None] files containing the initial and final control pulse amplitudes are saved to the current directory. The default name will be postfixed with this extension Setting this to None will suppress the output of files
- **gen_stats** [boolean] if set to True then statistics for the optimisation run will be generated accessible through attributes of the stats object

Returns

opt [OptimResult] Returns instance of OptimResult, which has attributes giving the reason for termination, final fidelity error, final evolution final amplitudes, statistics etc

create_pulse_optimizer (*drift, ctrls, initial, target, num_tslots=None, evo_time=None, tau=None,* amp_lbound=None, *amp_ubound=None*, fid_err_targ=1e-10, min_grad=1e-10, max_iter=500, max_wall_time=180, alg='GRAPE', alg_params=None, optim_params=None, optim_method='DEF', method_params=None, optim_alg=None, max_metric_corr=None, accuracy factor=None, *dyn_type='GEN_MAT'*, *dyn_params=None*, prop_type='DEF', prop_params=None, fid type='DEF', fid params=None, phase option=None, fid err scale factor=None, *tslot_type='DEF', tslot_params=None,* amp_update_mode=None, init_pulse_type='DEF', init_pulse_params=None, pulse_scaling=1.0, pulse offset=0.0, ramping_pulse_type=None, ramping_pulse_params=None, log_level=0, gen_stats=False)

Generate the objects of the appropriate subclasses required for the pulse optmisation based on the parameters given Note this method may be preferable to calling optimize_pulse if more detailed configuration is required before running the optmisation algorithm, or the algorithm will be run many times, for instances when trying to finding global the optimum or minimum time optimisation

Parameters

- **drift** [Qobj or list of Qobj] the underlying dynamics generator of the system can provide list (of length num_tslots) for time dependent drift
- **ctrls** [List of Qobj or array like [num_tslots, evo_time]] a list of control dynamics generators. These are scaled by the amplitudes to alter the overall dynamics Array like imput can be provided for time dependent control generators
- initial [Qobj] starting point for the evolution. Typically the identity matrix
- target [Qobj] target transformation, e.g. gate or state, for the time evolution
- **num_tslots** [integer or None] number of timeslots. None implies that timeslots will be given in the tau array
- evo_time [float or None] total time for the evolution None implies that timeslots will be given in the tau array
- **tau** [array[num_tslots] of floats or None] durations for the timeslots. if this is given then num_tslots and evo_time are dervived from it None implies that timeslot durations will be equal and calculated as evo_time/num_tslots
- **amp_lbound** [float or list of floats] lower boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control
- **amp_ubound** [float or list of floats] upper boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control
- fid_err_targ [float] Fidelity error target. Pulse optimisation will terminate when the fidelity error falls below this value
- **mim_grad** [float] Minimum gradient. When the sum of the squares of the gradients wrt to the control amplitudes falls below this value, the optimisation terminates, assuming local minima
- max_iter [integer] Maximum number of iterations of the optimisation algorithm
- max_wall_time [float] Maximum allowed elapsed time for the optimisation algorithm
- alg [string] Algorithm to use in pulse optimisation. Options are:

'GRAPE' (default) - GRadient Ascent Pulse Engineering 'CRAB' - Chopped RAndom Basis

- alg_params [Dictionary] options that are specific to the algorithm see above
- **optim_params** [Dictionary] The key value pairs are the attribute name and value used to set attribute values Note: attributes are created if they do not exist already, and are over-

written if they do. Note: method_params are applied afterwards and so may override these

- **optim_method** [string] a scipy.optimize.minimize method that will be used to optimise the pulse for minimum fidelity error Note that FMIN, FMIN_BFGS & FMIN_L_BFGS_B will all result in calling these specific scipy.optimize methods Note the LBFGSB is equivalent to FMIN_L_BFGS_B for backwards capatibility reasons. Supplying DEF will given alg dependent result:
 - GRAPE Default optim_method is FMIN_L_BFGS_B
 - CRAB Default optim_method is Nelder-Mead
- **method_params** [dict] Parameters for the optim_method. Note that where there is an attribute of the Optimizer object or the termination_conditions matching the key that attribute. Otherwise, and in some case also, they are assumed to be method_options for the scipy.optimize.minimize method.
- optim_alg [string] Deprecated. Use optim_method.
- max_metric_corr [integer] Deprecated. Use method_params instead
- accuracy_factor [float] Deprecated. Use method_params instead
- **dyn_type** [string] Dynamics type, i.e. the type of matrix used to describe the dynamics. Options are UNIT, GEN_MAT, SYMPL (see Dynamics classes for details)
- **dyn_params** [dict] Parameters for the Dynamics object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- prop_type [string] Propagator type i.e. the method used to calculate the propagtors and propagtor gradient for each timeslot options are DEF, APPROX, DIAG, FRECHET, AUG_MAT DEF will use the default for the specific dyn_type (see PropagatorComputer classes for details)
- **prop_params** [dict] Parameters for the PropagatorComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **fid_type** [string] Fidelity error (and fidelity error gradient) computation method Options are DEF, UNIT, TRACEDIFF, TD_APPROX DEF will use the default for the specific dyn_type (See FidelityComputer classes for details)
- **fid_params** [dict] Parameters for the FidelityComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- phase_option [string] Deprecated. Pass in fid_params instead.
- fid_err_scale_factor [float] Deprecated. Use scale_factor key in fid_params instead.
- **tslot_type** [string] Method for computing the dynamics generators, propagators and evolution in the timeslots. Options: DEF, UPDATE_ALL, DYNAMIC UPDATE_ALL is the only one that currently works (See TimeslotComputer classes for details)
- **tslot_params** [dict] Parameters for the TimeslotComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- amp_update_mode [string] Deprecated. Use tslot_type instead.
- **init_pulse_type** [string] type / shape of pulse(s) used to initialise the control amplitudes. Options (GRAPE) include:

RND, LIN, ZERO, SINE, SQUARE, TRIANGLE, SAW DEF is RND

(see PulseGen classes for details) For the CRAB the this the guess_pulse_type.

init_pulse_params [dict] Parameters for the initial / guess pulse generator object The key value pairs are assumed to be attribute name value pairs They applied after the object is created

- **pulse_scaling** [float] Linear scale factor for generated initial / guess pulses By default initial pulses are generated with amplitudes in the range (-1.0, 1.0). These will be scaled by this parameter
- pulse_offset [float] Linear offset for the pulse. That is this value will be added to any initial
 / guess pulses generated.
- **ramping_pulse_type** [string] Type of pulse used to modulate the control pulse. It's intended use for a ramping modulation, which is often required in experimental setups. This is only currently implemented in CRAB. GAUSSIAN_EDGE was added for this purpose.
- ramping_pulse_params [dict] Parameters for the ramping pulse generator object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **log_level** [integer] level of messaging output from the logger. Options are attributes of qutip.logging_utils, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN
- **gen_stats** [boolean] if set to True then statistics for the optimisation run will be generated accessible through attributes of the stats object

opt [Optimizer] Instance of an Optimizer, through which the Config, Dynamics, PulseGen, and TerminationConditions objects can be accessed as attributes. The PropagatorComputer, FidelityComputer and TimeslotComputer objects can be accessed as attributes of the Dynamics object, e.g. optimizer.dynamics.fid_computer The optimisation can be run through the optimizer.run_optimization

opt_pulse_crab (*drift*, ctrls. initial, target, *num_tslots=None*, evo_time=None, tau=None, *amp_lbound=None*, amp ubound=None, fid_err_targ=1e-05, max_wall_time=180, max_iter=500, alg_params=None, num_coeffs=None, *init_coeff_scaling=1.0*, optim_params=None, optim_method='fmin', *method_params=None*, dyn_type='GEN_MAT', dyn_params=None, prop_type='DEF', prop_params=None, fid_type='DEF', fid_params=None, tslot_type='DEF', *tslot_params=None*, guess_pulse_type=None, guess_pulse_params=None, guess_pulse_scaling=1.0, guess_pulse_offset=0.0, guess pulse_action='MODULATE', ramping_pulse_type=None, ramping_pulse_params=None, log_level=0, out_file_ext=None, gen_stats=False)

Optimise a control pulse to minimise the fidelity error. The dynamics of the system in any given timeslot are governed by the combined dynamics generator, i.e. the sum of the drift+ctrl_amp[j]*ctrls[j] The control pulse is an [n_ts, n_ctrls] array of piecewise amplitudes. The CRAB algorithm uses basis function coefficents as the variables to optimise. It does NOT use any gradient function. A multivariable optimisation algorithm attempts to determines the optimal values for the control pulse to minimise the fidelity error The fidelity error is some measure of distance of the system evolution from the given target evolution in the time allowed for the evolution.

Parameters

- **drift** [Qobj or list of Qobj] the underlying dynamics generator of the system can provide list (of length num_tslots) for time dependent drift
- **ctrls** [List of Qobj or array like [num_tslots, evo_time]] a list of control dynamics generators. These are scaled by the amplitudes to alter the overall dynamics Array like imput can be provided for time dependent control generators
- initial [Qobj] starting point for the evolution. Typically the identity matrix
- target [Qobj] target transformation, e.g. gate or state, for the time evolution

- **num_tslots** [integer or None] number of timeslots. None implies that timeslots will be given in the tau array
- evo_time [float or None] total time for the evolution None implies that timeslots will be given in the tau array
- **tau** [array[num_tslots] of floats or None] durations for the timeslots. if this is given then num_tslots and evo_time are dervived from it None implies that timeslot durations will be equal and calculated as evo_time/num_tslots
- **amp_lbound** [float or list of floats] lower boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control
- **amp_ubound** [float or list of floats] upper boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control
- fid_err_targ [float] Fidelity error target. Pulse optimisation will terminate when the fidelity error falls below this value
- max_iter [integer] Maximum number of iterations of the optimisation algorithm
- max_wall_time [float] Maximum allowed elapsed time for the optimisation algorithm
- alg_params [Dictionary] options that are specific to the algorithm see above
- **optim_params** [Dictionary] The key value pairs are the attribute name and value used to set attribute values Note: attributes are created if they do not exist already, and are overwritten if they do. Note: method_params are applied afterwards and so may override these
- **coeff_scaling** [float] Linear scale factor for the random basis coefficients By default these range from -1.0 to 1.0 Note this is overridden by alg_params (if given there)
- num_coeffs [integer] Number of coefficients used for each basis function Note this is calculated automatically based on the dimension of the dynamics if not given. It is crucial to the performane of the algorithm that it is set as low as possible, while still giving high enough frequencies. Note this is overridden by alg_params (if given there)
- **optim_method** [string] Multi-variable optimisation method The only tested options are 'fmin' and 'Nelder-mead' In theory any non-gradient method implemented in scipy.optimize.mininize could be used.
- **method_params** [dict] Parameters for the optim_method. Note that where there is an attribute of the Optimizer object or the termination_conditions matching the key that attribute. Otherwise, and in some case also, they are assumed to be method_options for the scipy.optimize.minimize method. The commonly used parameter are:

xtol - limit on variable change for convergence ftol - limit on fidelity error change for convergence

- **dyn_type** [string] Dynamics type, i.e. the type of matrix used to describe the dynamics. Options are UNIT, GEN_MAT, SYMPL (see Dynamics classes for details)
- **dyn_params** [dict] Parameters for the Dynamics object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- prop_type [string] Propagator type i.e. the method used to calculate the propagtors and propagtor gradient for each timeslot options are DEF, APPROX, DIAG, FRECHET, AUG_MAT DEF will use the default for the specific dyn_type (see PropagatorComputer classes for details)
- **prop_params** [dict] Parameters for the PropagatorComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- fid_type [string] Fidelity error (and fidelity error gradient) computation method Options are DEF, UNIT, TRACEDIFF, TD_APPROX DEF will use the default for the specific dyn_type (See FidelityComputer classes for details)

- **fid_params** [dict] Parameters for the FidelityComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **tslot_type** [string] Method for computing the dynamics generators, propagators and evolution in the timeslots. Options: DEF, UPDATE_ALL, DYNAMIC UPDATE_ALL is the only one that currently works (See TimeslotComputer classes for details)
- **tslot_params** [dict] Parameters for the TimeslotComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **guess_pulse_type** [string] type / shape of pulse(s) used modulate the control amplitudes. Options include:

RND, LIN, ZERO, SINE, SQUARE, TRIANGLE, SAW, GAUSSIAN

Default is None

- **guess_pulse_params** [dict] Parameters for the guess pulse generator object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **guess_pulse_action** [string] Determines how the guess pulse is applied to the pulse generated by the basis expansion. Options are: MODULATE, ADD Default is MODULATE
- **pulse_scaling** [float] Linear scale factor for generated guess pulses By default initial pulses are generated with amplitudes in the range (-1.0, 1.0). These will be scaled by this parameter
- **pulse_offset** [float] Linear offset for the pulse. That is this value will be added to any guess pulses generated.
- **ramping_pulse_type** [string] Type of pulse used to modulate the control pulse. It's intended use for a ramping modulation, which is often required in experimental setups. This is only currently implemented in CRAB. GAUSSIAN_EDGE was added for this purpose.
- ramping_pulse_params [dict] Parameters for the ramping pulse generator object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **log_level** [integer] level of messaging output from the logger. Options are attributes of qutip.logging_utils, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN
- **out_file_ext** [string or None] files containing the initial and final control pulse amplitudes are saved to the current directory. The default name will be postfixed with this extension Setting this to None will suppress the output of files
- **gen_stats** [boolean] if set to True then statistics for the optimisation run will be generated accessible through attributes of the stats object

Returns

opt [OptimResult] Returns instance of OptimResult, which has attributes giving the reason for termination, final fidelity error, final evolution final amplitudes, statistics etc

 $opt_pulse_crab_unitary(H_d, H_c, U_0, U_targ, num_tslots=None, evo_time=None,$ tau=None, amp_lbound=None, amp_ubound=None, fid_err_targ=1e-05, $max_iter=500$, *max_wall_time=180*, alg_params=None, num_coeffs=None, init_coeff_scaling=1.0, optim_params=None, optim_method='fmin', method_params=None, phase_option='PSU', dyn params=None, prop_params=None, fid_params=None, tslot type='DEF', tslot params=None, guess_pulse_type=None, guess_pulse_params=None, guess pulse scaling=1.0, guess_pulse_offset=0.0, guess_pulse_action='MODULATE', ramping_pulse_type=None, ramping_pulse_params=None, log_level=0, out_file_ext=None, gen_stats=False)

Optimise a control pulse to minimise the fidelity error, assuming that the dynamics of the system are generated by unitary operators. This function is simply a wrapper for optimize_pulse, where the appropriate options for unitary dynamics are chosen and the parameter names are in the format familiar to unitary dynamics. The dynamics of the system in any given timeslot are governed by the combined Hamiltonian, i.e. the sum of the $H_d + ctrl_amp[j]*H_c[j]$ The control pulse is an [n_ts, n_ctrls] array of piecewise amplitudes

The CRAB algorithm uses basis function coefficients as the variables to optimise. It does NOT use any gradient function. A multivariable optimisation algorithm attempts to determines the optimal values for the control pulse to minimise the fidelity error. The fidelity error is some measure of distance of the system evolution from the given target evolution in the time allowed for the evolution.

Parameters

- **H_d** [Qobj or list of Qobj] Drift (aka system) the underlying Hamiltonian of the system can provide list (of length num_tslots) for time dependent drift
- **H_c** [List of Qobj or array like [num_tslots, evo_time]] a list of control Hamiltonians. These are scaled by the amplitudes to alter the overall dynamics Array like imput can be provided for time dependent control generators
- U_0 [Qobj] starting point for the evolution. Typically the identity matrix
- U_targ [Qobj] target transformation, e.g. gate or state, for the time evolution
- num_tslots [integer or None] number of timeslots. None implies that timeslots will be
 given in the tau array
- evo_time [float or None] total time for the evolution None implies that timeslots will be given in the tau array
- **tau** [array[num_tslots] of floats or None] durations for the timeslots. if this is given then num_tslots and evo_time are dervived from it None implies that timeslot durations will be equal and calculated as evo_time/num_tslots
- **amp_lbound** [float or list of floats] lower boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control
- **amp_ubound** [float or list of floats] upper boundaries for the control amplitudes Can be a scalar value applied to all controls or a list of bounds for each control
- fid_err_targ [float] Fidelity error target. Pulse optimisation will terminate when the fidelity error falls below this value
- max_iter [integer] Maximum number of iterations of the optimisation algorithm
- max_wall_time [float] Maximum allowed elapsed time for the optimisation algorithm
- alg_params [Dictionary] options that are specific to the algorithm see above
- **optim_params** [Dictionary] The key value pairs are the attribute name and value used to set attribute values Note: attributes are created if they do not exist already, and are overwritten if they do. Note: method_params are applied afterwards and so may override these
- **coeff_scaling** [float] Linear scale factor for the random basis coefficients By default these range from -1.0 to 1.0 Note this is overridden by alg_params (if given there)

- num_coeffs [integer] Number of coefficients used for each basis function Note this is calculated automatically based on the dimension of the dynamics if not given. It is crucial to the performane of the algorithm that it is set as low as possible, while still giving high enough frequencies. Note this is overridden by alg_params (if given there)
- **optim_method** [string] Multi-variable optimisation method The only tested options are 'fmin' and 'Nelder-mead' In theory any non-gradient method implemented in scipy.optimize.mininize could be used.
- **method_params** [dict] Parameters for the optim_method. Note that where there is an attribute of the Optimizer object or the termination_conditions matching the key that attribute. Otherwise, and in some case also, they are assumed to be method_options for the scipy.optimize.minimize method. The commonly used parameter are:

xtol - limit on variable change for convergence ftol - limit on fidelity error change for convergence

phase_option [string] determines how global phase is treated in fidelity calculations
 (fid_type='UNIT' only). Options:

PSU - global phase ignored SU - global phase included

- **dyn_params** [dict] Parameters for the Dynamics object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **prop_params** [dict] Parameters for the PropagatorComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **fid_params** [dict] Parameters for the FidelityComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **tslot_type** [string] Method for computing the dynamics generators, propagators and evolution in the timeslots. Options: DEF, UPDATE_ALL, DYNAMIC UPDATE_ALL is the only one that currently works (See TimeslotComputer classes for details)
- **tslot_params** [dict] Parameters for the TimeslotComputer object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **guess_pulse_type** [string] type / shape of pulse(s) used modulate the control amplitudes. Options include:

RND, LIN, ZERO, SINE, SQUARE, TRIANGLE, SAW, GAUSSIAN

Default is None

- **guess_pulse_params** [dict] Parameters for the guess pulse generator object The key value pairs are assumed to be attribute name value pairs They applied after the object is created
- **guess_pulse_action** [string] Determines how the guess pulse is applied to the pulse generated by the basis expansion. Options are: MODULATE, ADD Default is MODULATE
- **pulse_scaling** [float] Linear scale factor for generated guess pulses By default initial pulses are generated with amplitudes in the range (-1.0, 1.0). These will be scaled by this parameter
- **pulse_offset** [float] Linear offset for the pulse. That is this value will be added to any guess pulses generated.
- ramping_pulse_type [string] Type of pulse used to modulate the control pulse. It's intended use for a ramping modulation, which is often required in experimental setups. This is only currently implemented in CRAB. GAUSSIAN_EDGE was added for this purpose.
- ramping_pulse_params [dict] Parameters for the ramping pulse generator object The key value pairs are assumed to be attribute name value pairs They applied after the object is created

- **log_level** [integer] level of messaging output from the logger. Options are attributes of qutip.logging_utils, in decreasing levels of messaging, are: DEBUG_INTENSE, DEBUG_VERBOSE, DEBUG, INFO, WARN, ERROR, CRITICAL Anything WARN or above is effectively 'quiet' execution, assuming everything runs as expected. The default NOTSET implies that the level will be taken from the QuTiP settings file, which by default is WARN
- out_file_ext [string or None] files containing the initial and final control pulse amplitudes are saved to the current directory. The default name will be postfixed with this extension Setting this to None will suppress the output of files
- **gen_stats** [boolean] if set to True then statistics for the optimisation run will be generated accessible through attributes of the stats object

opt [OptimResult] Returns instance of OptimResult, which has attributes giving the reason for termination, final fidelity error, final evolution final amplitudes, statistics etc

Pulse generator - Generate pulses for the timeslots Each class defines a gen_pulse function that produces a float array of size num_tslots. Each class produces a differ type of pulse. See the class and gen_pulse function descriptions for details

create_pulse_gen (pulse_type='RND', dyn=None, pulse_params=None)

Create and return a pulse generator object matching the given type. The pulse generators each produce a different type of pulse, see the gen_pulse function description for details. These are the random pulse options:

RND - Independent random value in each timeslot RNDFOURIER - Fourier series with random coefficients RNDWAVES - Summation of random waves RNDWALK1 - Random change in amplitude each timeslot RNDWALK2 - Random change in amp gradient each timeslot

These are the other non-periodic options:

LIN - Linear, i.e. contant gradient over the time ZERO - special case of the LIN pulse, where the gradient is $\mathbf{0}$

These are the periodic options

SINE - Sine wave SQUARE - Square wave SAW - Saw tooth wave TRIANGLE - Triangular wave

If a Dynamics object is passed in then this is used in instantiate the PulseGen, meaning that some timeslot and amplitude properties are copied over.

4.2.8 Utility Functions

Graph Theory Routines

This module contains a collection of graph theory routines used mainly to reorder matrices for iterative steady state solvers.

breadth_first_search(A, start)

Breadth-First-Search (BFS) of a graph in CSR or CSC matrix format starting from a given node (row). Takes Qobjs and CSR or CSC matrices as inputs.

This function requires a matrix with symmetric structure. Use A+trans(A) if original matrix is not symmetric or not sure.

Parameters

A [csc_matrix, csr_matrix] Input graph in CSC or CSR matrix format

start [int] Staring node for BFS traversal.

Returns

order [array] Order in which nodes are traversed from starting node.

levels [array] Level of the nodes in the order that they are traversed.

$graph_degree(A)$

Returns the degree for the nodes (rows) of a symmetric graph in sparse CSR or CSC format, or a qobj.

Parameters

A [qobj, csr_matrix, csc_matrix] Input quantum object or csr_matrix.

Returns

degree [array] Array of integers giving the degree for each node (row).

reverse_cuthill_mckee(A, sym=False)

Returns the permutation array that orders a sparse CSR or CSC matrix in Reverse-Cuthill McKee ordering. Since the input matrix must be symmetric, this routine works on the matrix A+Trans(A) if the sym flag is set to False (Default).

It is assumed by default (sym=False) that the input matrix is not symmetric. This is because it is faster to do A+Trans(A) than it is to check for symmetry for a generic matrix. If you are guaranteed that the matrix is symmetric in structure (values of matrix element do not matter) then set sym=True

Parameters

A [csc_matrix, csr_matrix] Input sparse CSC or CSR sparse matrix format.

sym [bool {False, True}] Flag to set whether input matrix is symmetric.

Returns

perm [array] Array of permuted row and column indices.

Notes

This routine is used primarily for internal reordering of Lindblad superoperators for use in iterative solver routines.

References

E. Cuthill and J. McKee, "Reducing the Bandwidth of Sparse Symmetric Matrices", ACM '69 Proceedings of the 1969 24th national conference, (1969).

maximum_bipartite_matching(A, perm_type='row')

Returns an array of row or column permutations that removes nonzero elements from the diagonal of a nonsingular square CSC sparse matrix. Such a permutation is always possible provided that the matrix is nonsingular. This function looks at the structure of the matrix only.

The input matrix will be converted to CSC matrix format if necessary.

Parameters

A [sparse matrix] Input matrix

perm_type [str {'row', 'column'}] Type of permutation to generate.

Returns

perm [array] Array of row or column permutations.

Notes

This function relies on a maximum cardinality bipartite matching algorithm based on a breadth-first search (BFS) of the underlying graph[1]_.

References

I. S. Duff, K. Kaya, and B. Ucar, "Design, Implementation, and Analysis of Maximum Transversal Algorithms", ACM Trans. Math. Softw. 38, no. 2, (2011).

weighted_bipartite_matching(A, perm_type='row')

Returns an array of row permutations that attempts to maximize the product of the ABS values of the diagonal elements in a nonsingular square CSC sparse matrix. Such a permutation is always possible provided that the matrix is nonsingular.

This function looks at both the structure and ABS values of the underlying matrix.

Parameters

A [csc_matrix] Input matrix

perm_type [str {'row', 'column'}] Type of permutation to generate.

Returns

perm [array] Array of row or column permutations.

Notes

This function uses a weighted maximum cardinality bipartite matching algorithm based on breadth-first search (BFS). The columns are weighted according to the element of max ABS value in the associated rows and are traversed in descending order by weight. When performing the BFS traversal, the row associated to a given column is the one with maximum weight. Unlike other techniques[1]_, this algorithm does not guarantee the product of the diagonal is maximized. However, this limitation is offset by the substantially faster runtime of this method.

References

I. S. Duff and J. Koster, "The design and use of algorithms for permuting large entries to the diagonal of sparse matrices", SIAM J. Matrix Anal. and Applics. 20, no. 4, 889 (1997).

Utility Functions

This module contains utility functions that are commonly needed in other qutip modules.

n_thermal(w, w_th)

Return the number of photons in thermal equilibrium for an harmonic oscillator mode with frequency 'w', at the temperature described by 'w_th' where $\omega_{th} = k_B T / \hbar$.

Parameters

w [float or array] Frequency of the oscillator.

w_th [*float*] The temperature in units of frequency (or the same units as *w*).

Returns

n_avg [*float* or *array*] Return the number of average photons in thermal equilibrium for a an oscillator with the given frequency and temperature.

Return an array of numbers sampled over specified interval with additional elements added.

Returns num spaced array with elements from elems inserted if not already included in set.

Returned sample array is not evenly spaced if additional elements are added.

Parameters

start [int] The starting value of the sequence.

stop [int] The stoping values of the sequence.

num [int, optional] Number of samples to generate.

elems [list/ndarray, optional] Requested elements to include in array

Returns

samples [ndadrray] Original equally spaced sample array with additional elements added.

clebsch (j1, j2, j3, m1, m2, m3)

Calculates the Clebsch-Gordon coefficient for coupling (j1,m1) and (j2,m2) to give (j3,m3).

Parameters

j1 [float] Total angular momentum 1.

j2 [float] Total angular momentum 2.

j3 [float] Total angular momentum 3.

m1 [float] z-component of angular momentum 1.

m2 [float] z-component of angular momentum 2.

m3 [float] z-component of angular momentum 3.

Returns

cg_coeff [float] Requested Clebsch-Gordan coefficient.

convert_unit (value, orig='meV', to='GHz')

Convert an energy from unit *orig* to unit to.

Parameters

value [float / array] The energy in the old unit.

orig [string] The name of the original unit ("J", "eV", "meV", "GHz", "mK")

to [string] The name of the new unit ("J", "eV", "meV", "GHz", "mK")

Returns

value_new_unit [float / array] The energy in the new unit.

File I/O Functions

file_data_read (filename, sep=None)

Retrieves an array of data from the requested file.

Parameters

filename [str] Name of file containing reqested data.

sep [str] Seperator used to store data.

Returns

data [array_like] Data from selected file.

file_data_store (filename, data, numtype='complex', numformat='decimal', sep=', ')
Stores a matrix of data to a file to be read by an external program.

Parameters

filename [str] Name of data file to be stored, including extension.

data: array_like Data to be written to file.

numtype [str {'complex, 'real'}] Type of numerical data.

numformat [str {'decimal','exp'}] Format for written data.

sep [str] Single-character field seperator. Usually a tab, space, comma, or semicolon.

qload(*name*)

Loads data file from file named 'filename.qu' in current directory.

Parameters

name [str] Name of data file to be loaded.

Returns

qobject [instance / array_like] Object retrieved from requested file.

qsave (*data*, *name='qutip_data'*)

Saves given data to file named 'filename.qu' in current directory.

Parameters

data [instance/array_like] Input Python object to be stored.

filename [str] Name of output data file.

Parallelization

This function provides functions for parallel execution of loops and function mappings, using the builtin Python module multiprocessing.

parfor (func, *args, **kwargs)

Executes a multi-variable function in parallel on the local machine.

Parallel execution of a for-loop over function *func* for multiple input arguments and keyword arguments.

Note: From QuTiP 3.1, we recommend to use qutip.parallel_map instead of this function.

Parameters

func [function_type] A function to run in parallel on the local machine. The function 'func' accepts a series of arguments that are passed to the function as variables. In general, the function can have multiple input variables, and these arguments must be passed in the same order as they are defined in the function definition. In addition, the user can pass multiple keyword arguments to the function.

The following keyword argument is reserved:

num_cpus [int] Number of CPU's to use. Default uses maximum number of CPU's. Performance degrades if num_cpus is larger than the physical CPU count of your machine.

Returns

result [list] A list with length equal to number of input parameters containing the output from *func*.

parallel_map (task, values, task_args=(), task_kwargs={}, **kwargs)

Parallel execution of a mapping of *values* to the function *task*. This is functionally equivalent to:

result = [task(value, *task_args, **task_kwargs) **for** value **in** values]

Parameters

task [a Python function] The function that is to be called for each value in task_vec.

values [array / list] The list or array of values for which the task function is to be evaluated.

task_args [list / dictionary] The optional additional argument to the task function.

task_kwargs [list / dictionary] The optional additional keyword argument to the task function.

progress_bar [ProgressBar] Progress bar class instance for showing progress.

Returns

result [list] The result list contains the value of task(value, *task_args, **task_kwargs) for each value in values.

serial_map (task, values, task_args=(), task_kwargs={}, **kwargs)

Serial mapping function with the same call signature as parallel_map, for easy switching between serial and parallel execution. This is functionally equivalent to:

result = [task(value, *task_args, **task_kwargs) **for** value **in** values]

This function work as a drop-in replacement of qutip.parallel_map.

Parameters

task [a Python function] The function that is to be called for each value in task_vec.

- **values** [array / list] The list or array of values for which the task function is to be evaluated.
- task_args [list / dictionary] The optional additional argument to the task function.
- **task_kwargs** [list / dictionary] The optional additional keyword argument to the task function.

progress_bar [ProgressBar] Progress bar class instance for showing progress.

Returns

result [list] The result list contains the value of task(value, *task_args, **task_kwargs) for each value in values.

IPython Notebook Tools

This module contains utility functions for using QuTiP with IPython notebooks.

Call the function tast for each value in task_vec using a cluster of IPython engines. The function task should have the signature task (value, args) or task (value) if args=None.

The client and view are the IPython.parallel client and load-balanced view that will be used in the parfor execution. If these are None, new instances will be created.

Parameters

task: a Python function The function that is to be called for each value in task_vec.

- **task_vec: array / list** The list or array of values for which the task function is to be evaluated.
- **args: list / dictionary** The optional additional argument to the task function. For example a dictionary with parameter values.
- **client: IPython.parallel.Client** The IPython.parallel Client instance that will be used in the parfor execution.
- **view: a IPython.parallel.Client view** The view that is to be used in scheduling the tasks on the IPython cluster. Preferably a load-balanced view, which is obtained from the IPython.parallel.Client instance client by calling, view = client.load_balanced_view().

- show_scheduling: bool {False, True}, default False Display a graph showing how the
 tasks (the evaluation of task for for the value in task_vec1) was scheduled on the
 IPython engine cluster.
- **show_progressbar: bool {False, True}, default False** Display a HTML-based progress bar duing the execution of the parfor loop.

Returns

result [list] The result list contains the value of task(value, args) for each value in task_vec, that is, it should be equivalent to [task(v, args) for v in task_vec].

Call the function task for each value in values using a cluster of IPython engines. The function task should have the signature task (value, *args, **kwargs).

The client and view are the IPython.parallel client and load-balanced view that will be used in the parfor execution. If these are None, new instances will be created.

Parameters

- task: a Python function The function that is to be called for each value in task_vec.
- values: array / list The list or array of values for which the task function is to be evaluated.
- task_args: list / dictionary The optional additional argument to the task function.
- **task_kwargs: list / dictionary** The optional additional keyword argument to the task function.
- **client: IPython.parallel.Client** The IPython.parallel Client instance that will be used in the parfor execution.
- **view: a IPython.parallel.Client view** The view that is to be used in scheduling the tasks on the IPython cluster. Preferably a load-balanced view, which is obtained from the IPython.parallel.Client instance client by calling, view = client.load_balanced_view().
- show_scheduling: bool {False, True}, default False Display a graph showing how the
 tasks (the evaluation of task for for the value in task_vec1) was scheduled on the
 IPython engine cluster.
- **show_progressbar: bool {False, True}, default False** Display a HTML-based progress bar during the execution of the parfor loop.

Returns

result [list] The result list contains the value of task(value, task_args, task_kwargs) for each value in values.

version_table (verbose=False)

Print an HTML-formatted table with version numbers for QuTiP and its dependencies. Use it in a IPython notebook to show which versions of different packages that were used to run the notebook. This should make it possible to reproduce the environment and the calculation later on.

Returns

version_table: string Return an HTML-formatted string containing version information for QuTiP dependencies.

Miscellaneous

about ()

About box for QuTiP. Gives version numbers for QuTiP, NumPy, SciPy, Cython, and MatPlotLib.

simdiag(ops, evals=True)

Simultaneous diagonalization of commuting Hermitian matrices.

Parameters

ops [list/array] list or array of qobjs representing commuting Hermitian operators.

Returns

eigs [tuple] Tuple of arrays representing eigvecs and eigvals of quantum objects corresponding to simultaneous eigenvectors and eigenvalues for each operator.

Chapter 5

Change Log

5.1 Version 4.4.0 (July 03, 2019)

- MAJOR FEATURE: Added methods and techniques to the stochastic solvers (by Eric Giguère) which allows to use a much broader set of solvers and much more efficiently.
- MAJOR FEATURE: Optimization of the montecarlo solver (by Eric Giguère). Computation are faster in many cases. Collapse information available to time dependant information.
- Added the QObjEvo class and methods (**by Eric Giguère**), which is used behind the scenes by the dynamical solvers, making the code more efficient and tidier. More built-in function available to string coefficients. The coefficients can be made from interpolated array with variable timesteps and can obtain state information more easily. Time-dependant collapse operator can have multiple terms.
- New wigner_transform and plot_wigner_sphere function. (by Nithin Ramu).
- ptrace is faster and work on bigger systems, from 15 Qbits to 30 Qbits.
- QIP module: added the possibility for user-defined gates, added the possibility to remove or add gates in any point of an already built circuit, added the molmer_sorensen gate, and fixed some bugs (by Boxi Li).
- Added the quantum Hellinger distance to qutip.metrics (by Wojciech Rzadkowski).
- Implemented possibility of choosing a random seed (by Marek marekyggdrasil).
- Added a code of conduct to Github.

5.1.1 Bug Fixes

- Fixed bug that made QuTiP incompatible with SciPy 1.3.
- quite.cite() is improved.
- · Added matplotlib as optional dependency and updated numpy and scipy requirements.
- Fixed matrix generating coherent spin states in qutip.piqs to include complex coefficients.

5.2 Version 4.3.0 (July 14, 2018)

5.2.1 Improvements

• MAJOR FEATURE: Added the Permutational Invariant Quantum Solver (PIQS) module (by Nathan Shammah and Shahnawaz Ahmed) which allows the simulation of large TLSs ensembles including collective and local Lindblad dissipation. Applications range from superradiance to spin squeezing.

- **MAJOR FEATURE**: Added a photon scattering module (**by Ben Bartlett**) which can be used to study scattering in arbitrary driven systems coupled to some configuration of output waveguides.
- Cubic_Spline functions as time-dependent arguments for the collapse operators in mesolve are now allowed.
- Added a faster version of bloch_redfield_tensor, using components from the time-dependent version. About 3x+ faster for secular tensors, and 10x+ faster for non-secular tensors.
- Computing Q.overlap() [inner product] is now ~30x faster.
- Added projector method to Qobj class.
- Added fast projector method, Q.proj().
- Computing matrix elements, Q.matrix_element is now ~10x faster.
- Computing expectation values for ket vectors using expect is now ~10x faster.
- Q.tr() is now faster for small Hilbert space dimensions.
- Unitary operator evolution added to sesolve
- Use OPENMP for tidyup if installed.

5.2.2 Bug Fixes

- Fixed bug that stopped simdiag working for python 3.
- Fixed semidefinite cvxpy Variable and Parameter.
- Fixed iterative lu solve atol keyword issue.
- Fixed unitary op evolution rhs matrix in ssesolve.
- Fixed interpolating function to return zero outside range.
- Fixed dnorm complex casting bug.
- Fixed control.io path checking issue.
- Fixed ENR fock dimension.
- Fixed hard coded options in propagator 'batch' mode
- Fixed bug in trace-norm for non-Hermitian operators.
- Fixed bug related to args not being passed to coherence_function_g2
- · Fixed MKL error checking dict key error

5.3 Version 4.2.0 (July 28, 2017)

5.3.1 Improvements

- MAJOR FEATURE: Initial implementation of time-dependent Bloch-Redfield Solver.
- Qobj tidyup is now an order of magnitude faster.
- Time-dependent codegen now generates output NumPy arrays faster.
- Improved calculation for analytic coefficients in coherent states (Sebastian Kramer).
- Input array to correlation FFT method now checked for validity.
- Function-based time-dependent mesolve and sesolve routines now faster.
- Codegen now makes sure that division is done in C, as opposed to Python.
- Can now set different controls for a each timeslot in quantum optimization.

This allows time-varying controls to be used in pulse optimisation.

5.3.2 Bug Fixes

- resolve importing old Odeoptions Class rather than Options.
- Non-int issue in spin Q and Wigner functions.
- Qobj's should tidyup before determining isherm.
- Fixed time-dependent RHS function loading on Win.
- Fixed several issues with compiling with Cython 0.26.
- Liouvillian superoperators were hard setting isherm=True by default.
- Fixed an issue with the solver safety checks when inputing a list

with Python functions as time-dependence.

- Fixed non-int issue in Wigner_cmap.
- MKL solver error handling not working properly.

5.4 Version 4.1.0 (March 10, 2017)

5.4.1 Improvements

Core libraries

- MAJOR FEATURE: QuTiP now works for Python 3.5+ on Windows using Visual Studio 2015.
- MAJOR FEATURE: Cython and other low level code switched to C++ for MS Windows compatibility.
- MAJOR FEATURE: Can now use interpolating cubic splines as time-dependent coefficients.
- MAJOR FEATURE: Sparse matrix vector multiplication now parallel using OPENMP.
- Automatic tuning of OPENMP threading threshold.
- Partial trace function is now up to 100x+ faster.
- Hermitian verification now up to 100x+ faster.
- Internal Qobj objects now created up to 60x faster.
- Inplace conversion from COO -> CSR sparse formats (e.g. Memory efficiency improvement.)
- Faster reverse Cuthill-Mckee and sparse one and inf norms.

5.4.2 Bug Fixes

• Cleanup of temp. Cython files now more robust and working under Windows.

5.5 Version 4.0.2 (January 5, 2017)

5.5.1 Bug Fixes

- td files no longer left behind by correlation tests
- Various fast sparse fixes

5.6 Version 4.0.0 (December 22, 2016)

5.6.1 Improvements

Core libraries

- MAJOR FEATURE: Fast sparse: New subclass of csr_matrix added that overrides commonly used methods to avoid certain checks that incurr execution cost. All Qobj.data now fast_csr_matrix
- HEOM performance enhancements
- spmv now faster
- mcsolve codegen further optimised

Control modules

- Time dependent drift (through list of pwc dynamics generators)
- memory optimisation options provided for control.dynamics

5.6.2 Bug Fixes

- · recompilation of pyx files on first import removed
- tau array in control.pulseoptim funcs now works

5.7 Version 3.2.0 (Never officially released)

5.7.1 New Features

Core libraries

- MAJOR FEATURE: Non-Markovian solvers: Hierarchy (Added by Neill Lambert), Memory-Cascade, and Transfer-Tensor methods.
- **MAJOR FEATURE**: Default steady state solver now up to 100x faster using the Intel Pardiso library under the Anaconda and Intel Python distributions.
- The default Wigner function now uses a Clenshaw summation algorithm to evaluate a polynomial series that is applicable for any number of excitations (previous limitation was ~50 quanta), and is ~3x faster than before. (Added by Denis Vasilyev)
- Can now define a given eigen spectrum for random Hermitian and density operators.
- The Qobj expm method now uses the equivilent SciPy routine, and performs a much faster exp operation if the matrix is diagonal.
- One can now build zero operators using the <code>qzero</code> function.

Control modules

• **MAJOR FEATURE**: CRAB algorithm added This is an alternative to the GRAPE algorithm, which allows for analytical control functions, which means that experimental constraints can more easily be added into optimisation. See tutorial notebook for full information.

5.7.2 Improvements

Core libraries

• Two-time correlation functions can now be calculated for fully time-dependent Hamiltonians and collapse operators. (Added by Kevin Fischer)

- The code for the inverse-power method for the steady state solver has been simplified.
- Bloch-Redfield tensor creation is now up to an order of magnitude faster. (Added by Johannes Feist)
- Q.transform now works properly for arrays directly from sp_eigs (or eig).
- Q.groundstate now checks for degeneracy.
- Added sinm and cosm methods to the Qobj class.
- Added charge and tunneling operators.
- Time-dependent Cython code is now easier to read and debug.

Control modules

• The internal state / quantum operator data type can now be either Qobj or ndarray Previous only ndarray was possible. This now opens up possibility of using Qobj methods in fidelity calculations The attributes and functions that return these operators are now preceded by an underscore, to indicate that the data type could change depending on the configuration options. In most cases these functions were for internal processing only anyway, and should have been 'private'. Accessors to the properties that could be useful outside of the library have been added. These always return Qobj. If the internal operator data type is not Qobj, then there could be signicant overhead in the conversion, and so this should be avoided during pulse optimisation. If custom sub-classes are developed that use Qobj properties and methods (e.g. partial trace), then it is very likely that it will be more efficient to set the internal data type to Qobj. The internal operator data will be chosen automatically based on the size and sparsity of the dynamics generator. It can be forced by setting dynamics.oper_dtype = <type> Note this can be done by passing dyn_params={'oper_dtype':<type>} in any of the pulseoptim functions.

Some other properties and methods were renamed at the same time. A full list is given here.

- All modules function: set_log_level -> property: log_level
- dynamics functions
 - * _init_lists now _init_evo
 - * get_num_ctrls now property: num_ctrls
 - * get_owd_evo_target now property: onto_evo_target
 - * combine_dyn_gen now _combine_dyn_gen (no longer returns a value)
 - * get_dyn_gen now _get_phased_dyn_gen
 - * get_ctrl_den_gen now _get_phased_ctrl_dyn_gen
 - * ensure_decomp_curr now _ensure_decomp_curr
 - * spectral_decomp now _spectral_decomp
- dynamics properties
 - * evo_init2t now _fwd_evo (fwd_evo as Qobj)
 - * evo_t2end now _onwd_evo (onwd_evo as Qobj)
 - * evo_t2targ now _onto_evo (onto_evo as Qobj)
- fidcomp properties
 - * uses_evo_t2end now uses_onwd_evo
 - * uses_evo_t2targ now uses_onto_evo
 - * set_phase_option function now property phase_option
- propcomp properties
 - * grad_exact (now read only)
- propcomp functions
 - * compute_propagator now _compute_propagator

- * compute_diff_prop now _compute_diff_prop
- * compute_prop_grad now _compute_prop_grad
- tslotcomp functions
 - * get_timeslot_for_fidelity_calc now_get_timeslot_for_fidelity_calc

Miscellaneous

- QuTiP Travis CI tests now use the Anaconda distribution.
- The about box and ipynb version_table now display addition system information.
- Updated Cython cleanup to remove depreciation warning in sysconfig.
- Updated ipynb_parallel to look for ipyparallel module in V4 of the notebooks.

5.7.3 Bug Fixes

- Fixes for countstat and psuedo-inverse functions
- Fixed Qobj division tests on 32-bit systems.
- Removed extra call to Python in time-dependent Cython code.
- Fixed issue with repeated Bloch sphere saving.
- Fixed T_0 triplet state not normalized properly. (Fixed by Eric Hontz)
- Simplified compiler flags (support for ARM systems).
- Fixed a decoding error in gload.
- Fixed issue using complex.h math and np.kind_t variables.
- Corrected output states mismatch for ntraj=1 in the mcf90 solver.
- Qobj data is now copied by default to avoid a bug in multiplication. (Fixed by Richard Brierley)
- Fixed bug overwriting hardware_info in __init__. (Fixed by Johannes Feist)
- Restored ability to explicitly set Q.isherm, Q.type, and Q.superrep.
- Fixed integer depreciation warnings from NumPy.
- Qobj * (dense vec) would result in a recursive loop.
- Fixed args=None -> args={} in correlation functions to be compatible with mesolve.
- Fixed depreciation warnings in mcsolve.
- Fixed neagtive only real parts in rand_ket.
- Fixed a complicated list-cast-map-list antipattern in super operator reps. (Fixed by Stefan Krastanov)
- Fixed incorrect isherm for sigmam spin operator.
- Fixed the dims when using final_state_output in mesolve and sesolve.

5.8 Version 3.1.0 (January 1, 2015):

5.8.1 New Features

- MAJOR FEATURE: New module for quantum control (qutip.control).
- NAMESPACE CHANGE: QuTiP no longer exports symbols from NumPy and matplotlib, so those modules must now be explicitly imported when required.
- New module for counting statistics.

- Stochastic solvers now run trajectories in parallel.
- New superoperator and tensor manipulation functions (super_tensor, composite, tensor_contract).
- New logging module for debugging (qutip.logging).
- New user-available API for parallelization (parallel_map).
- New enhanced (optional) text-based progressbar (qutip.ui.EnhancedTextProgressBar)
- Faster Python based monte carlo solver (mcsolve).
- Support for progress bars in propagator function.
- Time-dependent Cython code now calls complex cmath functions.
- Random numbers seeds can now be reused for successive calls to mcsolve.
- The Bloch-Redfield master equation solver now supports optional Lindblad type collapse operators.
- Improved handling of ODE integration errors in mesolve.
- Improved correlation function module (for example, improved support for time-dependent problems).
- Improved parallelization of mcsolve (can now be interrupted easily, support for IPython.parallel, etc.)
- Many performance improvements, and much internal code restructuring.

5.8.2 Bug Fixes

- Cython build files for time-dependent string format now removed automatically.
- Fixed incorrect solution time from inverse-power method steady state solver.
- mcsolve now supports *Options(store_states=True)*
- Fixed bug in *hadamard* gate function.
- Fixed compatibility issues with NumPy 1.9.0.
- Progressbar in mcsolve can now be suppressed.
- Fixed bug in *gate_expand_3toN*.
- Fixed bug for time-dependent problem (list string format) with multiple terms in coefficient to an operator.

5.9 Version 3.0.1 (Aug 5, 2014):

5.9.1 Bug Fixes

- Fix bug in create(), which returned a Qobj with CSC data instead of CSR.
- Fix several bugs in mcsolve: Incorrect storing of collapse times and collapse operator records. Incorrect averaging of expectation values for different trajectories when using only 1 CPU.
- Fix bug in parsing of time-dependent Hamiltonian/collapse operator arguments that occurred when the args argument is not a dictionary.
- Fix bug in internal _version2int function that cause a failure when parsingthe version number of the Cython package.

•

5.10 Version 3.0.0 (July 17, 2014):

5.10.1 New Features

- New module *qutip.stochastic* with stochastic master equation and stochastic Schrödinger equation solvers.
- Expanded steady state solvers. The function steady has been deprecated in favor of steadystate. The steadystate solver no longer use umfpack by default. New pre-processing methods for reordering and balancing the linear equation system used in direct solution of the steady state.
- New module *qutip.qip* with utilities for quantum information processing, including pre-defined quantum gates along with functions for expanding arbitrary 1, 2, and 3 qubit gates to N qubit registers, circuit representations, library of quantum algorithms, and basic physical models for some common QIP architectures.
- New module qutip.distributions with unified API for working with distribution functions.
- New format for defining time-dependent Hamiltonians and collapse operators, using a pre-calculated numpy array that specifies the values of the Qobj-coefficients for each time step.
- New functions for working with different superoperator representations, including Kraus and Chi representation.
- New functions for visualizing quantum states using Qubism and Schimdt plots: plot_qubism and plot_schmidt.
- Dynamics solver now support taking argument e_ops (expectation value operators) in dictionary form.
- Public plotting functions from the qutip.visualization module are now prefixed with plot_(e.g., plot_fock_distribution). The plot_wigner and plot_wigner_fock_distribution now supports 3D views in addition to contour views.
- New API and new functions for working with spin operators and states, including for example spin_Jx, spin_Jy, spin_Jz and spin_state, spin_coherent.
- The expect function now supports a list of operators, in addition to the previously supported list of states.
- Simplified creation of qubit states using ket function.
- The module qutip.cyQ has been renamed to qutip.cy and the sparse matrix-vector functions spmv and spmvld has been combined into one function spmv. New functions for operating directly on the underlaying sparse CSR data have been added (e.g., spmv_csr). Performance improvements. New and improved Cython functions for calculating expectation values for state vectors, density matrices in matrix and vector form.
- The concurrence function now supports both pure and mixed states. Added function for calculating the entangling power of a two-qubit gate.
- Added function for generating (generalized) Lindblad dissipator superoperators.
- New functions for generating Bell states, and singlet and triplet states.
- QuTiP no longer contains the demos GUI. The examples are now available on the QuTiP web site. The qutip.gui module has been renamed to qutip.ui and does no longer contain graphical UI elements. New text-based and HTML-based progressbar classes.
- Support for harmonic oscillator operators/states in a Fock state basis that does not start from zero (e.g., in the range [M,N+1]). Support for eliminating and extracting states from Qobj instances (e.g., removing one state from a two-qubit system to obtain a three-level system).
- Support for time-dependent Hamiltonian and Liouvillian callback functions that depend on the instantaneous state, which for example can be used for solving master equations with mean field terms.

5.10.2 Improvements

- Restructured and optimized implementation of Qobj, which now has significantly lower memory footprint due to avoiding excessive copying of internal matrix data.
- The classes OdeData, Odeoptions, Odeconfig are now called Result, Options, and Config, respectively, and are available in the module *qutip.solver*.
- The squeez function has been renamed to squeeze.
- Better support for sparse matrices when calculating propagators using the propagator function.
- Improved Bloch sphere.
- Restructured and improved the module qutip.sparse, which now only operates directly on sparse matrices (not on Qobj instances).
- Improved and simplified implement of the tensor function.
- Improved performance, major code cleanup (including namespace changes), and numerous bug fixes.
- Benchmark scripts improved and restructured.
- QuTiP is now using continuous integration tests (TravisCI).

5.11 Version 2.2.0 (March 01, 2013):

5.11.1 New Features

- Added Support for Windows
- New Bloch3d class for plotting 3D Bloch spheres using Mayavi.
- Bloch sphere vectors now look like arrows.
- Partial transpose function.
- Continuos variable functions for calculating correlation and covariance matrices, the Wigner covariance matrix and the logarithmic negativity for for multimode fields in Fock basis.
- The master-equation solver (mesolve) now accepts pre-constructed Liouvillian terms, which makes it possible to solve master equations that are not on the standard Lindblad form.
- Optional Fortran Monte Carlo solver (mcsolve_f90) by Arne Grimsmo.
- A module of tools for using QuTiP in IPython notebooks.
- Increased performance of the steady state solver.
- New Wigner colormap for highlighting negative values.
- More graph styles to the visualization module.

5.11.2 Bug Fixes:

- Function based time-dependent Hamiltonians now keep the correct phase.
- mcsolve no longer prints to the command line if ntraj=1.

5.12 Version 2.1.0 (October 05, 2012):

5.12.1 New Features

- New method for generating Wigner functions based on Laguerre polynomials.
- coherent(), coherent_dm(), and thermal_dm() can now be expressed using analytic values.
- Unittests now use nose and can be run after installation.
- Added iswap and sqrt-iswap gates.
- Functions for quantum process tomography.
- Window icons are now set for Ubuntu application launcher.
- The propagator function can now take a list of times as argument, and returns a list of corresponding propagators.

5.12.2 Bug Fixes:

- mesolver now correctly uses the user defined rhs_filename in Odeoptions().
- rhs_generate() now handles user defined filenames properly.
- Density matrix returned by propagator_steadystate is now Hermitian.
- eseries_value returns real list if all imag parts are zero.
- mcsolver now gives correct results for strong damping rates.
- Odeoptions now prints mc_avg correctly.
- Do not check for PyObj in mcsolve when gui=False.
- Eseries now correctly handles purely complex rates.
- thermal_dm() function now uses truncated operator method.
- Cython based time-dependence now Python 3 compatible.
- Removed call to NSAutoPool on mac systems.
- Progress bar now displays the correct number of CPU's used.
- Qobj.diag() returns reals if operator is Hermitian.
- Text for progress bar on Linux systems is no longer cutoff.

5.13 Version 2.0.0 (June 01, 2012):

The second version of QuTiP has seen many improvements in the performance of the original code base, as well as the addition of several new routines supporting a wide range of functionality. Some of the highlights of this release include:

5.13.1 New Features

- QuTiP now includes solvers for both Floquet and Bloch-Redfield master equations.
- The Lindblad master equation and Monte Carlo solvers allow for time-dependent collapse operators.
- It is possible to automatically compile time-dependent problems into c-code using Cython (if installed).
- Python functions can be used to create arbitrary time-dependent Hamiltonians and collapse operators.

• Solvers now return Odedata objects containing all simulation results and parameters, simplifying the saving of simulation results.

Important: This breaks compatibility with QuTiP version 1.x.

- mesolve and mcsolve can reuse Hamiltonian data when only the initial state, or time-dependent arguments, need to be changed.
- QuTiP includes functions for creating random quantum states and operators.
- The generation and manipulation of quantum objects is now more efficient.
- Quantum objects have basis transformation and matrix element calculations as built-in methods.
- The quantum object eigensolver can use sparse solvers.
- The partial-trace (ptrace) function is up to 20x faster.
- The Bloch sphere can now be used with the Matplotlib animation function, and embedded as a subplot in a figure.
- QuTiP has built-in functions for saving quantum objects and data arrays.
- The steady-state solver has been further optimized for sparse matrices, and can handle much larger system Hamiltonians.
- The steady-state solver can use the iterative bi-conjugate gradient method instead of a direct solver.
- There are three new entropy functions for concurrence, mutual information, and conditional entropy.
- Correlation functions have been combined under a single function.
- The operator norm can now be set to trace, Frobius, one, or max norm.
- Global QuTiP settings can now be modified.
- QuTiP includes a collection of unit tests for verifying the installation.
- Demos window now lets you copy and paste code from each example.

5.14 Version 1.1.4 (May 28, 2012):

5.14.1 Bug Fixes:

- Fixed bug pointed out by Brendan Abolins.
- Qobj.tr() returns zero-dim ndarray instead of float or complex.
- Updated factorial import for scipy version 0.10+

5.15 Version 1.1.3 (November 21, 2011):

5.15.1 New Functions:

• Allow custom naming of Bloch sphere.

5.15.2 Bug Fixes:

- Fixed text alignment issues in AboutBox.
- Added fix for SciPy V>0.10 where factorial was moved to scipy.misc module.
- Added tidyup function to tensor function output.
- Removed openmp flags from setup.py as new Mac Xcode compiler does not recognize them.
- Qobj diag method now returns real array if all imaginary parts are zero.
- Examples GUI now links to new documentation.
- Fixed zero-dimensional array output from metrics module.

5.16 Version 1.1.2 (October 27, 2011)

5.16.1 Bug Fixes

• Fixed issue where Monte Carlo states were not output properly.

5.17 Version 1.1.1 (October 25, 2011)

THIS POINT-RELEASE INCLUDES VASTLY IMPROVED TIME-INDEPENDENT MCSOLVE AND ODESOLVE PERFORMANCE

5.17.1 New Functions

- Added linear entropy function.
- Number of CPU's can now be changed.

5.17.2 Bug Fixes

- Metrics no longer use dense matrices.
- Fixed Bloch sphere grid issue with matplotlib 1.1.
- Qobj trace operation uses only sparse matrices.
- Fixed issue where GUI windows do not raise to front.

5.18 Version 1.1.0 (October 04, 2011)

THIS RELEASE NOW REQUIRES THE GCC COMPILER TO BE INSTALLED

5.18.1 New Functions

- tidyup function to remove small elements from a Qobj.
- Added concurrence function.
- Added simdiag for simultaneous diagonalization of operators.
- Added eigenstates method returning eigenstates and eigenvalues to Qobj class.

- Added fileio for saving and loading data sets and/or Qobj's.
- Added hinton function for visualizing density matrices.

5.18.2 Bug Fixes

- Switched Examples to new Signals method used in PySide 1.0.6+.
- Switched ProgressBar to new Signals method.
- Fixed memory issue in expm functions.
- Fixed memory bug in isherm.
- Made all Qobj data complex by default.
- Reduced ODE tolerance levels in Odeoptions.
- Fixed bug in ptrace where dense matrix was used instead of sparse.
- Fixed issue where PyQt4 version would not be displayed in about box.
- Fixed issue in Wigner where xvec was used twice (in place of yvec).

5.19 Version 1.0.0 (July 29, 2011)

• Initial release.

Chapter 6

Developers

6.1 Lead Developers

Robert Johansson (RIKEN) Paul Nation (Korea University)

6.2 Contributors

Note: Anyone is welcome to contribute to QuTiP. If you are interested in helping, please let us know!

alexbrc (github user) - Code contributor Alexander Pitchford (Aberystwyth University) - Code contributor Amit Jamadagni - Bug fix Anders Lund (Technical University of Denmark) - Bug hunting for the Monte-Carlo solver Andre Carvalho - Bug hunter André Xuereb (University of Hannover) - Bug hunter Anubhav Vardhan (IIT, Kanpur) - Bug hunter, Code contributor, Documentation Arne Grimsmo (University of Auckland) - Bug hunter, Code contributor Ben Criger (Waterloo IQC) - Code contributor Ben Bartlett (Stanford) - Code contributor Bredan Abolins (Berkeley) - Bug hunter Chris Granade - Code contributor Claudia Degrandi (Yale University) - Documentation Dawid Crivelli - Bug hunter Denis Vasilyev (St. Petersburg State University) - Code contributor Dong Zhou (Yale University) - Bug hunter Eric Giguere (Sherbrooke University) - Code contributor Florian Ong (Institute for Quantum Computation) - Bug hunter Frank Schima - Macports packaging

Henri Nielsen (Technical University of Denmark) - Bug hunter Hwajung Kang (Systems Biology Institute, Tokyo) - Suggestions for improving Bloch class James Clemens (Miami University - Ohio) - Bug hunter Johannes Feist - Code contributor Jonas Hörsch - Code contributor Jonas Neergaard-Nielsen (Technical University of Denmark) - Code contributor, Windows support JP Hadden (University of Bristol) - Code contributor, improved Bloch sphere visualization Kevin Fischer (Stanford) - Code contributor Laurence Stant - Documentation Markus Baden (Centre for Quantum Technologies, Singapore) - Code contributor, Documentation Myung-Joong Hwang (Pohang University of Science and Technology) - Bug hunter Nathan Shammah (RIKEN) - Code contributor Neill Lambert (RIKEN) - Code contributor, Windows support Nikolas Tezak (Stanford) - Code contributor Nithin Ramu Code contributor Per Nielsen (Technical University of Denmark) - Bug hunter, Code contributor Piotr Migdał (ICFO) - Code contributor Reinier Heeres (Yale University) - Code contributor Robert Jördens (NIST) - Linux packaging Simon Whalen - Code contributor Shahnawaz Ahmed (RIKEN, BITS Pilani) - Code contributor, Bug hunter

W.M. Witzel - Bug hunter

Chapter 7

Bibliography

Chapter 8

Indices and tables

- genindex
- modindex
- search

Bibliography

I	R0be8dcf25d86-1	Shore, B. V	W., "The	Theory of	Coherent A	tomic Ex	citation".	Wiley.	1990.

- [1] http://en.wikipedia.org/wiki/Concurrence_(quantum_computing)
- [BCSZ08] W. Bruzda, V. Cappellini, H.-J. Sommers, K. Życzkowski, *Random Quantum Operations*, Phys. Lett. A 373, 320-324 (2009). doi:10.1016/j.physleta.2008.11.043.
- [Hav03] Havel, T. Robust procedures for converting among Lindblad, Kraus and matrix representations of quantum dynamical semigroups. Journal of Mathematical Physics 44 2, 534 (2003). doi:10.1063/1.1518555.
- [Wat13] Watrous, J. Theory of Quantum Information, lecture notes.
- [Mez07] F. Mezzadri, How to generate random matrices from the classical compact groups, Notices of the AMS 54 592-604 (2007). arXiv:math-ph/0609050.
- [Mis12] J. A. Miszczak, *Generating and using truly random quantum states in Mathematica*, Computer Physics Communications **183** 1, 118-124 (2012). doi:10.1016/j.cpc.2011.08.002.
- [Moh08] M. Mohseni, A. T. Rezakhani, D. A. Lidar, Quantum-process tomography: Resource analysis of different strategies, Phys. Rev. A 77, 032322 (2008). doi:10.1103/PhysRevA.77.032322.
- [Gri98] M. Grifoni, P. Hänggi, *Driven quantum tunneling*, Physics Reports **304**, 299 (1998). doi:10.1016/S0370-1573(98)00022-2.
- [Cre03] C. E. Creffield, Location of crossings in the Floquet spectrum of a driven two-level system, Phys. Rev. B 67, 165301 (2003). doi:10.1103/PhysRevB.67.165301.
- [Gar03] Gardineer and Zoller, *Quantum Noise* (Springer, 2004).
- [Bre02] H.-P. Breuer and F. Petruccione, *The Theory of Open Quantum Systems* (Oxford, 2002).
- [Coh92] C. Cohen-Tannoudji, J. Dupont-Roc, G. Grynberg, Atom-Photon Interactions: Basic Processes and Applications, (Wiley, 1992).
- [WBC11] C. Wood, J. Biamonte, D. G. Cory, *Tensor networks and graphical calculus for open quantum systems*. arXiv:1111.6950
- [dAless08] D. d'Alessandro, Introduction to Quantum Control and Dynamics, (Chapman & Hall/CRC, 2008)
- [Kha05] N. Khaneja, T. Reiss, C. Kehlet, T. Schulte-Herbruggen, and S. J. Glaser, Optimal control of coupled spin dynamics: Design of NMR pulse sequences by gradient ascent algorithms, J. Magn. Reson. 172, 296 (2005). doi:10.1016/j.jmr.2004.11.004
- [Byrd95] R. H. Byrd, P. Lu, J. Nocedal, and C. Zhu, A Limited Memory Algorithm for Bound Constrained Optimization, SIAM J. Sci. Comput. 16, 1190 (1995). doi:10.1137/0916069
- [Flo12] F. F. Floether, P. de Fouquieres, and S. G. Schirmer, *Robust quantum gates for open systems via optimal control: Markovian versus non-Markovian dynamics*, New J. Phys. 14, 073023 (2012). doi:10.1088/1367-2630/14/7/073023
- [Lloyd14] S. Lloyd and S. Montangero, *Information theoretical analysis of quantum optimal control*, Phys. Rev. Lett. **113**, 010502 (2014). doi:10.1103/PhysRevLett.113.010502
- [Doria11] P. Doria, T. Calarco & S. Montangero, Optimal Control Technique for Many-Body Quantum Dynamics, Phys. Rev. Lett. 106, 190501 (2011). doi:10.1103/PhysRevLett.106.190501

- [Caneva11] T. Caneva, T. Calarco, & S. Montangero, *Chopped random-basis quantum optimization*, Phys. Rev. A 84, 022326 (2011). doi:10.1103/PhysRevA.84.022326
- [Rach15] N. Rach, M. M. Müller, T. Calarco, and S. Montangero, Dressing the chopped-random-basis optimization: A bandwidth-limited access to the trap-free landscape, Phys. Rev. A. 92, 062343 (2015). doi:10.1103/PhysRevA.92.062343
- [DYNAMO] S. Machnes, U. Sander, S. J. Glaser, P. De Fouquieres, A. Gruslys, S. Schirmer, and T. Schulte-Herbrueggen, Comparing, Optimising and Benchmarking Quantum Control Algorithms in a Unifying Programming Framework, Phys. Rev. A. 84, 022305 (2010). arXiv:1011.4874

Python Module Index

q

qutip, 288 qutip.bloch_redfield, 229 qutip.continuous_variables,223 qutip.control.pulsegen, 282 qutip.control.pulseoptim, 269 qutip.correlation, 237 qutip.entropy, 220 qutip.essolve, 228 qutip.expect, 218 qutip.fileio,285 qutip.floquet, 231 qutip.graph, 282 qutip.ipynbtools, 287 qutip.mcsolve, 227 qutip.mesolve, 226 qutip.metrics, 221 qutip.nonmarkov.transfertensor, 268 qutip.operators, 205 qutip.orbital, 260 qutip.parallel,286 qutip.partial_transpose, 220 qutip.piqs, 249 qutip.propagator, 247 qutip.qip.algorithms.qft, 268 qutip.qip.gates,262 qutip.qip.qubits, 267 qutip.random_objects, 213 qutip.rhs_generate, 248 qutip.scattering, 248 qutip.sesolve, 225 qutip.states, 195 qutip.steadystate,244 qutip.stochastic,235 qutip.superop_reps, 217 qutip.superoperator, 216 qutip.tensor, 219 qutip.three_level_atom, 216 qutip.tomography, 261 qutip.utilities, 284 qutip.visualization, 255 qutip.wigner, 254

Index

A

about () (in module qutip), 288 add_1q_gate() (QubitCircuit method), 170 add_annotation() (Bloch method), 154 add_circuit() (QubitCircuit method), 170 add count () (Stats method), 161 add evo comp summary() (DynamicsDump method), 195 add_evo_dump() (DynamicsDump method), 195 add_gate() (QubitCircuit method), 170 add_iter_summary() (OptimDump method), 194 add_message() (Stats method), 162 add_points() (Bloch method), 154 add_section() (Stats method), 162 add_state() (QubitCircuit method), 170 add_states() (Bloch method), 154 add_timing() (Stats method), 162 add_vectors() (Bloch method), 154 adjacent_gates() (CircuitProcessor method), 171 adjacent_gates() (CircularSpinChain method), 173 adjacent_gates() (LinearSpinChain method), 173 adjacent_gates() (QubitCircuit method), 170 adjacent gates () (SpinChain method), 172 am() (in module qutip.piqs), 252 ap() (in module qutip.piqs), 252 apply_method_params() (Optimizer method), 176 apply_params() (Dynamics method), 181 apply_params() (FidelityComputer method), 185 apply_params() (Optimizer method), 176 apply_params() (PropagatorComputer method), 184 apply_params() (PulseGen method), 189 apply_params() (*TimeslotComputer method*), 188 average_gate_fidelity() (in module qutip.metrics), 223 B basis() (in module qutip.states), 195 bell_state() (in module qutip.states), 196 berkeley() (in module qutip.qip.gates), 263 Bloch (class in qutip.bloch), 153 bloch_redfield_solve() (in module

qutip.bloch_redfield), 230
bloch_redfield_tensor() (in module
 qutip.bloch_redfield), 230

bra() (in module qutip.states), 196 breadth_first_search() (in module qutip.graph), 282 brmesolve() (in module qutip.bloch_redfield), 229 build_preconditioner() (in module qutip.steadystate), 246 bures_angle() (in module qutip.metrics), 222 bures_dist() (in module qutip.metrics), 222

С

c_ops() (Dicke method), 165 calculate() (Stats method), 193 calculate_j_m() (Pim method), 166 calculate_k() (Pim method), 166 charge() (in module qutip.operators), 205 check_herm() (Qobj method), 143 check_isunitary() (Qobj method), 143 check_unitarity() (DynamicsUnitary method), 184 CircuitProcessor (class in qutip.qip.models), 171 CircularSpinChain (class in qutip.qip.models.spinchain), 173 clear() (Bloch method), 154 clear() (FidCompUnitary method), 186 clear() (FidelityComputer method), 185 clear() (Stats method), 162 clebsch() (in module qutip.utilities), 285 cnot() (in module qutip.qip.gates), 263 coefficient_matrix() (Dicke method), 165 coefficient matrix() (Pim method), 167 coherence_function_g1() module (in *qutip.correlation*), 243 coherence_function_g2() (in module qutip.correlation), 244 coherent() (in module qutip.states), 197 coherent_dm() (in module qutip.states), 197 collapse_uncoupled() (in module qutip.piqs), 253 combine_dyn_gen() (Dynamics method), 182 commutator () (in module qutip.operators), 205 compare_amps() (TSlotCompUpdateAll method), 188 composite() (in module qutip.tensor), 219 compute_evolution() (Dynamics method), 182 compute_fid_err_grad() (FidCompTraceDiff method), 187 compute_fid_err_grad() (FidCompTraceDiffApprox method), 187

compute_fid_grad() (FidCompUnitary method), 186 concurrence () (in module qutip.entropy), 220 configure() (HEOMSolver method), 156 configure() (HSolverDL method), 157 conj() (Qobj method), 143 controlled_gate() (in module qutip.qip.gates), 266 convert_unit() (in module qutip.utilities), 285 copy () (*Qobj method*), 143 correlation() (in module qutip.correlation), 237 correlation_2op_1t() module (in qutip.correlation), 238 correlation_2op_2t() (in module qutip.correlation), 238 correlation_3op_1t() (in module qutip.correlation), 239 correlation_3op_2t() module (in *qutip.correlation*), 240 correlation_4op_1t() (in module qutip.correlation), 240 correlation_4op_2t() module (in qutip.correlation), 241 correlation_matrix() (in module qutip.continuous_variables), 223 correlation_matrix_field() (in module qutip.continuous variables), 224 correlation_matrix_quadrature() (in module qutip.continuous_variables), 224 correlation_ss() (in module qutip.correlation), 237 cosm() (Qobj method), 143 module covariance_matrix() (in qutip.continuous_variables), 223 cphase() (in module qutip.qip.gates), 262 create() (in module qutip.operators), 205 create_dump_dir() (Dump method), 193 create_new_stats() (*HEOMSolver method*), 157 (in module create_pulse_gen() qutip.control.pulsegen), 282 create_pulse_optimizer() (in module qutip.control.pulseoptim), 274 csign() (in module qutip.qip.gates), 263 css() (in module qutip.piqs), 250 Cubic_Spline (class in qutip.interpolate), 155 D

dag() (*Qobj method*), 143 destroy() (in module qutip.operators), 206 diag() (Qobj method), 143 Dicke (class in qutip.piqs), 164 dicke() (in module qutip.piqs), 250 dicke_basis() (in module qutip.piqs), 253 dispersive_gate_correction() (DispersivecQED method), 174 DispersivecQED (class in qutip.qip.models.cged), 174

displace() (in module qutip.operators), 206 Distribution (class in qutip. distributions), 168 dnorm() (Qobj method), 143 dual_chan() (Qobj method), 143 Dump (class in qutip.control.dump), 193 dump_all() (DynamicsDump property), 195 dump_all() (OptimDump property), 194 dump any () (DynamicsDump property), 195 dump_any() (OptimDump property), 194 dump_current() (TimeslotComputer method), 188 dumping() (Dynamics property), 182 dumping() (Optimizer property), 176 DumpItem (class in qutip.control.dump), 195 DumpSummaryItem (class in qutip.control.dump), 195 dyn_gen() (Dynamics property), 182 dyn_gen_phase() (Dynamics property), 182 dyn_gen_phase() (DynamicsSymplectic property), 184 Dynamics (class in qutip.control.dynamics), 179 DynamicsDump (class in qutip.control.dump), 194 DynamicsGenMat (class in qutip.control.dynamics), 183 DynamicsSymplectic (class in qutip.control.dynamics), 184 DynamicsUnitary (class in

qutip.control.dynamics), 183

Ε

eigenenergies () (Qobj method), 143 eigenstates() (Qobj method), 144 eliminate_states() (*Qobj method*), 144 enr_destroy() (in module qutip.operators), 207 enr_fock() (in module qutip.states), 199 enr_identity() (in module qutip.operators), 207 enr_state_dictionaries() (in module qutip.states), 198 enr_thermal_dm() (in module qutip.states), 198 entropy_conditional() (in module *qutip.entropy*), 220 entropy_linear() (in module qutip.entropy), 220 entropy_mutual() (in module qutip.entropy), 221 entropy_vn() (in module qutip.entropy), 221 eseries (class in qutip), 152 essolve() (in module qutip.essolve), 228 estimate num coeffs() (PulseGenCrab method), 191 evaluate() (Qobj static method), 145 EvoCompDumpItem (class in qutip.control.dump), 195 excited() (in module qutip.piqs), 251 expect () (in module qutip.expect), 218 expm() (Qobj method), 145 extract_states() (Qobj method), 145

F

fid_err_func_wrapper() (Optimizer method), 176

fid_err_grad_wrapper() (Optimizer method), gate_expand_3toN() (in module qutip.gip.gates), 176 FidCompTraceDiff (class in qutip.control.fidcomp), 187 FidCompTraceDiffApprox (class in qutip.control.fidcomp), 187 FidCompUnitary (class in qutip.control.fidcomp), 186 fidelity() (in module qutip.metrics), 221 FidelityComputer (class qutip.control.fidcomp), 185 file_data_read() (in module qutip.fileio), 285 file_data_store() (in module qutip.fileio), 285 flag_system_changed() (Dynamics method), 182 flag_system_changed() (*FidCompUnitary* method), 186 flag_system_changed() (FidelityComputer *method*), 186 floquet_basis_transform() (in module qutip.floquet), 235 floquet_markov_mesolve() module (in qutip.floquet), 235 floquet_master_equation_rates() (in module qutip.floquet), 234 floquet_master_equation_steadystate() (in module qutip.floquet), 235 floquet modes () (in module qutip.floquet), 232 floquet_modes_t() (in module qutip.floquet), 232 floquet_modes_t_lookup() (in module qutip.floquet), 233 floquet_modes_table() (in module qutip.floquet), 232 floquet_state_decomposition() (in module qutip.floquet), 234 floquet_states() (in module qutip.floquet), 233 floquet_states_t() (in module qutip.floquet), 233 floquet_wavefunction() module (in *qutip.floquet*), 233 floquet_wavefunction_t() (in module qutip.floquet), 234 fmmesolve() (in module qutip.floquet), 231 fock () (in module qutip.states), 199 fock_dm() (in module qutip.states), 199 fredkin() (in module qutip.gip.gates), 265 fsesolve() (in module qutip.floquet), 234 full() (Qobj method), 146 full_evo() (Dynamics property), 182 fwd_evo() (Dynamics property), 182

G

Gate (class in qutip.qip.circuit), 169 gate_expand_ltoN() (in module qutip.qip.gates), 267

gate_expand_2toN() (in module qutip.qip.gates), 267

267 gate_sequence_product() (in module qutip.qip.gates), 267 gen_pulse() (PulseGen method), 189 gen_pulse() (PulseGenCrabFourier method), 191 gen_pulse() (PulseGenGaussian method), 190 qen pulse() (PulseGenGaussianEdge method), 191 in gen_pulse() (PulseGenLinear method), 189 gen_pulse() (PulseGenRandom method), 189 gen_pulse() (PulseGenSaw method), 190 gen_pulse() (PulseGenSine method), 190 gen_pulse() (PulseGenSquare method), 190 gen_pulse() (PulseGenTriangle method), 190 gen_pulse() (PulseGenZero method), 189 get_ctrl_dyn_gen() (Dynamics method), 182 get_drift_dim() (Dynamics method), 182 get_dyn_gen() (Dynamics method), 182 get_fid_err() (FidCompTraceDiff method), 187 get_fid_err() (FidCompUnitary method), 186 get_fid_err() (FidelityComputer method), 186 get_fid_err_gradient() (FidCompTraceDiff *method*), 187 get_fid_err_gradient() (FidCompUnitary *method*), 186 get fid err gradient() (FidelityComputer method), 186 get_fidelity() (FidCompUnitary method), 186 get_fidelity_prenorm() (*FidCompUnitary method*), 186 get_num_ctrls() (Dynamics method), 182 get_ops_and_u() (CircuitProcessor method), 171 get_ops_and_u() (DispersivecQED method), 174 get_ops_and_u() (SpinChain method), 173 get_ops_labels() (CircuitProcessor method), 171 get_ops_labels() (CircularSpinChain method), 173 get_ops_labels() (DispersivecQED method), 174 get_ops_labels() (LinearSpinChain method), 173 get_optim_var_vals() (PulseGenCrab *method*), 191 get_timeslot_for_fidelity_calc() (TSlotCompUpdateAll method), 188 ghz() (in module qutip.piqs), 250 ghz_state() (in module qutip.states), 200 globalphase() (in module qutip.qip.gates), 266 graph_degree() (in module qutip.graph), 283 ground() (in module qutip.piqs), 251

groundstate() (Qobj method), 146

Н

hadamard_transform() (in module qutip.qip.gates), 266

HarmonicOscillatorProbabilityFunction (class in qutip.distributions), 169

HarmonicOscillatorWaveFunction (class in qutip.distributions), 169

HEOMSolver (class in qutip.nonmarkov.heom), 156 hilbert_dist() (in module qutip.metrics), 223 hinton() (in module qutip.visualization), 255 HSolverDL (class in qutip.nonmarkov.heom), 157

I

identity() (in module qutip.operators), 209 init_coeffs() (PulseGenCrab method), 191 init_comp() (FidCompTraceDiff method), 187 init comp() (FidCompUnitary method), 186 init_comp() (FidelityComputer method), 186 init_freqs() (PulseGenCrabFourier method), 192 init_normalization() (FidCompUnitary *method*), 186 init_optim() (Optimizer method), 176 init_optim() (OptimizerCrab method), 178 init_optim() (OptimizerLBFGSB method), 177 init_pulse() (PulseGen method), 189 init_pulse() (PulseGenCrab method), 191 init_pulse() (PulseGenCrabFourier method), 192 init pulse() (PulseGenLinear method), 189 init_pulse() (PulseGenPeriodic method), 190 init_timeslots() (Dynamics method), 182 initialize_controls() (Dynamics method), 182 (DynamicsUnitary initialize_controls() *method*), 184 isdiagonal() (in module qutip.piqs), 251 isdicke() (Pim method), 167 iswap() (in module qutip.qip.gates), 264

J

jmat() (in module qutip.operators), 207
jspin() (in module qutip.piqs), 249

K

ket() (in module qutip.states), 200
ket2dm() (in module qutip.states), 201

L

level() (Dump property), 193				
lindblad_dissipator()	(in	module		
qutip.superoperator), 21	7			
lindbladian() (Dicke method	l), 165			
LinearSpinChain	(class	in		
qutip.qip.models.spinchain), 173				
<pre>linspace_with() (in module qutip.utilities), 284</pre>				
liouvillian() (Dicke method), 165				
<pre>liouvillian() (in module qutip.superoperator),</pre>				
216				
<pre>load_circuit() (CircuitProce</pre>	essor meth	od), 172		
<pre>load_circuit() (Dispersivec)</pre>	QED metho	od), 174		

load_circuit() (SpinChain method), 173

logarithmic_negativity() (in module qutip.continuous_variables), 225

Μ

m_degeneracy() (in module qutip.piqs), 252

- make_sphere() (Bloch method), 154
- marginal() (Distribution method), 168
- matrix_element() (Qobj method), 146
- matrix_histogram() (in module
 qutip.visualization), 255
- matrix_histogram_complex() (in module
 qutip.visualization), 256

maximally_mixed_dm() (in module qutip.states),
200

- mcsolve() (in module qutip.mcsolve), 227
 MemoryCascade (class in
 qutip.nonmarkov.memorycascade), 157
 mesolve() (in module qutip.mesolve), 226
- momentum() (in module qutip.operators), 209

Ν

- num_dicke_states() (in module qutip.piqs), 251
 num_tls() (in module qutip.piqs), 251

0

ode2es() (in module qui	tip.essolve), 229					
onto_evo() (Dynamics	property), 183					
onwd_evo() (Dynamics	property), 183					
operator_to_vector	() (<i>in</i>	module				
qutip.superopera	tor), 216					
opt_pulse_crab()	(in	module				
qutip.control.pulseoptim), 277						
opt_pulse_crab_uni	tary() (<i>in</i>	module				
qutip.control.pulseoptim), 279						
OptimDump (class in quti	p.control.dump),	, 193				
OptimIterSummary	(class	in				
qutip.control.optimizer), 178						
<pre>optimize_circuit()</pre>	(CircuitProcess	or method),				
172						
<pre>optimize_circuit()</pre>	(DispersivecQE	ED method),				
174						
<pre>optimize_circuit()</pre>	(SpinChain met	hod), 173				

optimize_pulse() (in module qutip.control.pulseoptim), 269

Optimizer (class in qutip.control.optimizer), 174

OptimizerBFGS (*class in qutip.control.optimizer*), 177

- OptimizerCrab (*class in qutip.control.optimizer*), 177
- OptimizerCrabFmin (class in qutip.control.optimizer), 178
- OptimizerLBFGSB (class in qutip.control.optimizer), 177
- OptimResult (*class in qutip.control.optimresult*), 179

Options (class in qutip.solver), 160

- orbital() (in module qutip.orbital), 260
- outfieldcorr() (MemoryCascade method), 158
- overlap() (Qobj method), 147

Ρ

parallel_map() (in module qutip.ipynbtools), 288 parallel map() (in module qutip.parallel), 286 parfor() (in module qutip.ipynbtools), 287 parfor() (in module qutip.parallel), 286 partial_transpose() (in module qutip.partial_transpose), 220 permute() (Qobj method), 147 phase() (in module qutip.operators), 209 phase_application() (Dynamics property), 183 phase_basis() (in module qutip.states), 201 phasegate() (in module qutip.qip.gates), 262 Pim (class in qutip.piqs), 166 pisolve() (Dicke method), 165 (in module plot_energy_levels() qutip.visualization), 256 plot_expectation_values() (in module *qutip.visualization*), 259 plot_fock_distribution() (in module qutip.visualization), 257 plot_pulses() (CircuitProcessor method), 172 plot_qubism() (in module qutip.visualization), 259 plot_schmidt() (in module qutip.visualization), 258 plot spin distribution 2d() (in module qutip.visualization), 260 plot_spin_distribution_3d() (in module qutip.visualization), 260 plot_wigner() (in module qutip.visualization), 258 plot_wigner_fock_distribution() (in module qutip.visualization), 257 position() (in module qutip.operators), 209 process_fidelity() (in module qutip.metrics), 223 proj() (*Qobj method*), 147 project () (Distribution method), 168

projection()(<i>in module</i>)2
prop() (Dynamics property)		
prop_grad() (<i>Dynamics</i> p	roperty), 183	
propagator() (<i>in module</i>	qutip.propagato	or), 247
propagator() (<i>MemoryCa</i>	ascade method),	159
propagator_steadysta	te() (<i>in</i>	module
qutip.propagator), 2	247	
PropagatorComputer	(class	in
qutip.control.propce	omp), 184	
propagators()(<i>QubitCir</i>	cuit method), 17	71
PropCompApproxGrad	(class	in
qutip.control.propce		
PropCompDiag (class in	qutip.control.pr	ropcomp),
185		
PropCompFrechet	(class	in
qutip.control.propce	omp), 185	
ptrace() (<i>Qobj method</i>), 1	47	
pulse_matrix()(<i>Circuit</i>	Processor metho	od), 172
PulseGen (class in qutip.co.	ntrol.pulsegen),	188
PulseGenCrab(<i>class in qu</i>	tip.control.pulse	egen), 191
PulseGenCrabFourier	(class	in
qutip.control.pulseg	en), 191	
PulseGenGaussian	(class	in
qutip.control.pulseg	en), 190	
PulseGenGaussianEdge	(class	in
qutip.control.pulseg	en), 190	
PulseGenLinear (<i>class i</i>	1 qutip.control.p	oulsegen),
189		
PulseGenPeriodic	(class	in
qutip.control.pulseg	en), 190	
PulseGenRandom (<i>class in</i>	ı qutip.control.p	oulsegen),
189		> 100
PulseGenSaw (class in quti		
PulseGenSine (<i>class in qu</i>		
PulseGenSquare (<i>class in</i> 190	1 qutip.control.p	oulsegen),
PulseGenTriangle	(class	in
qutip.control.pulseg	en), 190	
PulseGenZero (<i>class in qu</i>	tip.control.pulse	egen), 189
Q		
qdiags() (<i>in module qutip</i> .	operators), 209	
QDistribution (<i>class in g</i>		ns). 169
		10), 10)

- qeye() (in module qutip.operators), 208
- qft() (in module qutip.qip.algorithms.qft), 268

- qfunc() (in module qutip.wigner), 254
- gload() (in module qutip.fileio), 286
- Qobj (class in qutip), 141
- QobjEvo (class in qutip), 150
- qpt() (in module qutip.tomography), 261
- qpt_plot() (in module qutip.tomography), 261
- qpt_plot_combined() (in module
 qutip.tomography), 261
- qsave() (in module qutip.fileio), 286

qubit_states() (in module qutip.qip.qubits), 267 QubitCircuit (class in qutip.qip.circuit), 169 qutip (module), 288 qutip.bloch_redfield(module), 229 qutip.continuous_variables (module), 223 qutip.control.pulsegen (module), 282 qutip.control.pulseoptim(module), 269 gutip.correlation (module), 237 qutip.entropy (module), 220 qutip.essolve (module), 228 qutip.expect (module), 218 qutip.fileio (module), 285 qutip.floquet (module), 231 qutip.graph (module), 282 qutip.ipynbtools (module), 287 qutip.mcsolve (module), 227 qutip.mesolve (module), 226 qutip.metrics (module), 221 qutip.nonmarkov.transfertensor (module), 268 qutip.operators (module), 205 qutip.orbital (module), 260 qutip.parallel (module), 286 qutip.partial_transpose (module), 220 qutip.piqs (module), 249 qutip.propagator(module), 247 gutip.gip.algorithms.gft (module), 268 qutip.gip.gates (module), 262 qutip.qip.qubits (module), 267 qutip.random_objects (module), 213 qutip.rhs_generate (module), 248 qutip.scattering (module), 248 qutip.sesolve (module), 225 qutip.states (module), 195 qutip.steadystate(module), 244 qutip.stochastic(module), 235 qutip.superop_reps (module), 217 qutip.superoperator (module), 216 qutip.tensor (module), 219 qutip.three_level_atom (module), 216 qutip.tomography (module), 261 qutip.utilities (module), 284 qutip.visualization (module), 255 qutip.wigner (module), 254 qutrit_basis() (in module qutip.states), 202 qutrit_ops() (in module qutip.operators), 210 gzero() (in module qutip.operators), 210

R

rand_dm() (in module qutip.random_objects), 213
rand_dm_ginibre() (in module
 qutip.random_objects), 213
rand_dm_hs() (in module qutip.random_objects),
 214
rand_herm() (in module qutip.random_objects),
 214
rand_ket() (in module qutip.random_objects), 214

rand_ket_haar() (in module qutip.random_objects), 214 rand_super() (in module qutip.random_objects), 215 rand_super_bcsz() (in module qutip.random_objects), 215 module rand unitary() (in qutip.random objects), 215 rand_unitary_haar() module (in qutip.random_objects), 215 recompute_evolution() (TSlotCompUpdateAll *method*), 188 refresh_drift_attribs() (Dynamics method), 183 remove_gate() (QubitCircuit method), 171 render() (Bloch method), 155 report () (Stats method), 162, 193 reset() (FidCompTraceDiff method), 187 reset() (FidCompTraceDiffApprox method), 187 reset() (FidCompUnitary method), 187 reset() (FidelityComputer method), 186 reset() (HEOMSolver method), 157 reset() (HSolverDL method), 157 reset() (PropagatorComputer method), 184 reset() (PropCompApproxGrad method), 184 reset() (PropCompDiag method), 185 reset() (PropCompFrechet method), 185 reset() (PulseGen method), 189 reset() (PulseGenCrab method), 191 reset() (PulseGenCrabFourier method), 192 reset() (PulseGenGaussian method), 190 reset() (PulseGenGaussianEdge method), 191 reset() (PulseGenLinear method), 189 reset() (PulseGenPeriodic method), 190 reset() (PulseGenRandom method), 189 resolve_gates() (QubitCircuit method), 171 Result (class in qutip.solver), 161 reverse_circuit() (QubitCircuit method), 171 reverse_cuthill_mckee() module (in qutip.graph), 283 rhot () (MemoryCascade method), 159 rhs_clear() (in module qutip.rhs_generate), 248 rhs_generate() (in module qutip.rhs_generate), 248 rotation() (in module qutip.qip.gates), 266 run() (CircuitProcessor method), 172 run() (HSolverDL method), 157 run_optimization() (Optimizer method), 176 run_optimization() (OptimizerBFGS method), 177 (OptimizerCrabFmin run_optimization() *method*), 178 (OptimizerLBFGSB run_optimization() method), 177 run_state() (CircuitProcessor method), 172 rx() (in module qutip.qip.gates), 262 ry() (in module qutip.qip.gates), 262 rz() (in module qutip.qip.gates), 262

S

save() (Bloch method), 155 save amps() (Dynamics method), 183 scattering_probability() module (in qutip.scattering), 249 serial_map() (in module qutip.parallel), 287 sesolve() (in module qutip.sesolve), 225 set_label_convention() (Bloch method), 155 set_optim_var_vals() (PulseGenCrab method), 191 set_phase_option() (FidCompUnitary method), 187 set_total_time() (Stats method), 162 show() (Bloch method), 155 sigmam() (in module qutip.operators), 210 sigmap() (in module qutip.operators), 210 sigmax() (in module qutip.operators), 211 sigmay() (in module qutip.operators), 211 sigmaz() (in module gutip.operators), 211 simdiag() (in module qutip), 288 singlet_state() (in module qutip.states), 202 sinm() (Qobj method), 148 smepdpsolve() (in module qutip.stochastic), 236 smesolve() (in module qutip.stochastic), 235 snot() (in module qutip.gip.gates), 262 solve() (Pim method), 167 spec() (eseries method), 153 spectrum() (in module qutip.correlation), 242 spectrum_correlation_fft() (in module qutip.correlation), 243 spectrum_pi() (in module qutip.correlation), 243 spectrum_ss() (in module qutip.correlation), 242 sphereplot () (in module qutip.visualization), 258 spin algebra() (in module gutip.pigs), 252 spin_coherent() (in module qutip.states), 202 spin_Jm() (in module qutip.operators), 212 spin_Jp() (in module qutip.operators), 212 spin Jx() (in module qutip.operators), 211 spin_Jy() (in module qutip.operators), 211 spin_Jz() (in module qutip.operators), 212 spin_q_function() (in module qutip.wigner), 254 spin_state() (in module qutip.states), 202 spin_wigner() (in module qutip.wigner), 254 SpinChain (class in qutip.qip.models.spinchain), 172 spost() (in module qutip.superoperator), 217 spre() (in module qutip.superoperator), 217 sprepost() (in module qutip.superoperator), 217 sqrtiswap() (in module qutip.gip.gates), 265 sqrtm() (Qobj method), 148 sqrtnot() (in module qutip.qip.gates), 262 sqrtswap() (in module qutip.gip.gates), 265 squeeze() (in module qutip.operators), 212 squeezing() (in module qutip.operators), 212 ssepdpsolve() (in module qutip.stochastic), 236 ssesolve() (in module gutip.stochastic), 235 state_degeneracy() (in module qutip.piqs), 252

state_index_number() (in module qutip.states), 203 module state_number_enumerate() (in qutip.states), 202 state_number_index() (in module qutip.states), 203 state_number_qobj() (in module qutip.states), 204 Stats (class in qutip.control.stats), 192 Stats (class in qutip.solver), 161 steadystate() (in module qutip.steadystate), 244 StochasticSolverOptions (class in qutip.stochastic), 163 super_tensor() (in module qutip.tensor), 219 superradiant() (in module qutip.piqs), 250 swap() (in module qutip.gip.gates), 264 swapalpha() (in module qutip.gip.gates), 264

Т

tau1() (Pim method), 167 tau2() (Pim method), 167 tau3() (Pim method), 167 tau4() (Pim method), 167 tau5() (Pim method), 167 tau6() (Pim method), 167 tau7 () (Pim method), 167 tau8() (Pim method), 167 tau9() (Pim method), 167 tau_valid() (Pim method), 167 temporal_basis_vector() module (in qutip.scattering), 248 temporal_scattered_state() (in module qutip.scattering), 248 tensor() (in module qutip.tensor), 219 tensor_contract() (in module qutip.tensor), 219 TerminationConditions (class in qutip.control.termcond), 178 thermal_dm() (in module qutip.states), 204 three_level_basis() (in module qutip.three_level_atom), 216 three_level_ops() module (in qutip.three_level_atom), 216 tidyup() (eseries method), 153 tidyup() (Qobj method), 148 TimeslotComputer (class in qutip.control.tslotcomp), 188 to choi() (in module qutip. superop reps), 217 to_kraus() (in module qutip.superop_reps), 218 to_super() (in module qutip.superop_reps), 218 toffoli() (in module qutip.qip.gates), 265 tr() (Qobj method), 148 tracedist() (in module qutip.metrics), 222 trans() (Qobj method), 149 transform() (Qobj method), 149 trunc_neg() (Qobj method), 149 TSlotCompUpdateAll (class in qutip.control.tslotcomp), 188

ttmsolve()	(in	module			
qutip.nonmarkov.transfertensor), 268					
TTMSolverOptions	s (class	in	ı		
qutip.nonmarkov.transfertensor), 159					
<pre>tunneling() (in module qutip.operators), 213</pre>					
TwoModeQuadratur	eCorrelation	(class in	ı		
qutip.distribu	tions), 169				

U

unit() (Qobj method), 149 unitarity_check() (Dynamics method), 183 update() (HarmonicOscillatorProbabilityFunction method), 169 (HarmonicOscillatorWaveFunction update() method), 169 update() (TwoModeQuadratureCorrelation method), 169 update_ctrl_amps() (Dynamics method), 183 update_fid_err_log() (OptimDump method), 194 update_grad_log() (OptimDump method), 194 update_grad_norm_log() (OptimDump method), 194 update_psi() (TwoModeQuadratureCorrelation method), 169 (TwoModeQuadratureCorrelation update_rho() method), 169

V

W

```
weighted_bipartite_matching() (in module
    qutip.graph), 284
wigner() (in module qutip.wigner), 254
wigner_covariance_matrix() (in module
    qutip.continuous_variables), 224
WignerDistribution (class in
    qutip.distributions), 169
writeout() (DynamicsDump method), 195
writeout() (EvoCompDumpItem method), 195
writeout() (OptimDump method), 194
```

Ζ

zero_ket() (in module qutip.states), 205